


Network Topology



Router 1

```
Router0
Physical Config CLI Attributes
IOS Command Line Interface

--- System Configuration Dialog ---

Would you like to enter the initial configuration dialog? [yes/no]: n

Press RETURN to get started!

Router>en
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int se2/0
Router(config-if)#ip add 192.168.10.97 255.255.255.224
Router(config-if)#clock rate 64000
Router(config-if)#no shut


Router(config-if)#
%LINK-5-CHANGED: Interface Serial2/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up

Router(config-if)#int fa0/0
Router(config-if)#ip add 192.168.10.35 255.255.255.224
Router(config-if)#no shut

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#exi
Router(config)#router rip
Router(config-router)#network 192.168.10.32
Router(config-router)#network 192.168.10.96
Router(config-router)#
```

Router 2



```
Router1
Physical Config CLI Attributes
IOS Command Line Interface

Router>en
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int se2/0
Router(config-if)#ip add 192.168.10.98 255.255.255.224
Router(config-if)#no shut

%LINK-5-CHANGED: Interface Serial2/0, changed state to down
Router(config-if)#
Router(config-if)#exi
Router(config)#
Router(config)#int fa0/0
Router(config-if)#ip add 192.168.10.35 255.255.255.224
Router(config-if)#no shut


Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#exi
Router(config)#
%LINK-5-CHANGED: Interface Serial2/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up

Router(config)#router rip
Router(config-router)#network 192.168.10.64
Router(config-router)#network 192.168.10.96
Router(config-router)#exi
Router(config)#
Router(config)#int fa0/0
Router(config-if)#ip add 192.168.10.67 255.255.255.224
Router(config-if)#no shut
Router(config-if)#exi
Router(config)#
```



PC3

Physical Config Desktop Programming Attributes

IP Configuration

Interface: FastEthernet0

IP Configuration

☐ DHCP ☒ Static

IPv4 Address: 192.168.10.66

Subnet Mask: 255.255.255.224

Default Gateway: 192.168.10.67

DNS Server: 0.0.0.0

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address: /

Link Local Address: FE80::201:C7FF:FE2D:DD81

Default Gateway:

DNS Server:


802.1X

☐ Use 802.1X Security

Authentication: MDS

Username:

Password:



PC1

Physical Config Desktop Programming Attributes

IP Configuration

Interface: FastEthernet0

IP Configuration

☐ DHCP ☒ Static

IPv4 Address: 192.168.10.34

Subnet Mask: 255.255.255.224

Default Gateway: 192.168.10.35

DNS Server: 0.0.0.0

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address: /

Link Local Address: FE80::20D:80FF:FE09:12A5

Default Gateway:

DNS Server:

802.1X

☐ Use 802.1X Security

Authentication: MDS

Username:

Password:

PC0

Physical Config Desktop Programming Attributes

IP Configuration

Interface FastEthernet0

IP Configuration

☐ DHCP ☒ Static

IPv4 Address 192.168.10.33

Subnet Mask 255.255.255.224

Default Gateway 192.168.10.35

DNS Server 0.0.0.0

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address /

Link Local Address FE80::2E0:F7FF:FE00:A83

Default Gateway

DNS Server

802.1X

☐ Use 802.1X Security

Authentication MD5

Username

Password

☐ Top

PC2

Physical Config Desktop Programming Attributes

IP Configuration

Interface FastEthernet0

IP Configuration

☐ DHCP ☒ Static

IPv4 Address 192.168.10.65

Subnet Mask 255.255.255.224

Default Gateway 192.168.10.67

DNS Server 0.0.0.0

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address /

Link Local Address FE80::20A:41FF:FE3A:5C9A

Default Gateway

DNS Server

802.1X

☐ Use 802.1X Security

Authentication MD5

Username

Password

☐ Top

PDU List Window									
Fire	Last Status	Source	Destination	Type	Color	Time(sec)	Periodic	Num	Edit
	Failed	PC0	PC2	ICMP		0.000	N	0	(edit)
	Successful	PC0	PC2	ICMP		0.000	N	1	(edit)
	Failed	PC1	PC3	ICMP		0.000	N	2	(edit)
	Successful	PC1	PC3	ICMP		0.000	N	3	(edit)
	Successful	PC0	PC3	ICMP		0.000	N	4	(edit)
	Successful	PC2	PC1	ICMP		0.000	N	5	(edit)