

ROUTER

ROUTER con0 is now available

Press RETURN to get started.

User Access Verification

Username: shakthi

Password:

ROUTER>en

ROUTER>line vty 0 4

^
% Invalid input detected at '^' marker.

ROUTER#config

Configuring from terminal, memory, or network [terminal]?
Enter configuration commands, one per line. End with CNTL/Z.

ROUTER(config)#line vty 0 4

ROUTER(config-line)#transport input telnet

ROUTER(config-line)#password telnet

ROUTER(config-line)#login local

ROUTER(config-line)#exit

ROUTER(config)#

ROUTER

3, changed state to down

ROUTER#config t

Enter configuration commands, one per line. End with CNTL/Z.

ROUTER(config)#interface ethernet 0/0

ROUTER(config-if)#ip address 50.0.0.0 255.0.0.1

Bad mask 0xFF000001 for address 50.0.0.0

ROUTER(config-if)#ip address 50.0.0.1 255.0.0.0

ROUTER(config-if)#no shutdown

^
% Invalid input detected at '^' marker.

ROUTER(config-if)#no shut

ROUTER(config-if)#exit

ROUTER(config)#exit

*Aug 19 14:52:54.532: %SYS-5-CONFIG_I: Configured from console by console

ROUTER#show ip int brief

Interface	IP-Address	OK?	Method	Status	Protocol
Ethernet0/0	50.0.0.1	YES	manual	up	up
Ethernet0/1	unassigned	YES	TFTP	down	down
Ethernet0/2	unassigned	YES	TFTP	down	down
Ethernet0/3	unassigned	YES	TFTP	down	down

ROUTER#config t

Enter configuration commands, one per line. End with CNTL/Z.

ROUTER(config)#username shakthi password 12345

ROUTER(config)#line console 0

ROUTER(config-line)#password shakthi

ROUTER(config-line)#login local

ROUTER(config-line)#exit

ROUTER(config)#exit

ROUTER#

*Aug 19 14:55:52.332: %SYS-5-CONFIG_I: Configured from console by console

ROUTER#enable secret shakthi

^
% Invalid input detected at '^' marker.

ROUTER#config t

Enter configuration commands, one per line. End with CNTL/Z.

ROUTER(config)#enable secret shakthi

ROUTER(config)#exit

ROUTER#ex

*Aug 19 14:58:02.258: %SYS-5-CONFIG_I: Configured from console by console

ROUTER#exit