TFTP Configuration Backup Lab – Cisco Packet Tracer

What is TFTP (Trivial File Transfer Protocol) is a simple protocol used to transfer files between routers, switches, and servers. It does not provide encryption or authentication by default, so files are transferred without encryption

TFTP Configuration Backup Lab And Rstore

In this lab, I will back up the running configuration of a Cisco 2911 router to a TFTP server using Cisco Packet Tracer. I will enable the TFTP service on the server and use the copy running-config tftp: command on the router to transfer the configuration file. Finally, I will verify that the backup file, named R1-backup, appears on the TFTP server.

To save a backup of the router's running configuration on a TFTP server.

1. Devices

- Cisco Router 2911
- Server-PT
- Switch (if required to connect multiple devices)

2. IP Configuration

- Router IP Address: 192.168.1.1
- Server IP Address: 192.168.1.2
- Subnet Mask: 255.255.255.0

3. Enable TFTP Service

Open the Server → Services → TFTP → Turn the TFTP service ON.

4. Router Command

Open the router CLI and execute the following command:

copy running-config tftp:

Enter the TFTP server's IP address:

192.168.1.2

Enter the destination filename:

R1-backup

5. Verification

Open Server → Services → TFTP and verify that the R1-backup file appears in the file list.


Result


The router's running configuration was successfully backed up to the TFTP server.


Learning Outcome


Learned how to use TFTP to back up a Cisco router's running configuration. TFTP can also be used to transfer IOS images between network devices and a TFTP server

Takes Simple Network Just Practice Store and Restore Router Back on TFTP Server




Physical
Config
CLI
Attributes
IOS Command Line Interface
Router(config)#interface gigabitEthernet 0/0
Router(config-if)#ip address 192.168.1.1 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#end
%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed state to up
Router#
%SYS-5-CONFIG_I: Configured from console by console
Router#
Router#
Router#show ip int bri
Interface IP-Address OK? Method Status Protocol
GigabitEthernet0/0 192.168.1.1 YES manual up up
GigabitEthernet0/1 unassigned YES unset administratively down down
GigabitEthernet0/2 unassigned YES unset administratively down down
Vlan1 unassigned YES unset administratively down down
Router#
Router#
Router#ping 192.168.1.2
Copy
Paste


Router0
Physical
Config
CLI
Attributes
IOS Command Line Interface
Router#ping 192.168.1.2
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 192.168.1.2, timeout is 2 seconds:
.!!!!
Success rate is 80 percent (4/5), round-trip min/avg/max = 0/0/0 ms
Router#
Router#
Router#ping 192.168.1.2
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 192.168.1.2, timeout is 2 seconds:
!!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 0/0/0 ms
Router#
Router#copy running-config tftp:
Address or name of remote host []? 192.168.1.2
Destination filename [Router-confg]? R1-Backup
Writing running-config...!!
[OK - 706 bytes]
706 bytes copied in 0 secs
Copy
Paste


Server0
Physical
Config
Services
Desktop
Programming
Attributes
SERVICES
HTTP
DHCP
DHCPv6
TFTP
DNS
SYSLOG
AAA
NTP
EMAIL
FTP
TFTP
Service
On
Off
File
R1-Backup
asa842-k8.bin
asa923-k8.bin
c1841-advipservicesk9-mz.124-15.T1.bin