

```

DRAWGBK(1, RGB(0, 0, 0)),layer7;
{=====}
MID := MA(CLOSE,26),DRAWNULL,COLORWHITE;
partline(MID, 1, RGB(0, 66, 99)),LAYER5,LINETHICK1;
{=====}
{*****}

```

```

{=====}
{===== 系统ZKQK =====}
{=====}
{----- QK -----}
QK := SMA(C,3,1);
QD := SMA(QK,3,1);
QJ := 3*QK-2*QD;
{----- ZK -----}
ZK := SMA(C,7,1);
ZD := SMA(ZK,3,1);
ZJ := 3*ZK-2*ZD;
ZH := 5*ZK-4*ZD;
{----- 划线 -----}
partline(ZK, 1, RGB(0, 0, 40)),LAYER6,LINETHICK4;
partline((ZK+ZD)/2,1, RGB(0, 0, 50)),LAYER6,LINETHICK2;
partline(ZD, 1, RGB(0, 0, 60)),LAYER6,LINETHICK1;
{-----}
partline(QK, 1, RGB(80, 100, 100)),LAYER4;
partline(ZH, 1, RGB(30, 0, 0)),LAYER5,LINETHICK2;
partline(QJ, 1, RGB(30, 0, 0)),LAYER5;
{----- 立柱 -----}
STICKLINE( QK>=ZK, ZK, QK, 5, 0),COLOR22227B,LAYER7;
STICKLINE( QK< ZK, ZK, QK, 5, 0),COLOR005B22,LAYER7;
{=====}
{*****}

```

```

{=====}
{===== 系统FQK =====}
{=====}
{----- FQK -----}
FQKM := EMA(QK,3);
FQKMMM := EMA(EMA(EMA(CLOSE,3),3),3,3);
{----- 划线 -----}
PARTLINE(FQKM, 1, RGB(0, 222, 0)),LAYER2,linethick1;
PARTLINE(FQKMMM, 1, RGB(205, 149, 12)),LAYER4,linethick2;
{----- 信号 -----}
DRAWICON(cross(FQKM,FQKMMM), FQKMMM,12), ALIGN1,VALIGN0,LAYER6,COLORRED;
DRAWICON(cross(FQKMMM,FQKM), FQKMMM,13), ALIGN1,VALIGN2,LAYER6,COLORGREEN;
{=====}

```

```
{*****}
```

```
{=====}  
{===== 乾坤阴阳 =====}  
{=====}  
IFS(FQKM >= FQKMMMM, '阳, '), DRAWNULL, COLORred;  
IFS(FQKM < FQKMMMM, '阴, '), DRAWNULL, COLORgray;  
  
IFS(FQKM - FQKMMMM >= ref(FQKM - FQKMMMM,1), '增, '减'), DRAWNULL, COLORwhite;  
  
Vfqk : 100*(FQKM - FQKMMMM)/MAX(C,1)  
,DRAWNULL,COLORYELLOW;  
{=====}  
{=====}  
IFS((QJ>ZH AND QK<ZK) AND (QJ>=QK), '青龙关注, '), DRAWNULL, COLORCYAN;  
IFS((QJ>ZH AND QK<ZK) AND (QJ< QK), '玄龙勿动, '), DRAWNULL, COLORGRAY;  
{-----}  
IFS((QJ>ZH AND QK>=ZK), '朱雀拿牢, '), DRAWNULL, COLORRED;  
{-----}  
IFS((QJ<=ZH AND QK>ZK) AND (QJ>=QK), '白虎减仓, '), DRAWNULL, COLORWHITE;  
IFS((QJ<=ZH AND QK>ZK) AND (QJ< QK), '玄虎清仓, '), DRAWNULL, COLORGRAY;  
{-----}  
IFS((QJ<=ZH AND QK<=ZK), '玄武勿动, '), DRAWNULL, COLORGRAY;  
{=====}  
{*****}
```

```
{=====}  
{===== 赋值 =====}  
{=====}  
C,DRAWNULL, COLORwhite;  
{=====}  
  
{=====}  
bH: 100*(C-ZH)/ZH,DRAWNULL,COLORAAAAAA;  
bC: 100*(C-QK)/QK,DRAWNULL,COLORAAAAAA;  
bM: 100*(C-MID)/MID,DRAWNULL,COLORAAAAAA;  
{----- QJ-ZH -----}  
QJZH : 100*(QJ - ZH)/MAX(C,1)  
,DRAWNULL,COLORYELLOW;
```

QJQK : 100*(QJ - QK)/MAX(C,1)
,DRAWNULL,COLORYELLOW;

QKZK : 100*(QK - ZK)/MAX(C,1)
,DRAWNULL,COLORYELLOW;

```
{=====}  
{  
龙 : QJ>ZH AND QK<=ZK, DRAWNULL, COLORCYAN;  
雀 : QJ>ZH AND QK>ZK, DRAWNULL, COLORRED;  
虎 : QJ<ZH AND QK>ZK, DRAWNULL, COLORWHITE;  
武 : QJ<ZH AND QK<ZK, DRAWNULL, COLORGRAY;  
}  
{=====}  
{*****}  
{*****}
```

```
{=====}  
{===== 选股专用 =====}  
{=====}  
{=====}  
选阳初 : QJ>ZH AND QK>ZK  
AND (REF(QJZH,1)>0 AND REF(QKZK,1)>0)=0  
, DRAWNULL,COLORRED;  
{STICKLINE(阳一, OPEN,CLOSE, 6,0),COLOR008BEE,LAYER7;}
```

```
选阳三 : count(cross(QK,ZK),3)=1 and C>=QK, DRAWNULL,COLORRED;  
{STICKLINE(阳一, OPEN,CLOSE, 6,0),COLOR008BEE,LAYER7;}  
{=====}
```

```
{以下乾坤与选天机等合并}  
{----- ZXX:地机 -----}  
选地机 :=  
(  
(QJ>ZH AND QK<=ZK)  
AND QJ>=QK  
)  
AND QJ>REF(QJ,1)  
, COLORAAAA00,DRAWNULL;  
{STICKLINE(选地机, OPEN,CLOSE, 6,0),COLORAAAA00,LAYER6;}
```

```
{----- ZXX:天机 -----}  
选天机 :  
(  
(QJ>ZH AND QK<=ZK)  
AND QJ>=QK  
)  
AND QJ>REF(QJ,1)
```

AND QJ>ZK
AND C>ZK
, COLORCYAN,DRAWNULL;

{STICKLINE(选天机, OPEN,CLOSE, 6,0),COLORCYAN,LAYER6;}

{=====}

{=====}

鼎：

(QJ>ZH AND QK>ZK)
AND OPEN<QK AND C>QK
AND C>ZH*0.97
,DRAWNULL,COLORRED;

{=====}

{*****}