

Router(config)#exit Router#copy run start

Router#copy run start Router#config t

Router 2: Router>en

Router#config t

Router(config)#interface f0/0

Router(config-if)#ip address 172.16.3.1 255.255.255.0

Router(config)#ip route 172.16.3.0 255.255.255.0 172.16.2.1 Router(config)#ip route 192.168.2.0 255.255.255.0 192.168.1.1

Router(config-if)#no shut

Router(config-if)#interface s2/0

Router(config-if)#clock rate 64000

Router(config-if)#ip address 172.16.2.1 255.255.255.0

Router(config-if)#no shut

Router(config-if)#exit

Router(config)#exit

Router#copy run start

Router#config t

Router(config)#ip route 172.16.1.0 255.255.255.0 172.16.2.2

Router(config)#ip route 192.168.1.0 255.255.255.0 172.16.2.2

Router(config)#ip route 192.168.2.0 255.255.255.0 172.16.2.2

Router(config)#exit

Router#copy run start

Router 3:

Router>en

Router#config t

Router(config)#interface f0/0

Router(config-if)#ip address 192.168.2.1 255.255.255.0

Router(config-if)#no shut

Router(config-if)#interface s2/0

Router(config-if)#ip address 192.168.1.1 255.255.255.0

Router(config-if)#no shut

Router(config-if)#exit

Router(config)#exit

Router#copy run start

Router#config t

Router(config)#ip route 172.16.1.0 255.255.255.0 192.168.1.2

Router(config)#ip route 172.16.2.0 255.255.255.0 192.168.1.2

Router(config)#ip route 172.16.3.0 255.255.255.0 192.168.1.2

Router(config)#exit

Router#copy run start

Dynamic Routing (RIP):

Router 1:

Router#config t

Router(config)#no ip route 172.16.3.0 255.255.255.0 172.16.2.1

Router(config)#no ip route 192.168.2.0 255.255.255.0 192.168.1.1

Router(config)#router rip

Router(config-router)#network 172.16.2.0

Router(config-router)#network 172.16.1.0

Router(config-router)#network 192.168.1.0

Router(config-router)#exit

Router(config)#exit

Router#copy run start

Router 2:

Router>en

Router#config t

Router(config)#no ip route 172.16.1.0 255.255.255.0 172.16.2.2

Router(config)#no ip route 192.168.1.0 255.255.255.0 172.16.2.2

Router(config)#no ip route 192.168.2.0 255.255.255.0 172.16.2.2

Router(config)#router rip

Router(config-router)#network 172.16.3.0

Router(config-router)#network 172.16.2.2

Router(config-router)#exit

Router(config)#exit

Router#copy run start

Router 3:

Router#config t

Router(config)#no ip route 172.16.1.0 255.255.255.0 192.168.1.2

Router(config)#no ip route 172.16.2.0 255.255.255.0 192.168.1.2

Router(config)#no ip route 172.16.3.0 255.255.255.0 192.168.1.2

Router(config)#router rip

Router(config-router)#network 172.16.3.0

Router(config-router)#network 192.168.1.0

Router(config-router)#network 192.168.2.0

Router(config-router)#exit

Router(config)#exit

Router#copy run start