

To **block (disable) any driver in Linux**, the standard method is to **blacklist the module** so it does not load automatically. This works for drivers like **UAS**, **usb-storage**, network drivers, GPU drivers, etc.

Here's the correct way step-by-step 📌

```
[root@localhost ~]#  
[root@localhost ~]# lsmod | grep usb  
usb_storage      81920  0  
btusb            65536  0  
btrtl            28672  1 btusb  
btbcm            20480  1 btusb  
btintel          49152  1 btusb  
btmtk            16384  1 btusb  
bluetooth        937984  13 btrtl,btmtk,btintel,btbcm,bnep,btusb  
[root@localhost ~]#  
[root@localhost ~]#
```

✅ Method 1 — Permanently block a driver (recommended way)

Step 1: Create blacklist file

vi /etc/modprobe.d/blacklist-driver.conf


```
[root@localhost ~]# vi /etc/modprobe.d/blacklist-driver.conf  
[root@localhost ~]#  
[root@localhost ~]#  
[root@localhost ~]#
```

Add this line:

Example (block UAS driver):

```
# blacklist uas_storage
```

Save and exit.



Step 2: Rebuild initramfs

Required on most systems:

```
# sudo dracut -f
```

```
[root@localhost ~]#  
[root@localhost ~]#  
[root@localhost ~]# # sudo dracut -f
```

Step 3: Reboot system

```
# reboot
```

Now the driver will not load automatically 

Verify driver is blocked

Check loaded modules:

```
# lsmod | grep driver_name
```

```
[root@localhost ~]#  
[root@localhost ~]# lsmod | grep usb  
btusb                65536  0  
btrtl                28672  1 btusb  
btbcm                20480  1 btusb  
btintel              49152  1 btusb  
btmtk                16384  1 btusb  
bluetooth            937984 13 btrtl,btmtk,btintel,btbcm,bnep,btusb  
[root@localhost ~]#
```

in **production/industry environments**, rebooting is often **not allowed**, so instead of rebooting after blacklist changes, you can **apply driver block/unblock changes dynamically (live)**.

Here are the correct no-reboot methods

✓ Method 2— Prevent driver from loading again (without reboot)

Since you already created:

```
# /etc/modprobe.d/blacklist-driver.conf
```

That prevents **future loads**, but current session still has driver loaded.

So remove it now:

```
# rmmod driver_name
```

Example:

```
# rmmod usb_storage
```

```
[root@localhost ~]#  
[root@localhost ~]#  
[root@localhost ~]# # sudo dracut -f  
[root@localhost ~]# lsmod | grep usb  
usb_storage      81920  0  
btusb            65536  0  
btrtl            28672  1 btusb  
btbcm            20480  1 btusb  
btintel          49152  1 btusb  
btmtk            16384  1 btusb  
bluetooth        937984  13 btrtl,btmtk,btintel,btbcm,bnep,btusb  
[root@localhost ~]#  
[root@localhost ~]# rmmod usb_storage  
[root@localhost ~]#  
[root@localhost ~]#  
[root@localhost ~]# lsmod | grep usb  
btusb            65536  0  
btrtl            28672  1 btusb  
btbcm            20480  1 btusb  
btintel          49152  1 btusb  
btmtk            16384  1 btusb  
bluetooth        937984  13 btrtl,btmtk,btintel,btbcm,bnep,btusb  
[root@localhost ~]#
```