Objects , Variables and Types

22 March 2026
10:39

Types - Blueprints
Objects - Structured data

Everything we see on the screen are the objects- the output we get of every command are treated as an objects.
Example



Example - AUDI car
1. Color : silver
2. Mileage - 20km/l
3. Speed : 200km/s
4. Cc: 600cc

MARUTI car
1. Color : white
2. Mileage : 60km/l
3. Speed - 200 km/s
4. cc: 800cc

For both the cars the **methods are same** what changes is the properties
Every objects has specific Methods and Properties
OBJETCS = MEHTODS + PROPERTIES

Examples
("this is test string").gettype() or "this is string".gettype()

```
PS C:\Users\lenovo> ("this is the test string").gettype()

IsPublic IsSerial Name                                     BaseType
-------- -------- ----                                     --------
True     True     String                                   System.Object
```

It explains that this string (name) is derived from the Objects (Basetype)
Note - if we see any type like string, integer, boolean, these are derived always from the objects(basetype)

To use the boolean we use **$** symbol
Example
($true).gettype()

```
PS C:\Users\lenovo> $true.gettype()

IsPublic IsSerial Name                                     BaseType
-------- -------- ----                                     --------
True     True     Boolean                                  System.ValueType
```

To prove the ValueType is an object we use this command
($true).gettype().basetype.basetype
or
$true.gettype().basetype

```
PS C:\Users\lenovo> $true.gettype().basetype. basetype

IsPublic IsSerial Name                                     BaseType
-------- -------- ----                                     --------
True     True     Object


PS C:\Users\lenovo> $true.gettype().basetype

IsPublic IsSerial Name                                     BaseType
-------- -------- ----                                     --------
True     True     ValueType                                System.Object
```

To check the Available Members in the list

2 Methods
1. Get-member -inputobject (" ") : we get multiple system.strings
   Example:

```
PS C:\Users\lenovo> get-member -inputobject ("")


   TypeName: System.String

Name             MemberType            Definition
----             ----------            ----------
Clone            Method                System.Object Clone(), System.Object ICloneable.Clone()
CompareTo        Method                int CompareTo(System.Object value), int CompareTo(string strB), int IComparable.CompareTo(System.Object obj), int IComparable[string].CompareTo(strin...
Contains         Method                bool Contains(string value)
CopyTo           Method                void CopyTo(int sourceIndex, char[] destination, int destinationIndex, int count)
EndsWith         Method                bool EndsWith(string value), bool EndsWith(string value, System.StringComparison comparisonType), bool EndsWith(string value, bool ignoreCase, cultur...
Equals           Method                bool Equals(System.Object obj), bool Equals(string value), bool Equals(string value, System.StringComparison comparisonType), bool IEquatable[string]...
GetEnumerator    Method                System.CharEnumerator GetEnumerator(), System.Collections.IEnumerator IEnumerable.GetEnumerator(), System.Collections.Generic.IEnumerator[char] IEnum...
GetHashCode      Method                int GetHashCode()
GetType          Method                type GetType()
GetTypeCode      Method                System.TypeCode GetTypeCode(), System.TypeCode IConvertible.GetTypeCode()
IndexOf          Method                int IndexOf(char value), int IndexOf(char value, int startIndex), int IndexOf(string value), int IndexOf(string value, int startIndex), int IndexOf(s...
IndexOfAny       Method                int IndexOfAny(char[] anyOf), int IndexOfAny(char[] anyOf, int startIndex), int IndexOfAny(char[] anyOf, int startIndex, int count)
Insert           Method                string Insert(int startIndex, string value)
IsNormalized     Method                bool IsNormalized(), bool IsNormalized(System.Text.NormalizationForm normalizationForm)
LastIndexOf      Method                int LastIndexOf(char value), int LastIndexOf(char value, int startIndex), int LastIndexOf(string value), int LastIndexOf(string value, int startIndex...
LastIndexOfAny   Method                int LastIndexOfAny(char[] anyOf), int LastIndexOfAny(char[] anyOf, int startIndex), int LastIndexOfAny(char[] anyOf, int startIndex, int count)
Normalize        Method                string Normalize(), string Normalize(System.Text.NormalizationForm normalizationForm)
PadLeft          Method                string PadLeft(int totalWidth), string PadLeft(int totalWidth, char paddingChar)
PadRight         Method                string PadRight(int totalWidth), string PadRight(int totalWidth, char paddingChar)
Remove           Method                string Remove(int startIndex, int count), string Remove(int startIndex)
Replace          Method                string Replace(char oldChar, char newChar), string Replace(string oldValue, string newValue)
Split            Method                string[] Split(Params char[] separator), string[] Split(char[] separator, int count), string[] Split(char[] separator, System.StringSplitOptions opti...
StartsWith       Method                bool StartsWith(string value), bool StartsWith(string value, System.StringComparison comparisonType), bool StartsWith(string value, bool ignoreCase, ...
Substring        Method                string Substring(int startIndex), string Substring(int startIndex, int length)
ToBoolean        Method                bool IConvertible.ToBoolean(System.IFormatProvider provider)
ToByte           Method                byte IConvertible.ToByte(System.IFormatProvider provider)
ToChar           Method                char IConvertible.ToChar(System.IFormatProvider provider)
ToCharArray      Method                char[] ToCharArray(), char[] ToCharArray(int startIndex, int length)
ToDateTime       Method                datetime IConvertible.ToDateTime(System.IFormatProvider provider)
ToDecimal        Method                decimal IConvertible.ToDecimal(System.IFormatProvider provider)
ToDouble         Method                double IConvertible.ToDouble(System.IFormatProvider provider)
ToInt16          Method                int16 IConvertible.ToInt16(System.IFormatProvider provider)
ToInt32          Method                int IConvertible.ToInt32(System.IFormatProvider provider)
ToInt64          Method                long IConvertible.ToInt64(System.IFormatProvider provider)
ToLower          Method                string ToLower(), string ToLower(cultureinfo culture)
ToLowerInvariant Method                string ToLowerInvariant()
ToSByte          Method                sbyte IConvertible.ToSByte(System.IFormatProvider provider)
ToSingle         Method                float IConvertible.ToSingle(System.IFormatProvider provider)
ToString         Method                string ToString(), string ToString(System.IFormatProvider provider), string IConvertible.ToString(System.IFormatProvider provider)
ToType           Method                System.Object IConvertible.ToType(type conversionType, System.IFormatProvider provider)
ToUInt16         Method                uint16 IConvertible.ToUInt16(System.IFormatProvider provider)
ToUInt32         Method                uint32 IConvertible.ToUInt32(System.IFormatProvider provider)
```

Among this we can use any type

"this is what ".length : it Is used to display length of string

"this is string".toupper() : display string in upper characters

```
PS C:\Users\lenovo> "this is me".toupper()
THIS IS ME
PS C:\Users\lenovo> "this is me". length
10
```

2. Pipe Line symbol - provide properties of any type
   ("") | get-member
   ($true) | get-member

```
PS C:\Users\lenovo> ("") | get-member


   TypeName: System.String

Name             MemberType            Definition
----             ----------            ----------
Clone            Method                System.Object Clone(), System.Object ICloneable.Clone()
CompareTo        Method                int CompareTo(System.Object value), int CompareTo(string strB), int IComparable.CompareTo(System.Obj
Contains         Method                bool Contains(string value)
CopyTo           Method                void CopyTo(int sourceIndex, char[] destination, int destinationIndex, int count)
EndsWith         Method                bool EndsWith(string value), bool EndsWith(string value, System.StringComparison comparisonType), b
Equals           Method                bool Equals(System.Object obj), bool Equals(string value), bool Equals(string value, System.StringC
GetEnumerator    Method                System.CharEnumerator GetEnumerator(), System.Collections.IEnumerator IEnumerable.GetEnumerator(),
GetHashCode      Method                int GetHashCode()
GetType          Method                type GetType()
GetTypeCode      Method                System.TypeCode GetTypeCode(), System.TypeCode IConvertible.GetTypeCode()
IndexOf          Method                int IndexOf(char value), int IndexOf(char value, int startIndex), int IndexOf(string value), int In
IndexOfAny       Method                int IndexOfAny(char[] anyOf), int IndexOfAny(char[] anyOf, int startIndex), int IndexOfAny(char[] a
Insert           Method                string Insert(int startIndex, string value)
IsNormalized     Method                bool IsNormalized(), bool IsNormalized(System.Text.NormalizationForm normalizationForm)
LastIndexOf      Method                int LastIndexOf(char value), int LastIndexOf(char value, int startIndex), int LastIndexOf(string va
LastIndexOfAny   Method                int LastIndexOfAny(char[] anyOf), int LastIndexOfAny(char[] anyOf, int startIndex), int LastIndexOf
Normalize        Method                string Normalize(), string Normalize(System.Text.NormalizationForm normalizationForm)
PadLeft          Method                string PadLeft(int totalWidth), string PadLeft(int totalWidth, char paddingChar)
PadRight         Method                string PadRight(int totalWidth), string PadRight(int totalWidth, char paddingChar)
Remove           Method                string Remove(int startIndex, int count), string Remove(int startIndex)
Replace          Method                string Replace(char oldChar, char newChar), string Replace(string oldValue, string newValue)
Split            Method                string[] Split(Params char[] separator), string[] Split(char[] separator, int count), string[] Spli
StartsWith       Method                bool StartsWith(string value), bool StartsWith(string value, System.StringComparison comparisonType
Substring        Method                string Substring(int startIndex), string Substring(int startIndex, int length)
ToBoolean        Method                bool IConvertible.ToBoolean(System.IFormatProvider provider)
ToByte           Method                byte IConvertible.ToByte(System.IFormatProvider provider)
ToChar           Method                char IConvertible.ToChar(System.IFormatProvider provider)
ToCharArray      Method                char[] ToCharArray(), char[] ToCharArray(int startIndex, int length)
ToDateTime       Method                datetime IConvertible.ToDateTime(System.IFormatProvider provider)
ToDecimal        Method                decimal IConvertible.ToDecimal(System.IFormatProvider provider)
ToDouble         Method                double IConvertible.ToDouble(System.IFormatProvider provider)
ToInt16          Method                int16 IConvertible.ToInt16(System.IFormatProvider provider)
ToInt32          Method                int IConvertible.ToInt32(System.IFormatProvider provider)
ToInt64          Method                long IConvertible.ToInt64(System.IFormatProvider provider)
ToLower          Method                string ToLower(), string ToLower(cultureinfo culture)
ToLowerInvariant Method                string ToLowerInvariant()
ToSByte          Method                sbyte IConvertible.ToSByte(System.IFormatProvider provider)
ToSingle         Method                float IConvertible.ToSingle(System.IFormatProvider provider)
ToString         Method                string ToString(), string ToString(System.IFormatProvider provider), string IConvertible.ToString(S
ToType           Method                System.Object IConvertible.ToType(type conversionType, System.IFormatProvider provider)
ToUInt16         Method                uint16 IConvertible.ToUInt16(System.IFormatProvider provider)
```

Type here to search

Variables

Variable is a memory allocated to value which can be reused anytime.

```
PS C:\Users\lenovo> $name = "Shreya"
PS C:\Users\lenovo> $name
Shreya
```

2 types

1. **Built - in variable** : the variable build already in system
   $home , $host
2. **User -defined variable :** the variable created by user and not saved when we turn off the powershell
   $name, $shd

```
PS C:\Users\lenovo> $host


Name             : ConsoleHost
Version          : 5.1.19041.6456
InstanceId       : 7945f692-5a4f-4f20-82e8-4d98cdd635f1
UI               : System.Management.Automation.Internal.Host.InternalHostUserInterface
CurrentCulture   : en-IN
CurrentUICulture : en-US
PrivateData      : Microsoft.PowerShell.ConsoleHost+ConsoleColorProxy
DebuggerEnabled  : True
IsRunspacePushed : False
Runspace         : System.Management.Automation.Runspaces.LocalRunspace
```

Syntax to create a variable
$name = "Vivaan" : to create a variable $name
$name : to display output of variable

To print a variable on a console - we need to use **write-host**
Write-host " Welcome to Powershell "

```
PS C:\Users\lenovo> write-host "this is powershell"
this is powershell
```

Example of mathematical Operations
Example 1
$a =2
$b =9
$a + $b
Example 2
$a =2
$b =9
$c = $a+$b
Write-host "a+b = " $c

```
this is powershell
PS C:\Users\lenovo> $a =2
PS C:\Users\lenovo> $b=9
PS C:\Users\lenovo> write-host "a+b =" $a+$b
a+b = 2+9
PS C:\Users\lenovo> $c = $a+$b
PS C:\Users\lenovo> $c
11
PS C:\Users\lenovo> write-host "a+b =" $c
a+b = 11
```

Note - Variable can be reassigned
$a =2 it can be reassigned and used as $a =10

To check the type of variable : **gettype()**
$a.gettype()
Where name is Int32 and its basetype is System.object

```
PS C:\Users\lenovo> $a.gettype()

IsPublic IsSerial Name                                     BaseType
-------- -------- ----                                     --------
True     True     Int32                                    System.ValueType
```

$a = "abc" : type is string(used to check $a.gettype())
$a = $false (boolean Type)

Another way To Declare Variable
Command **- New- variable - name "test" -value "Hello Powershell"**
To check - **$test**
Remove the Variable **: Remove-variable -name "test"**
To check - **$test** : no variable exist

```
PS C:\Users\lenovo> new-variable -name "test" -value "helo powershell"
PS C:\Users\lenovo> $test
helo powershell
PS C:\Users\lenovo> remove-variable -name "test"
PS C:\Users\lenovo> $test
PS C:\Users\lenovo>
```

Read Only Variable
The variable created only for read purpose not to write/change the value
New-variable -name "test" -value "hello" -option readonly
Now if we change the value of $test then we face the error
$test = "Hill" : Get Error

```
PS C:\Users\lenovo> new-variable -name "test" -value "helo powershell"
PS C:\Users\lenovo> $test
helo powershell
PS C:\Users\lenovo> remove-variable -name "test"
PS C:\Users\lenovo> $test
```

```
PS C:\Users\lenovo> new-variable -name "th" -value "hi" -option readonly
PS C:\Users\lenovo> $th="hhhhhhhhi"
Cannot overwrite variable th because it is read-only or constant.
At line:1 char:1
+ $th="hhhhhhhhi"
+ ~~~~~~~~~~~~~~~~
    + CategoryInfo          : WriteError: (th:String) [], SessionStateUnauthorizedAccessExce
    + FullyQualifiedErrorId : VariableNotWritable
```

The error we get is we cannot overwrite a variable as it is ready only or constant.
We even cannot remove the variable nor set the variable if It is readonly

```
PS C:\Users\lenovo> remove-variable -name "th"
remove-variable : Cannot remove variable th because it is constant or read-only. If the variable is read-only, try the operation again spec
At line:1 char:1
+ remove-variable -name "th"
+ ~~~~~~~~~~~~~~~~~~~~~~~~~~
    + CategoryInfo          : WriteError: (th:String) [Remove-Variable], SessionStateUnauthorizedAccessException
    + FullyQualifiedErrorId : VariableNotRemovable,Microsoft.PowerShell.Commands.RemoveVariableCommand

PS C:\Users\lenovo> set-variable -name "th" -value "new"
set-variable : Cannot overwrite variable th because it is read-only or constant.
At line:1 char:1
+ set-variable -name "th" -value "new"
+ ~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~
    + CategoryInfo          : WriteError: (th:String) [Set-Variable], SessionStateUnauthorizedAccessException
    + FullyQualifiedErrorId : VariableNotWritable,Microsoft.PowerShell.Commands.SetVariableCommand
```

Set- Variables

Set Variables are used to change the value of variable
It is also used to create a value which doesn't exist
We need to remove "readonly" tag from the command to make changes in the "th" variable
Command : **Set -variable -name "th" -value "New Value Added" -force**

```
PS C:\Users\lenovo> set-variable -name "th" -value "new value addded" -force
PS C:\Users\lenovo> $th
new value addded
```

Constant Variables

The command to create a constant variable : **Set-variable -name "test" -value "Hoo hoo" -option constant**
To check **: $test** - error
We cannot set the constant variable but we can create it using new variable
Note: the constant variable cannot be set but can be created using new-variable command

```
PS C:\Users\lenovo> new-variable -name "text" -value "hey" -option constant
PS C:\Users\lenovo> $text
hey
PS C:\Users\lenovo> set-variable -name "text" -value "hoo" -option constant
set-variable : Cannot overwrite variable text because it is read-only or constant.
At line:1 char:1
+ set-variable -name "text" -value "hoo" -option constant
+ ~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~
    + CategoryInfo          : WriteError: (text:String) [Set-Variable], SessionStateUnauthorizedAccessException
    + FullyQualifiedErrorId : VariableNotWritable,Microsoft.PowerShell.Commands.SetVariableCommand
```

If we use force then also we cannot set the constant variable nor removed until the PowerShell is turned off(shutdown)

```
PS C:\Users\lenovo> set-variable -name "text" -value "hoo" -force
set-variable : Cannot overwrite variable text because it is read-only or constant.
At line:1 char:1
+ set-variable -name "text" -value "hoo" -force
+ ~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~
    + CategoryInfo          : WriteError: (text:String) [Set-Variable], SessionStateUnauthorizedAccessException
    + FullyQualifiedErrorId : VariableNotWritable,Microsoft.PowerShell.Commands.SetVariableCommand
```

New-Variable is "strict." If the variable is already there, it will throw an error (unless you use -Force). Use this when you want to ensure you aren't accidentally overwriting something.
Set-Variable is "flexible." It doesn't care if the variable exists or not—it will either create it or update it without complaining.

```
PS C:\Users\lenovo> remove-variable -name "text" -force
remove-variable : Cannot remove variable text because it is constant or read-only. If the variable is read-only, try the operation again specifying the Force
At line:1 char:1
+ remove-variable -name "text" -force
+ ~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~
    + CategoryInfo          : WriteError: (text:String) [Remove-Variable], SessionStateUnauthorizedAccessException
    + FullyQualifiedErrorId : VariableNotRemovable,Microsoft.PowerShell.Commands.RemoveVariableCommand
```

The command stored in variable

$a = get-service
The output of get-service is stored in $a

```
PS C:\Users\lenovo> $a =get-service
PS C:\Users\lenovo> $a

Status   Name               DisplayName
------   ----               -----------
Stopped  AarSvc_35e2470     Agent Activation Runtime_35e2470
Running  AdobeARMservice    Adobe Acrobat Update Service
Stopped  AJRouter           AllJoyn Router Service
Stopped  ALG                Application Layer Gateway Service
Stopped  AppIDSvc           Application Identity
Running  Appinfo            Application Information
Stopped  AppMgmt            Application Management
Stopped  AppReadiness       App Readiness
Stopped  AppVClient         Microsoft App-V Client
Running  AppXSvc            AppX Deployment Service (AppXSVC)
Stopped  AssignedAccessM... AssignedAccessManager Service
Running  AudioEndpointBu... Windows Audio Endpoint Builder
Running  Audiosrv           Windows Audio
Stopped  autotimesvc        Cellular Time
Stopped  AxInstSV           ActiveX Installer (AxInstSV)
Stopped  BcastDVRUserSer... GameDVR and Broadcast User Service_...
Stopped  BDESVC             BitLocker Drive Encryption Service
Running  BFE                Base Filtering Engine
Stopped  BITS               Background Intelligent Transfer Ser...
Stopped  BluetoothUserSe... Bluetooth User Support Service_35e2470
Running  BrokerInfrastru... Background Tasks Infrastructure Ser...
Running  BTAGService        Bluetooth Audio Gateway Service
Running  BthAvctpSvc        AVCTP service
Running  bthserv            Bluetooth Support Service
Running  camsvc             Capability Access Manager Service
Running  CaptureService_... CaptureService_35e2470
Running  cbdhsvc_35e2470    Clipboard User Service_35e2470
Running  CDPSvc             Connected Devices Platform Service
Running  CDPUserSvc_35e2470 Connected Devices Platform User Ser...
Stopped  CertPropSvc        Certificate Propagation
Stopped  ClipSVC            Client License Service (ClipSVC)
Stopped  cloudidsvc         Microsoft Cloud Identity Service
Stopped  COMSysApp          COM+ System Application
Stopped  ConsentUxUserSv... ConsentUX_35e2470
Running  CoreMessagingRe... CoreMessaging
```

Get-variable -outvariable till

Here by using outvariable we store the get service value in till variable (created without $)

```
S C:\Users\lenovo> get-service -outvariable till

tatus   Name               DisplayName
-----   ----               -----------
topped  AarSvc_35e2470     Agent Activation Runtime_35e2470
unning  AdobeARMservice    Adobe Acrobat Update Service
topped  AJRouter           AllJoyn Router Service
topped  ALG                Application Layer Gateway Service
topped  AppIDSvc           Application Identity
unning  Appinfo            Application Information
topped  AppMgmt            Application Management
topped  AppReadiness       App Readiness
topped  AppVClient         Microsoft App-V Client
unning  AppXSvc            AppX Deployment Service (AppXSVC)
topped  AssignedAccessM... AssignedAccessManager Service
unning  AudioEndpointBu... Windows Audio Endpoint Builder
unning  Audiosrv           Windows Audio
topped  autotimesvc        Cellular Time
topped  AxInstSV           ActiveX Installer (AxInstSV)
topped  BcastDVRUserSer... GameDVR and Broadcast User Service_...
topped  BDESVC             BitLocker Drive Encryption Service
unning  BFE                Base Filtering Engine
topped  BITS               Background Intelligent Transfer Ser...
topped  BluetoothUserSe... Bluetooth User Support Service_35e2470
unning  BrokerInfrastru... Background Tasks Infrastructure Ser...
unning  BTAGService        Bluetooth Audio Gateway Service
unning  BthAvctpSvc        AVCTP service
unning  bthserv            Bluetooth Support Service
unning  camsvc             Capability Access Manager Service
unning  CaptureService_... CaptureService_35e2470
unning  cbdhsvc_35e2470    Clipboard User Service_35e2470
unning  CDPSvc             Connected Devices Platform Service
unning  CDPUserSvc_35e2470 Connected Devices Platform User Ser...
topped  CertPropSvc        Certificate Propagation
topped  ClipSVC            Client License Service (ClipSVC)
topped  cloudidsvc         Microsoft Cloud Identity Service
topped  COMSysApp          COM+ System Application
topped  ConsentUxUserSv... ConsentUX_35e2470
unning  CoreMessagingRe... CoreMessaging
topped  cphs               Intel(R) Content Protection HECI Se...
topped  CredentialEnrol... CredentialEnrollmentManagerUserSvc_...
unning  CryptSvc           Cryptographic Services
topped  CscService         Offline Files
unning  DcomLaunch         DCOM Server Process Launcher
topped  dcsvc              Declared Configuration(DC) service
topped  defragsvc          Optimize drives
topped  DeviceAssociati... DeviceAssociationBroker_35e2470
unning  DeviceAssociati... Device Association Service
topped  DeviceInstall      Device Install Service
```

To get the type of variable "till"

```
PS C:\Users\lenovo> $till.gettype()

IsPublic IsSerial Name                                     BaseType
-------- -------- ----                                     --------
True     True     ArrayList                                System.Object
```

Common Data Types

int	numbers
Date	Stores date and time of system
Array	storing a collection of multiple items, accessed by an index(contigious memory)
long	Range of numbers (long numbers)
boolea	True/false
string	text
enum	value type that defines a fixed set of named integer constants, used for strong typing and code

Use a $a variable to store date and time and find the properties of it using get-member.

```
PS C:\Users\lenovo> $a =get-date
PS C:\Users\lenovo> $a

22 March 2026 13:31:50


PS C:\Users\lenovo> $a.gettype()

IsPublic IsSerial Name                                     BaseType
-------- -------- ----                                     --------
True     True     DateTime                                 System.ValueType


PS C:\Users\lenovo> $a |get-member


   TypeName: System.DateTime

Name                 MemberType     Definition
----                 ----------     ----------
Add                  Method         datetime Add(timespan value)
AddDays              Method         datetime AddDays(double value)
AddHours             Method         datetime AddHours(double value)
AddMilliseconds      Method         datetime AddMilliseconds(double value)
AddMinutes           Method         datetime AddMinutes(double value)
AddMonths            Method         datetime AddMonths(int months)
AddSeconds           Method         datetime AddSeconds(double value)
AddTicks             Method         datetime AddTicks(long value)
AddYears             Method         datetime AddYears(int value)
CompareTo            Method         int CompareTo(System.Object value), int CompareTo(datetim
Equals               Method         bool Equals(System.Object value), bool Equals(datetime va
GetDateTimeFormats   Method         string[] GetDateTimeFormats(), string[] GetDateTimeFormat
GetHashCode          Method         int GetHashCode()
GetObjectData        Method         void ISerializable.GetObjectData(System.Runtime.Serializa
GetType              Method         type GetType()
GetTypeCode          Method         System.TypeCode GetTypeCode(), System.TypeCode IConvertib
IsDaylightSavingTime Method         bool IsDaylightSavingTime()
Subtract             Method         timespan Subtract(datetime value), datetime Subtract(time
ToBinary             Method         long ToBinary()
ToBoolean            Method         bool IConvertible.ToBoolean(System.IFormatProvider provid
ToByte               Method         byte IConvertible.ToByte(System.IFormatProvider provider)
```

To use any of these properties use command
$a.property_name
example:

```
PS C:\Users\lenovo> $a.hour
13
PS C:\Users\lenovo> $a.kind
Local
PS C:\Users\lenovo> $a.month
3
PS C:\Users\lenovo> $a.second
50
```