


Server0
Physical
Config
Services
Desktop
Programming
Attributes
SERVICES
HTTP
DHCP
DHCPv6
TFTP
DNS
SYSLOG
AAA
NTP
EMAIL
FTP
IoT
VM Management
Radius EAP
PRP
DHCP
Interface
FastEthernet0
Service
On
Off
Pool Name
serverPool
Default Gateway
192.168.1.254
DNS Server
192.168.1.254
Start IP Address :
192
168
1
100
Subnet Mask:
255
255
255
0
Maximum Number of Users :
156
TFTP Server:
0.0.0.0
WLC Address:
0.0.0.0
Add
Save
Remove
Pool Name
Default Gateway
DNS Server
Start IP Address
Subnet Mask
Max User
TFTP Server
WLC Address
serverPool
192.168.1...
192.168.1...
192.168.1...
255.255.2...
156
0.0.0.0
0.0.0.0
Top
Server-PT
PC-PT PC2
PC-PT PC0
PC-PT PC1
2960-24TT Switch0
Fa0
Fa0/1
Fa0/4
Fa0/2


PC0
Physical
Config
Desktop
Programming
Attributes
IP Configuration
Interface
FastEthernet0
IP Configuration
DHCP
Static
IPv4 Address
192.168.1.100
Subnet Mask
255.255.255.0
Default Gateway
192.168.1.254
DNS Server
0.0.0.0
IPv6 Configuration
Automatic
Static
IPv6 Address
Link Local Address
FE80::240:BFF:FEA1:9C51
Default Gateway
DNS Server
802.1X
Use 802.1X Security
Authentication
MD5
Username
Password
Top
Server-PT
PC-PT PC2
PC-PT PC0
PC-PT PC1
2960-24TT Switch0
Fa0
Fa0/1
Fa0/4
Fa0/2
Realtime
Simulation
Scenario 0
New
Delete
Toggle PDU List Window
Fire
Last Status
Source
Destination
Type
Color
Time(sec)
Periodic
Num
Edit
Delete
Search for device
Attiva Windows
Passa a Impostazioni per attivare Windows.