## Message board

Based on the **Access** and **Message board owner** properties of the **Message board** web part, you can define who can add new messages to the board.



## **Changing the values**

Remember that once the message board is created (after inserting first message or subscribing), you cannot make changes to these settings in the **New board settings** section of the web part properties. You can only modify values of the **Access** property on the **Security** tab (there referred to as **Allow comments to**) when editing the corresponding message board in the **Message boards** application.

The following table explains **who can add messages to the board** under particular configurations. The difference between **User boards** and **Public boards** is that **Public boards** are always related to a page, while **User boards** are always related to a page and a user.

**Public boards** are typically used when you want multiple users to post messages to it. **User boards** are typically used on user profiles, as you can see on the sample **Community Starter site**, on the **Members -> Profile** page.

Message board owner	Access	Anonymous user	Authenticated user	Authorized role	Owner	Owner in authorized role
Public board	All users	•	•	•	•	•
Public board	Authenticated users		•	•	•	•
Public board	Authorized roles			•		•
Public board	Owner				•	•
User	All users	•	•	•	•	•
User	Authenticated users		•	•	•	•
User	Authorized roles			•		•
User	Owner				•	•

When a board is in the **User x Owner** configuration, the following conditions need to be met in order for the current user to be able to post messages:

- the page must be accessed with the userid or username parameter in the querystring
- the current user must be the same as the one whose userid or username is passed in the querystring
- the current user must not be hidden (configured by the *Is hidden* option when editing the user)

This can be typically used on user profiles, where messages to such a board can be posted only by the owner of the profile, while other users can only read these messages. An example of such a board is the **MessageBoardAnnouncements** board on the **/Members/Profile** page of the sample **Community Starter site**.

## Group message board

The Group message board is always related to a group, which means that you can specify only the **Access** property. You can see a typical usage of this web part on the sample **Community Starter site**, on the **Groups -> Profile** page.

Access	Anonymous user	Authenticated user	Authorized role	Group member	Group member in authorized role	Group admin
All users	<b>Ø</b>	•	0	<b>Ø</b>	•	•

https://docs.xperience.io

Authenticated users	•	•	•	•	•
Authorized roles		•		•	•
Group members			•	•	•
Group admin					•

When the **Group members** option is set, the following conditions need to be met in order for the current user to be able to post messages:

- the page must be accessed with the *groupid* parameter in the querystring
- the current user must be a member of the group whose *groupid* is in the querystring
- the current user must not be hidden (configured by the *Is hidden* option when editing the user)

This can be typically used on group profiles, where messages to such a board can be posted only by members of the group, while other users can only read these messages. An example of such a board is the **GroupMessageBoard** board on the **/Group-pages /<group name>** page of the sample **Community Starter site**.

## Permissions

You can set permissions for access to the **Message boards** administration interface in the **Permissions** application. You have to select the **Modules -> Message boards** permission matrix.

- Modify members of the roles can edit message board settings, delete the boards and manage message board posts.
- **Read** selected role members can read the records and configuration of particular message boards, but are not allowed to modify them.

https://docs.xperience.io 2