UNDERSTANDING KMS API CALLS - DEMO

Architecture Overview

A CLOUD GURU



Create CMK
Launch instance in the same region where CMK is created



```
[ec2-user@ip-172-31-59-8 ~]$ echo "Hello Cloud Gurus! " >secret.txt
[ec2-user@ip-172-31-59-8 ~]$ ls
secret.txt
[ec2-user@ip-172-31-59-8 ~]$ cat secret.txt
Hello Cloud Gurus!
[ec2-user@ip-172-31-59-8 ~]$
```

Plain Text file that we are going to encrypt

```
[ec2-user@ip-172-31-59-8 ~]$ aws configure
AWS Access Key ID [None]: AKIA5QFWU3GWKX6DXIXW
AWS Secret Access Key [None]: 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
Default region name [None]: us-east-1
Default output format [None]: text
[ec2-user@ip-172-31-59-8 ~]$
```

Cofigure AWS CLI

```
[ec2-user@ip-172-31-59-8 ~]$ aws kms encrypt --key-id 98400507-7f27-4bf7
-b80d-bfd80879a626 --plaintext fileb://secret.txt --output text --query
CiphertextBlob | base64 --decode > encryptedsecret.txt
[ec2-user@ip-172-31-59-8 ~]$ ls
encryptedsecret.txt  secret.txt
[ec2-user@ip-172-31-59-8 ~]$
```

Encrypt
Output – bytes format

```
[ec2-user@ip-172-31-59-8 ~]$ aws kms decrypt --ciphertext-blob fileb://e
ncryptedsecret.txt --output text --query Plaintext | base64 --decode > d
ecryptedsecret.txt
[ec2-user@ip-172-31-59-8 ~]$ ls
decryptedsecret.txt  encryptedsecret.txt  secret.txt
[ec2-user@ip-172-31-59-8 ~]$
```

Decrypt file
Output file type – ASCII text

```
[ec2-user@ip-172-31-59-8 ~]$ aws kms re-encrypt --destination-key-id 984
00507-7f27-4bf7-b80d-bfd80879a626 --ciphertext-blob fileb://encryptedsec
ret.txt | base64 > newencryption.txt
[ec2-user@ip-172-31-59-8 ~]$ ls
decryptedsecret.txt  encryptedsecret.txt  newencryption.txt  secret.txt
```

Re-encrypt takes the encrypted file and decrypt it without saving the plain text version anywhere. It decrypts and keep it in memory. Then it will re-encrypt it and save the newly encrypted file.
Useful when we want to encrypt something with different CMK.
We can re-crypt the encrypted file with different CMK id

```
[ec2-user@ip-172-31-59-8 ~]$ aws kms enable-key-rotation --key-id 984005
07-7f27-4bf7-b80d-bfd80879a626
[ec2-user@ip-172-31-59-8 ~]$ aws kms get-key-rotation-status --key-id 98
400507-7f27-4bf7-b80d-bfd80879a626
True
[ec2-user@ip-172-31-59-8 ~]$
```

Rotate key on annual key basis

Key status



Encryption and decryption on large amounts of data. It will give plain text version and cypher text version of the datakey

Exam Tips
KMS API Calls

`aws kms encrypt`

Encrypts plaintext into ciphertext by using a customer master key.

`aws kms re-encrypt`

Decrypts ciphertext and then re-encrypts it entirely within AWS KMS (e.g. when you change the CMK or manually rotate the CMK).

`aws kms decrypt`

Decrypts ciphertext that was encrypted by an AWS KMS customer master key (CMK).

`aws kms enable-key-rotation`

Enables automatic key rotation every 365 days.

Exam Tips
KMS API Calls

`aws kms generate-data-key`

Uses the CMK to generate a data key to encrypt data > 4KB.