

RETRO

Launcher

NEUTRINO

by Maximus32

POPStarter

by krHACKen

ENCELADUS

by DanielSant0s

 **RETROARCH**

Port by fjtruju

wLaunchELF

ISR mod by israpps

OPF

by Ps2homebrew Team



INDEX

What is RETROLauncher?	4
What do I need to run RETROLauncher?	4
Requirements for proper execution of RETROLauncher	4
What games can I launch with RETROLauncher?	5
List of emulators/APPS/Cores included in RETROLauncher	5
How do I use RETROLauncher?	7
RETROLauncher Controls	7
How do I add games?	9
Location of supported ROMs paths and extensions	9
How do I configure RETROLauncher?	11
Menu settings in RETROLauncher	11
Sprite configuration	12
Custom style	14
Controls for the editor	15
Restore RetroArch configurations individually	20
Deactivate wLaunchELF	20
General settings of POPStarter	20
Configure custom directory for OPL	21
Text font settings	21
Change the background	22
Static background	22
Animated background	23
Layered animated background	24
Custom APP/ELF output	26
Language	29
Reset all settings	30
How do I add covers and screenshots?	31
Image requirements	31
Image directories	31
How do I add text fonts?	33
Text font requirements	33
How do I add wallpapers?	33
Wallpaper requirements	33

How do I add sound effects?	34
Sound effects requirements	34
PlayStation 1 game settings menu	34
Prerequisites	34
POPStarter settings menu	35
Install patches for specific games	35
Install general patches	36
Install "CHEATS.TXT" file	37
Extra Settings	38
Clear game settings.....	39
Create executable for POPStarter games	39
PlayStation 2 game settings menu	39
Neutrino settings menu	39
Configure VMC (Neutrino)	40
Configure compatibility modes (Neutrino)	40
Configure GMS (Neutrino)	40
Open PS2 Loader settings menu	40
Configure VMC (OPL)	41
Configure compatibility modes (OPL)	41
Configure GMS (OPL)	41
How do I run PS2 games from MX4SIO? (Experimental)	42
How do I update the emulators and cores of RETROLauncher?.....	43
How do I run RETROLauncher from exFAT?.....	44
Files needed on the Memory Card.....	44
How to launch games through OPL?.....	44
Known Problems with RETROLauncher	45
Credits	47



RETROLAUNCHER

V1.0 / REV2

What is RETROLauncher?

RETROLauncher is a launcher with a graphical environment focused on retro games, created entirely in Lua under the Enceladus development environment, in conjunction with RetroArch, POPStarter, Neutrino, wLaunchELF ISR and OPL for running games/apps.

The main objective of creating this program is to provide a user-friendly, visually appealing, and highly customizable graphical environment for managing retro PS2 game libraries. It allows users to keep all their libraries in one place and access them easily.

RETROLauncher aims to avoid complex configurations, so settings are kept to a minimum: simply load the games and enjoy. All the settings of the applications used by RETROLauncher remain available should any advanced user wish to modify them.

What do I need to run RETROLauncher?

Requirements for proper execution of RETROLauncher:

- * Place the "RETROLauncher" folder in the root directory of your USB drive. You can also place it in other directories, although in the latter case, the first time you launch RETROLauncher, you will be asked if you want to relocate the configuration directories. Once the relocation process is complete, you will be able to use RETROLauncher in the directory you placed it in.

- * If you are going to run RETROLauncher from a USB drive formatted as "exFAT", make sure you have the corresponding drivers on your PS2 Memory Card.

- * For POPStarter (PS1) you must have the POPS folder in the root of the USB, as well as the binaries necessary for it to run ("IOPRP252.IMG" and "POPS_IOX.PAK" respect the name and capitalization), the binaries are not included with RETROLauncher for legal reasons (only POPStarter is found in the RETROLauncher files).

- * It is mandatory that no two USB drives are connected simultaneously to the PS/2 USB ports when running RETROLauncher. If RETROLauncher detects multiple drives in the USB ports, the program will not start and will require a restart, as will the case if the USB drive is in the second USB port (this is to avoid known problems in RETROLauncher when running and manipulating directories).

- * To run PS2 games from the disc drive, the disc must be inserted before launching RETROLauncher. If it is inserted after RETROLauncher has started, update the list so that the game is listed in the PS2/APPS section (once listed, a restart is required to load another DVD/CD).

Note: If you launch RETROLauncher from an application that has already loaded the DVD/CD modules, RETROLauncher may freeze when scanning the disc during startup.

- * RETROLauncher can be run from different launchers, although some require extra steps. The launchers tested were "Free MCBoot", "wLaunchELF", "FunTuna", and "OPL" (which requires extra steps).

Note: There have been reports of cases where the combination of certain console models and specific launcher versions causes RETROLauncher to fail to run. Therefore, it is not guaranteed to work 100% with all application launchers or console models.

IMPORTANT NOTE: RETROLauncher manipulates, reads, writes, and deletes its own data, so it's recommended that you don't use it alongside sensitive data. It's also very important to verify the source from which you download RETROLauncher, as being open source, it can be manipulated for malicious purposes.

YOU ARE RESPONSIBLE FOR THE USE OF RETROLAUNCHER. BACK UP YOUR DATA BEFORE USING RETROLAUNCHER AND DOWNLOAD THE PROGRAM FROM RELIABLE SOURCES.

What games can I launch with RETROLauncher?

RETROLauncher uses different versions of RetroArch, POPStarter, Neutrino, wLaunchELF ISR, and OPL. Therefore, game compatibility is limited to the specific cores, applications, and emulators used. RETROLauncher is only an application launcher; it is not an emulator (it does not improve game compatibility, it only launches games).

List of emulators/APPS/Cores included in RETROLauncher:

+ Atari 2600

RetroArch Core: "stella2014_libretro_ps2.elf" (Supports saving states)

Version: RetroArch - Version 1.20.0

+ Atari Lynk

RetroArch Core: "handy_libretro_ps2.elf" (Supports saving states)

Version: RetroArch - Version 1.21.0

+ Neo Geo Pocket

RetroArch Core: "race_libretro_ps2.elf" (Supports saving states)

Version: RetroArch - Version 1.21.2

+ Nintendo Game Boy

RetroArch Core: "gambatte_libretro_ps2.elf" (Supports saving states)

Version: RetroArch - Version 1.20.0

Alternative RetroArch Core: "tgbdual_libretro_ps2.elf" (Supports saving states)

Version: RetroArch - Version 1.19.1

+ Nintendo Game Boy Color

RetroArch Core: "gambatte_libretro_ps2.elf" (Supports saving states)

Version: RetroArch - Version 1.20.0

Alternative RetroArch Core: "tgbdual_libretro_ps2.elf" (Supports saving states)

Version: RetroArch - Version 1.19.1

+ Nintendo Game Boy Advance (Long loading times)

RetroArch Core: "gpsp_libretro_ps2.elf" (Supports saving states)

Version: RetroArch - Version 1.20.0

Alternative emulator: "TempGBA.elf" (Supports saving states)

Version: TempGBA - Version 1.45.5 - (Not compatible with "exFAT")

Note: For better game compatibility, place the GBA BIOS in the following directories:

* **Directory 1:** "USB:/RETROLauncher/System/RetroarchPS2/Nintendo Game Boy Advance/retroarch/system/"

* **Directory 2:** "USB:/RETROLauncher/System/RetroarchPS2/Nintendo Game Boy Advance/TempGBA/"

BIOS Name: "gba_bios.bin"

"USB:/RETROLauncher/System/RetroarchPS2/Nintendo Game Boy Advance/retroarch/system/gba_bios.bin"

"USB:/RETROLauncher/System/RetroarchPS2/Nintendo Game Boy Advance/TempGBA/gba_bios.bin"

+ Nintendo Famicom

RetroArch Core: "fceumm_libretro_ps2.elf" (Supports saving states)

Version: RetroArch - Version 1.19.1

Alternative RetroArch Core: "quicknes_libretro_ps2.elf" (Supports saving states)

Version: RetroArch - Version 1.21.0

+ Nintendo Super Famicom

RetroArch Core: "snes9x2002_libretro_ps2.elf" (Supports saving states)

Version: RetroArch - Version 1.20.0

Alternative emulator: "SNESticle.elf" (Not compatible with SRAM / Not compatible with PS2 Fat models)

Version: SNESticle – Version 0.3.4

Note: SNESticle will only run the emulator, it will not launch the selected games.

+ Sega Game Gear

RetroArch Core: "picodrive_libretro_ps2.elf" (Supports saving states)

Version: RetroArch - Version 1.19.1

+ Sega Master System

RetroArch Core: "picodrive_libretro_ps2.elf" (Supports saving states)

Version: RetroArch - Version 1.19.1

+ Sega Megadrive

RetroArch Core: "picodrive_libretro_ps2.elf" (Supports saving states)

Version: RetroArch - Version 1.19.1

Alternative RetroArch Core: "picodrive_libretro_ps2_alt.elf" (Better performance / Error with saving states)

Version: RetroArch - Version 1.15.0

+ Sega SG-1000

RetroArch Core: "picodrive_libretro_ps2.elf" (Supports saving states)

Version: RetroArch - Version 1.19.1

+ PlayStation 1

POPStarter: "POPSTARTER.ELF"

Version: POPSTARTER - Version 13

Note: Requires BDMAssault drivers for use with devices in exFAT.

+ PlayStation 2

Neutrino: "Neutrino.elf"

Version: Neutrino – Version 1.7.0

Alternative execution: "OPNPS2LD.elf"

Version: Open PS2 Loader v1.2.0-Beta-2223-45875da - Released 09/01/2026

Note 1: Running via OPL is only compatible with ISOs located on the USB drive.

Note 2: It is recommended that you replace the "OPNPS2LD.elf" file with the version of OPL you are using to avoid configuration conflicts.

+ Applications ELF

wLaunchELF ISR: "wLaunchELF 4.43x_isr.elf"

Version: Commit bb13043 - Released 21/08/2025

Note: If "WLE.elf" is not found when running the APPS, it will automatically be launched through Enceladus.

Alternative execution: "Enceladus.elf"

Version: Enceladus - Released 10/02/2024


How do I use RETROLauncher?

When you start RETROLauncher, it will automatically list the games and apps it finds; simply select an item from the list to launch the game or application.

RETROLauncher Controls:


- + To navigate the menu, use the "Directional Pad": "Up" and "Down" for slow movement, "Left" and "Right" for fast movement.
- + You can also use the "Left Analog Stick" in the menu: "Up" and "Down" for quick movement, "Left" and "Right" to skip to the next letter.
- + The buttons "L2" and "R2" are used to skip in the list (skip 10 titles).
- + Letter jumps are performed using the button combinations "L2" + "Up" and "R2" + "Down".
- + To switch between art types, press "△".
- + To view the Covers in full screen, press "□".
- + With the "Right Analog Stick" you can zoom in on the covers.
- + To switch systems, press "L1" or "R1".
- + To run the game, press "X".
- + To see the number of games found, press and hold "○".
- + To configure the games (on systems that allow it) hold "○" and press "△".
- + To perform alternative executions (on systems that allow it) hold "○" and press "X".
- + To view the RETROLauncher controls, hold "○" and press "L3", or enter the combination "L3 + R3".
- + If sprite movements are enabled, perform them using the "Right Analog Stick".
- + To refresh the current system list, press "R3".
- + To restart RETROLauncher, press "L3".
- + To configure RETROLauncher options, press "START".
- + To exit RETROLauncher, press "SELECT".

Note: Throughout RETROLauncher's menus, you will be constantly guided regarding the controls and the actions they perform. Depending on the menu you are in, the controls may vary and even be interchanged to prevent accidental changes.



Controls within RetroArch:

In the case of RetroArch, once the game is started, pressing the “L2 + R2” combination will open the RetroArch menu.



Once in the RetroArch menu (“QUICK MENU”), pressing “○” will return you to the RetroArch main menu (“MAIN MENU”) where you can configure RetroArch and restart it.

If you press “X” on “Restart” in the RetroArch main menu, you will return to RETROLauncher.



Note 1: Games launched with POPStarter, TempGBA, OPL, and Neutrino will not return to the RETROLauncher menu unless instructed to do so by external applications such as "Free MCBot".

Note 2: All systems save the last game launched, and the last positions of the other systems are also saved when switching between them. This ensures that everything is restored after restarting RETROLauncher.

Note 3: Adding or removing games may change the positions after restarting RETROLauncher.

How do I add games?

To add games and apps to RETROlauncher, simply copy the ROMs, ISOs, or apps to the directories corresponding to each system, respecting the file extensions supported by each system.

Location of supported ROMs paths and extensions:

Roms Atari 2600:

+ **Directory:** "USB:/RETROlauncher/Roms/Roms Atari 2600/"

+ **Supported extensions:** ".a26" ".bin" ".zip"

Example: "USB:/RETROlauncher/Roms/Roms Atari 2600/Game.a26"

Roms Atari Lynk:

+ **Directory:** "USB:/RETROlauncher/Roms/Roms Atari Lynk/"

+ **Supported extensions:** ".lnx" ".lyx" ".zip" (".o" compressed in ".zip")

Example: "USB:/RETROlauncher/Roms/Roms Atari Lynk/Game.lnx"

Roms Neo Geo Pocket:

+ **Directory:** "USB:/RETROlauncher/Roms/Roms Neo Geo Pocket/"

+ **Supported extensions:** ".ngc" ".ngp" ".zip"

Example: "USB:/RETROlauncher/Roms/Roms Neo Geo Pocket/Game.ngc"

Roms Nintendo Game Boy:

+ **Directory:** "USB:/RETROlauncher/Roms/Roms Nintendo Game Boy/"

+ **Supported extensions:** ".gb" ".zip"

Example: "USB:/RETROlauncher/Roms/Roms Nintendo Game Boy/Game.gb"

Roms Nintendo Game Boy Color:

+ **Directory:** "USB:/RETROlauncher/Roms/Roms Nintendo Game Boy Color/"

+ **Supported extensions:** ".gbc" ".zip"

Example: "USB:/RETROlauncher/Roms/Roms Nintendo Game Boy Color/Game.gbc"

Roms Nintendo Game Boy Advance:

+ **Directory:** "USB:/RETROlauncher/Roms/Roms Nintendo Game Boy Advance/"

+ **Supported extensions:** ".gba" ".bin"

Example: "USB:/RETROlauncher/Roms/Roms Nintendo Game Boy Advance/Game.gba"

Roms Nintendo Famicom:

+ **Directory:** "USB:/RETROlauncher/Roms/Roms Nintendo Famicom/"

+ **Supported extensions:** ".nes" ".fds" ".unf" ".zip"

Example: "USB:/RETROlauncher/Roms/Roms Nintendo Famicom/Game.nes"

Roms Nintendo Super Famicom:

+ **Directory:** "USB:/RETROlauncher/Roms/Roms Nintendo Super Famicom/"

+ **Supported extensions:** ".smc" ".sfc" ".zip"

Example: "USB:/RETROlauncher/Roms/Roms Nintendo Super Famicom/Game.smc"

Roms Sega Game Gear:

+ **Directory:** "USB:/RETROLauncher/Roms/Roms Sega Game Gear/"

+ **Supported extensions:** ".gg" ".zip"

Example: "USB:/RETROLauncher/Roms/Roms Sega Game Gear/Game.gg"

Roms Sega Master System:

+ **Directory:** "USB:/RETROLauncher/Roms/Roms Sega Master System/"

+ **Supported extensions:** ".sms" ".zip"

Example: "USB:/RETROLauncher/Roms/Roms Sega Master System/Game.sms"

Roms Sega Megadrive:

+ **Directory:** "USB:/RETROLauncher/Roms/Roms Sega Megadrive/"

+ **Supported extensions:** ".bin" ".gen" ".smd" ".md" ".zip"

Example: "USB:/RETROLauncher/Roms/Roms Sega Megadrive/Game.bin"

Roms Sega SG-1000:

+ **Directory:** "USB:/RETROLauncher/Roms/Roms Sega SG-1000/"

+ **Supported extensions:** ".sg" ".zip"

Example: "USB:/RETROLauncher/Roms/Roms Sega SG-1000/Game.sg"

VCDs PlayStation 1:

+ **Directory:** "USB:/POPS/"

+ **Supported extensions:** ".vcd", ".elf"

Example: "USB:/POPS/Game.vcd"

Note 1: Executable files with the ".elf" extension located within the "USB:/POPS/" folder will be listed as PlayStation 1 games. This is useful for adding POPStarter executables whose games are located on an SMB server or the internal hard drive.

Note 2: When you run a game, the executable will be searched for in the APPS folder and then in the POPS folder. If it is not found, you will be asked where to create the shortcut. If you create it in APPS, the game will be accessible in all launchers that support reading "Title.cfg".

ISOs PlayStation 2:

+ **Directory 1:** "USB:/RETROLauncher/Roms/ISOs PlayStation 2/"

+ **Directory 2:** "USB:/DVD/"

+ **Directory 3:** "USB:/CD/"

+ **Directory 4:** "CD:/" "DVD:/" PS2 games placed in the DVD/CD tray will be listed.

+ **Supported extensions:** ".iso"

Example 1: "USB:/RETROLauncher/Roms/ISOs PlayStation 2/Game.iso"

Example 2: "USB:/DVD/Game.iso"

Example 3: "USB:/CD/Game.iso"

Note 1: PlayStation 2 CDs/DVDs placed in the tray will be listed only once. If you change discs after a CD/DVD has been listed, it will not be updated and you will need to restart the console.

Note 2: If the game ID placed on the tray is found in RETROLauncher's internal dictionary, it will be translated. To add games to the dictionary, edit "USB:/RETROLauncher/System/Respaldo/PS2_IDs.cfg".

ELFs APPS:

+ **Directory 1:** "MC0:/APPS/"

+ **Directory 2:** "MC1:/APPS/"

+ **Directory 3:** "USB:/APPS/"

+ **Directory 4:** "USB:/RETROlauncher/Roms/APPS/"

+ **Directory 5:** "CD:/" "DVD:/" PS2 games and apps placed in the DVD/CD tray will be listed.

+ **Directory 6:** Any application installed on the MC or USB root via SAS (Save APP System).

+ **Supported extensions:** ".elf"

Example 1: "USB:/RETROlauncher/Roms/APPS/Application.elf"

Example 2: "USB:/APPS/Application.elf"

Note 1: RETROlauncher will search the root of the directories mentioned above, but also their subdirectories.

This means that if I place the application inside a folder within those directories, RETROlauncher will also find it and list it.

Example 1: "USB:/RETROlauncher/Roms/APPS/Subfolder/Application.elf"

Example 2: "USB:/APPS/New Folder/Application.elf"

Example 3: "MC0:/APPS/Subfolder/Application.elf"

Note 2: An attempt will be made to obtain the application name from a "Title.cfg" file if one is found.

How do I configure RETROlauncher?

To configure RETROlauncher on the home screen, press "START" to access the menu. Some settings will take effect immediately, but others need to be saved. If changes are not saved, they will be lost when RETROlauncher is restarted.

Note 1: Configurations that require the specific loading of a file will be reset to their default configuration if the files are not found after the reset.

Note 2: If you press the "L3" or "R3" buttons on the settings screen, you will see the RETROlauncher controls.

Note 3: Some settings, when applied, will kick you out of the settings menu; in these cases, any changes made that were not previously saved will be lost.

Note 4: There are settings that will not be affected by restorations; these options must be modified manually each time they are needed.

Menu settings in RETROlauncher:

Change page (page 1):



To switch between settings pages, press the shoulder buttons "L1" or "R1".

To jump between options, press the shoulder buttons "L2" or "R2".

RGB effect (page 1):



This setting enables and disables the backlight changing effect. If disabled, the colors will be fixed and will not change shade.

Note: It requires that the configuration be saved.

Color in backgrounds (page 1):



This setting controls the color layer applied to the background, turning it on and off. If the background is turned off, it will revert to its original color.

Note 1: If this option is disabled, the "RGB effect" option will also be disabled automatically.

Note 2: It requires that the configuration be saved.

Fixed color in backgrounds (page 1):



This setting assigns a default color to all elements of RETROLauncher.

The options "Red", "Green", and "Blue" correspond to the color you want to set. Both the text and the image in the center will automatically change to the selected color so you can see how it will look when applied.

+ The values are changed by placing the cursor over the color and pressing the directional buttons of the "Pad" or the "Left Analog Stick" towards the "Right" or "Left".

+ If you hold down "△", you can change the level of white that the items in the menus will have.

+ If you press and hold "□", you can change the transparency level for the menu images.

Note 1: If this option is enabled and the "Color in backgrounds" option is disabled, the configured color will not be applied to the background, leaving it in its original color.


Note 2: If the color transparency is set to "Transparency off", the color system will be applied directly onto the images (this method resulted in incorrect colors because the color red has no intermediate tones).

Note 3: If this option is activated, the "RGB effect" option will also be automatically deactivated.

Note 4: If there is no background mask, the color will be applied to the background screen.

Note 5: It requires that the configuration be saved.


List style (page 1):



This setting allows you to change the different styles available for displaying game lists; there are seven different styles in total. Six of these styles are predefined, and one allows you to edit and create custom styles; this style is called "Custom".

Note: It requires that the configuration be saved.

List style (page 1) / Sprite configuration submenu:



If we press "SELECT" on any of the predefined styles, a menu will open where we can configure the use and behavior of "Sprites" in the RETROLauncher main menu.

Note 1: If we have "Sprites" enabled in the style, we will be able to see the "Sprite" next to the style name.

Note 2: The "Sprites" have individual configurations, which means that the changes you make within the menu will only apply to the systems you edit.

Note 3: It is only possible to have one "Sprite" per system and it will always be associated with the state of the system, so if the system is deactivated the "Sprite" will not be displayed.

Note 4: It requires that the configuration be saved.



Example sprite with 12 animations, divided into 4 columns and 3 rows.
From the PlayStation 2 system, without extra animations and with fixed horizontal reflection.

Name: PlayStation2_01007_4x3.png

Sprite configuration:



Enable sprites in menu:

This option will enable or disable sprite rendering in the RETROLauncher main menu. This is the only sprite setting that does not apply to the image itself, so it requires that the RETROLauncher settings be saved to be retained.

Sprite corresponding to "system name":

Here you can switch between the different systems available to edit your corresponding sprite.

Note 1: You can also switch between systems by pressing the "**L1**" or "**R1**" buttons.

Nota 2: The default sprite names for each system must be respected; to see the names, check the file "**USB:/RETROLauncher/System/Medios/Sprites/.INFO - Sprites.txt**".

Type of animation:

In this option you can switch between the different available animations, you can see a brief description on the right side of the screen, as well as see the behavior of the sprite in real time.

Note: The sprite's position on the screen is only an example; once in the main menu, both the sprite and the animation will take their predefined position according to the style, and in the case of a custom style, they will take the position set by the user.

Animation speed:

Here you can modify the speed at which the animation runs. Some animations handle a different speed range; on the right side next to the description you can see the animation speed.

Transparencies in animation:

This option allows you to apply transparency effects to the sprite. You can configure both fixed levels and variable ranges. To the right of the settings, you'll see a brief description of the transparency level and its behavior. You can also see its effect on the sprite in real time.

Rotations in animation:

Here you can apply rotation to the sprite. The value will determine both the speed and direction of the rotation. A brief description of the rotation behavior and speed is shown on the right.

Flip sprites:

This option allows you to configure how sprite reflections will behave. A brief description of each setting's behavior can be seen on the right.


Columns:

In this option you can configure the number of columns that the image contains; it is useful for configuring a sprite for the first time as it allows you to see in real time how the image is divided.

Rows:

In this option you can configure the number of rows that the image contains; it is useful for configuring a sprite for the first time as it allows you to see in real time how the image is divided.

Set values:



Once you have the desired sprite configuration, you must set the settings to save the changes. These changes are applied to the image name, allowing the sprites to be automatically configured upon loading. After setting the configuration, you will be asked to confirm the change to the image name.


Note 1: The "Columns" and "Rows" options should only be changed if the sprite is not rendered correctly or to configure new images whose number of animations does not match their name.

Note 2: Each sprite configuration is individual, so they must be set before exiting the configuration menu; any unapplied configurations will be restored upon exiting.


Note 3: These settings can also be configured manually by changing the image name.

Note 4: If the sprite is not found, an "error" image will be displayed instead.

Custom style:




To customize the style, first place the "Custom" style in the "List style" option, then press the "SELECT" button to open the submenu, and finally select "Style editor" to access the editor.



Note: By default, the editor will load the positions and elements of the currently configured style. If you currently have a predefined style configured in this option, and you wish to edit a previously saved custom style, first place the "Custom" style in the "List style" option, then save the configuration and re-enter the RETROlauncher settings menu to then open the editor with the configurations of the custom style you previously saved.

Controls for the editor:

- + Slow movements are performed with the "Directional Pad".
- + The "Left Analog Stick" is used to perform rapid movements.
- + "L1" and "R1" are used to switch between the elements on the screen.
- + "L2" switches between changing position and changing size (only for some elements).
- + "R2" changes the number of pixels that will move with each movement.
- + The guide lines are activated and deactivated with "△".
- + "×" fixes the element to prevent accidental editing.
- + "R3" restores the position and size of the element to its initial state during editing.
- + Pressing "□" will expand the help bar, showing the rest of the controls.
- + Pressing "START" saves the settings.
- + "SELECT" accesses the editing submenu.
- + Pressing "○" exits the editor.
- + Pressing "L3" displays the style editor controls on the screen.



Help bar:

At the edge of the screen you will always see an indicator bar that will help you during editing; this bar changes its position according to the editing process so as not to interfere with it.


□ HELP	▶ SAVE	L1 PREV ITEM	R1 NEXT ITEM
— MENU	R2 PIXELS: 1	○ HELP	— MENU ITEM
		× LOCK ITEM	R3 RESTORE
		L2 RESIZE	R2 PIXELS: 1
		△ LINE GUIDE	▶ SAVE STYLE

In this bar you will see some of the editor's basic controls, but pressing "□" will expand the bar showing all the controls.

Editing submenu:

Pressing "SELECT" will open the editing submenu where you can:

- + Activate or deactivate on-screen elements.
- + Restore all elements to the original style position.
- + Change the type of transition the style will have.
- + Change the speed at which the transition will run.
- + Save style settings.
- + Exit the editor.



Note 1: If you press "R1" on the "List" option, the rendering of sprites in the custom style will be enabled or disabled.

Note 2: If you press "R1" on the "Art" option, it will hide or show the shadows behind all the artwork.

Note 3: If you press "X" on the "Transition Type" option you will be able to see a sample of the selected transition. There are a total of 15 transitions (some are slight variations of others), the last one being an immediate transition without any effect.

Note 4: The double-digit transition speed only applies to the first three transition types, and this speed ranges from 10 pixel jumps per frame to 50 pixel jumps per frame. For the remaining transitions, the speed will be applied at five different levels, determined by the first number in the setting (for example, if the setting is 29, the transition speed will be 2).

Note 5: If you restore all items from this submenu, they are restored to the default custom style settings, so they are not restored to the pre-edit position as happens when you press "R3" on an item, but rather to a predefined position internally in RETROlauncher.

Guide lines:

If you press "△" you will see the guide lines on the screen; these lines will help you center the elements, align them with others, or get a better perspective of the screen space.



Note 1: Pressing "△" will switch between the different guide line modes:


- + Mode 1: Off, no guide lines.
- + Mode 2: Element position lines with opaque background.
- + Mode 3: Element position lines plus grid with opaque background.
- + Mode 4: Element position lines without background (more visible lines).
- + Mode 5: Element position lines plus grid without background (more visible lines).

Note 2: When the rules are active, next to the bar you will be able to see the positions of the elements on the "X" (horizontal) and "Y" (vertical) axes, taking the upper left corner of each element as a reference.

Colored boxes:

During editing, you will see colored boxes that will help you know at all times which element you are editing and what its status is.


- + The "green" box indicates that the position of the element is being edited.




+ The "blue" box indicates that the size of the element is being edited.

Note: The only elements that allow modification of their size are:

- + List of games.
- + Main artwork.
- + Secondary art.
- + System logo.
- + Secondary art in the "Cover Flow" style.
- + Sprites.




+ The "red" box indicates that the item is locked, so its state will not be changed.



Save style settings:

To save the settings, simply press “**START**” from the editor or select the “**Save style**” option from the submenu.




Note: If a style configuration exists, saving the new configuration will create a backup of the previous one. If you accidentally save the configuration, you can recover this backup in the directory “USB:/RETROlauncher/System/Config/” under the name “style_old.cfg”. Rename the file to “style.cfg” and replace the existing one. (You can also manually back up the “style.cfg” file to export configurations or customize RETROlauncher derivatives.)

It is important not to save again if you intend to recover the backup, as each save will overwrite the previous backup.


Exit the style editor:

To exit the editor, simply press “**○**” in the editor or select the “**Exit editor**” option from the submenu.

Note: If changes are made and not saved, we will be asked to confirm the exit.




Activate systems (page 1):



This setting is used to activate and deactivate the different systems. If a system is deactivated, it will not appear in the RETROlauncher menu, and when you switch systems, it will automatically switch to the next activated one.


Note: It is mandatory that at least one system is activated; if all systems are deactivated, the first one will automatically be activated.

Restore RetroArch configurations individually:



RetroArch systems can be restored individually from here. To do this, place the cursor over the system you wish to restore and press "SELECT". Once done, a message will appear to confirm the restoration. Here you can also indicate whether you want to delete all saved games from the system to be restored; to do this, simply press "L1" or "R1" before confirming the restoration.


Deactivate wLaunchELF:



You can disable wLaunchELF from here. To do this, place your cursor over the "APPS" system and press "SELECT". Once done, a configuration menu will appear.

Note: Disabling it will cause applications to be launched by default through Enceladus.

General settings of POPStarter:



You can perform some general configurations for POPStarter from here. To do this, place the cursor over the "PlayStation" system and press "SELECT". Once done, a configuration menu will appear.

"IGR" Exits to "OSDSYS":

This option installs a patch in the POPS folder that changes the default output of the POPStarter "IGR" (MC0:/BOOT/BOOT.ELF) to the PlayStation 2 "OSDSYS" output.

Disable "Dithering" in games:

This option installs a patch that disables the "dithering" effect in all POPStarter games.

Install translation in "IGR" (language):

This option installs the "IGR" translations in the POPS folder.

Note 1: The translation language that will be installed will be the same as the one configured in RETROLauncher; this will appear in parentheses next to the option.

Note 2: Until the settings are established, they will not take effect.

Note 3: Those options that are activated will show their status, but the language option will always appear deactivated. You do not need to reinstall the translation if you change the other options, since this option, unlike the others, will not uninstall the translations when the settings are set.

Configure custom directory for OPL:



You can configure an “OPL” executable from here so that when launching games, it appears listed among the “OPL” versions found. To do this, place the cursor over the “PlayStation 2” system and press “**SELECT**”. Once done, the file explorer will appear.

Note: If other executables are found in the predefined "OPL" directory, the executable configured in this option will be added to those found in the aforementioned directory, but with the difference that it will be labeled as the user-configured executable. Otherwise, it will run directly with the configured executable.

Change page (page 2):



To switch between settings pages, press the shoulder buttons “**L1**” o “**R1**”.

To jump between options, press the shoulder buttons “**L2**” o “**R2**”.

Font type (page 2):



This setting is used to switch between the different text fonts found.

Some fonts don't work well with RETROlauncher. To try and correct this, once you've selected the font, press “**SELECT**” on the “**Font type**” option, and a menu will open to readjust the text font.

Note: The text sources found will not be represented by name, they will only receive a number in the order in which they were found.

Text font settings:



In this menu you can modify the parameters of the selected text font to try to adjust it to the different RETROlauncher menus.

Font adjustment:




Set width: This setting is responsible for configuring the text font width.

Set height: This setting is responsible for configuring the height of the text font.

Modify the “**Set width**” and “**Set height**” options, ensuring that both “**-Loading Art-**” texts remain within the dark boxes and are fully visible.

Text offset adjustment:



Set the start of the text scroll: This setting determines which character the text scrolling starts from. This setting applies to game lists and the width configured in the current style.

Modify the "Set the start of the text scroll" option by ensuring that the number "0" is visible in the green box at the end of the gray box.

Note: If the list width is too large, or too small, it will automatically adjust to the maximum of the adjustment window, in order to ensure a minimum and maximum safe text displacement.

Adjusting shadows behind text:



Set text background: This setting determines the shadows behind the text. This setting may not always be adjustable; if you're not getting good results, it's best to disable it by leaving this setting at 0.

Modify the "Set text background" option, ensuring that all texts are inside the dark bars behind them.

Note: al cambiar de fuente este valor se ajusta automáticamente a "0" ya que no es muy preciso con algunas fuentes de texto y es mejor que este desactivada.

Save font setting:

To apply the changes, press "□".

Note 1: If you press "○" it restores the default settings.

Note 2: If you cancel the adjustment by pressing "△", the changes made will be lost.

Note 3: It requires that the configuration be saved once the changes have been made.

Change the background (page 2):



This setting is responsible for switching between the different available background.

There are three possible types of backgrounds:

- + Static background.
- + Animated background.
- + Layered animated background.

Static background:

These funds do not require any special nomenclature in their names, they only require that they meet the minimum requirements.

Minimum requirements:

- + It must be an image in ".png" format
- + The image must have a transparency mask; otherwise, it will not be displayed.
- + The maximum resolution should be 640x480, although it can be lower.
- + It is recommended to use 8-bit PNG images with 256 colors.
- + It can have any name, as long as the extension is ".png" (short names are recommended).

Animated background:

These backgrounds require the nomenclature “_ANI” at the end of their name to be considered animations, in addition to having to meet the minimum requirements for their proper functioning.

Minimum requirements:

- + It must be an image in “.png” format
- + The image must have a transparency mask; otherwise, it will not be displayed.
- + Resolutions can be of various sizes, although the recommended one is 640x480.
- + The maximum tested resolutions are those with a difference of 280 pixels between height and width for the PAL format (760x480 and 480x760) and a difference of 460 pixels for the NTSC format (940x480 and 480x940); if these differences are exceeded, the program will fail.

Note: Ideally, images should have a maximum difference of 280 pixels between height and width to be compatible with PAL and NTSC.

- + It is recommended to use 8-bit PNG images with 256 colors.

For an image to be recognized as an animation, it must include the “_ANI” suffix at the end of its name.


Example: If the image is named "Background.png", it must be renamed by adding "_ANI" to the end, resulting in "Background_ANI.png".

Configure number of animations:


By default, the image is divided into 4x4 columns and rows, resulting in a total of 16 animations. This number of columns and rows can be configured in the RETROLauncher settings menu; however, the quickest way to automate this is to append the number of columns and rows to the image name.

Example: If the image is called "Background_ANI.png" and contains four animations, it is renamed by adding the number of columns and rows separated by an "x" just before "_ANI", the first number corresponds to the columns and the second to the rows.

It should be renamed to "Background_2x2_ANI.png", so that RETROLauncher automatically uses that configuration.




Example background with 4 animations arranged in 2 columns and 2 rows.
“Background_2x2_ANI.png”




Example background with 6 animations arranged in 3 columns and 2 rows.
“Background_3x2_ANI.png”

Configure the number of animations from RETROLauncher:

If you are unsure of the number of columns and rows, simply add the nomenclature "**_ANI**" to the end of the image name, enter the settings menu in RETROLauncher, once in the settings menu place your background in the "**Change the background**" option, then press "**SELECT**" and the settings menu will open.



From here you can see in real time how the image is divided as you change the number of columns and rows. Once you see the background correctly displayed, adjust the settings and you will be asked if you want to rename the image so that it is automatically configured upon loading.



Layered animated background:

These backgrounds require the "**_LAY**" suffix at the end of their name to be considered animations, in addition to having to meet the minimum requirements for their proper functioning.

Minimum requirements:

- + It must be an image in ".png" format
- + The image must have a transparency mask; otherwise, it will not be displayed.
- + Resolutions can be of various sizes, although the recommended one is 640x480.
- + The maximum tested resolutions are those with a difference of 280 pixels between height and width for the PAL format (760x480 and 480x760) and a difference of 460 pixels for the NTSC format (940x480 and 480x940); if these differences are exceeded, the program will fail.
Note: Ideally, images should have a maximum difference of 280 pixels between height and width to be compatible with PAL and NTSC.
- + It is recommended to use 8-bit PNG images with 256 colors.

For an image to be recognized as an animation, it must include the suffix "**_LAY**" at the end of its name.


Example: If the image is named "Background.png", it must be renamed by adding "**_LAY**" to the end, resulting in "Background_LAY.png".

All images will be divided into four layers:

- + The top left corner will be **layer 1** (it will be in front).
- + The top right corner will be **layer 2** (it will be at the bottom).
- + The bottom left corner will be **layer 3** (it will be between layers 2 and 4).
- + The bottom right corner will be **layer 4** (it will be in front of layer 3 and behind layer 1).

Note 1: The position of the layers may vary in some configurations to achieve certain effects.

Note 2: The dimensions of each layer will be automatically adjusted according to the image resolution.



Example of how the layers are divided.

This division will be the same for all layered animated backgrounds, and the different positions of the layers will depend on the type of animation configured.

Configure layer animations:

The configuration parameters are 8 alphanumeric characters (case-sensitive) located after the name and before "**_LAY.png**". Each of these alphanumeric characters represents a setting for the layer's animation. They can be configured manually using a settings table, but it is recommended to use RETROLauncher itself to make these changes.

Example name: "Background_**14101101**_LAY.png"


"**_LAY**" manages the image as a layered animation and "**_14101101**" manages the layered animation settings (the underscore "**_**" after the name and before the settings is mandatory).

Layer configuration parameters:

- + The first parameter determines the type of animation of the layers.
- + The second parameter determines the animation speed.
- + The third parameter is the speed multiplier.
- + The fourth parameter is the type of transparency of the layers.
- + The fifth parameter determines the level of transparency.
- + The sixth parameter determines the speed at which the transparency levels change.
- + The seventh parameter is the type of layer rotation.
- + The eighth parameter determines the rotation speed.

Configure layer animations from RETROLauncher:

To configure, first add the suffix "**_LAY**" to the end of the image name, then enter the settings menu in RETROLauncher. Once in the settings menu, place your background in the "**Change the background**" option, then press "**SELECT**" and the settings menu will open.



From here you can see in real time the different types of animations and their behavior.

Once you find the animations that best suit your background, set the configuration. You will be asked if you want to rename the image so that it automatically configures itself when loaded.

RENAME IMAGE FOR AUTO-CONFIGURATION?

CURRENT NAME:

FONDO_LAY.PNG

NEW NAME:

FONDO_01101101_LAY.PNG



CHANGE



CANCEL

Note 1: In the layer settings menu, you will see a brief description of the different options on the right side of the screen.

Note 2: If you press "O" in the layer settings menu, the settings menu will be hidden.

Note 3: The wallpapers found will not be represented by their name, they will only receive a number in the order in which they were found.

Note 4: It requires that the settings be saved in order to be applied.

Clean GUI (page 2):

CLEAN GUI

DISABLED

This setting is responsible for showing or hiding the navigation buttons on the screen as well as the text that accompanies them.

Note 1: Customizing the style will not affect this setting, as both are independent.

Note 2: It requires that the settings be saved in order to be applied.

Force garbage collection (page 2):

FORCE GARBAGE COLLECTION

DISABLED

This configuration allows you to force garbage collection in the program code. By default, it is disabled and Enceladus will handle garbage collection itself. If enabled, garbage collection will be performed in every program cycle. In some cases, this allows the program to be more stable but at the cost of lower performance (this may vary between different configurations).

By pressing "SELECT" on this option, you can activate single list loading, which allows for better performance when moving through lists but at the cost of small pauses when switching between systems.

-RELEASE REST OF LISTS?-

WHEN ENABLED, LIST MOVEMENT WILL BE SMOOTHER
AT THE COST OF PAUSES IN SYSTEM CHANGES.

DISABLED



CHANGE



BACK

Note: It requires that the settings be saved in order to be applied (it is also recommended to restart the program).

Custom APP/ELF output (Page 2):

CUSTOM APP/ELF OUTPUT

STANDARD

PS2 SYSTEM MENU


This configuration changes the default output of RETROLauncher to a custom ".ELF" application.

Pressing "SELECT" on the main menu to exit RETROLauncher will execute the application defined in this configuration.

Pressing "X" on the "Custom APP/ELF output" option changes the device where the ".ELF" file will be searched for.

The search options are:

- + "Standard" for the default output to the PS2 system.
- + "MCO:" for the first Memory Card.
- + "MC1:" for the second Memory Card.
- + "MASS:" for searching on the current device.



Clicking on the option below will open a file explorer to search for the ".ELF" application on the selected device.



Once in the browser, press "X" to open the directories and select the application, press "O" to return to the previous directory, and press "triangle" to cancel the search.

The file explorer will only display folders and applications with the ".ELF" extension. If no folder or application is found, a message will appear indicating that there are no compatible files. If everything is correct, you will see the selected application in the settings menu. Remember to save the settings before exiting the settings menu; otherwise, RETROLauncher will reset the option.

Note 1: Executable files will appear with a green box next to them, and folders with a yellow box.

Note 2: This output is only for RETROLauncher, it does not apply to any other application.

Note 3: If the selected application is not found when loading the configuration, the default output will be returned.

Note 4: It requires that the settings be saved in order to be applied.

See full route in the APPS menu (page 2):

SEE FULL ROUTE IN THE APPS MENU

DISABLED

This setting allows you to display the full path in the application menu, which is very useful when you have several applications with the same name in subfolders or on different devices.

Note: It requires that the settings be saved in order to be applied.

Sound in the menu (Page 2):

SOUND IN THE MENU

DISABLED

SOUND VOLUME

65

This setting toggles sound effects in the RETROlauncher menu. When enabled, the "Sound volume" option below controls the volume of the sound effects.

Note 1: To change the volume, place the cursor over the "Sound volume" option and press the direction keys on the Pad ("Left" or "Right").

Note 2: If the sounds are not found and the option is active, the playback of that sound will be skipped.

Note 3: It requires that the settings be saved in order to be applied.

If you press "SELECT" on the "Sounds in the menu" option, a window will appear where you can enable or disable the background music loop (it is disabled by default).

-BACKGROUND MUSIC LOOP?-

ENABLED



CHANGE



BACK

Screenshot as background (page 2):

SCREENSHOT AS BACKGROUND

DISABLED

This setting allows you to display screenshots of each game as the background in the menu of each system, when the game is selected.

Note: It requires that the settings be saved in order to be applied.

Video mode (page 2):

VIDEO MODE

NTSC

This option allows you to change the video mode of RETROlauncher, and the settings specific to each RetroArch system.

When we change this option, a window will appear asking if we want to confirm the change. Keep in mind that making this change causes all RetroArch systems to reset their configurations to the default settings, in order to adapt to each type of format ("NTSC/PAL 60Hz" or "PAL 50Hz").

-CHANGE VIDEO MODE TO NTSC?-

WARNING!

USE ONLY IF RETROARCH HAS AUDIO CUTS OR IF
YOU HAVE NO OTHER MEANS TO CHANGE THE FORMAT.
ALL RETROARCH OPTIONS WILL RESET.



CHANGE




CANCEL

Note 1: This configuration is not affected by RETROlauncher restores.

Note 2: RetroArch systems will be restored according to the selected video mode.

Vibration in menu (page 2):




This setting activates a vibration effect in the RETROLauncher menu.

Note 1: Sometimes the vibration effect gets stuck; simply perform another movement to correct it.

Note 2: It requires that the settings be saved in order to be applied.

Extra directories (page 2):



This setting enables or disables searches in the system's extra directories. These directories are where PS2 applications or ISOs are typically added. This is very useful when you don't want to move applications or ISOs to the RETROLauncher internal directory (which is enabled by default).

Directories that are added to the search when this option is enabled:


- + "MC0:/APPS/" - For the APPS system.
- + "MC1:/APPS/" - For the APPS system.
- + "USB:/APPS/" - For the APPS system.
- + "DVD:/" - For the APPS system.
- + "Applications installed by SAS (Save APP System)" - For the APPS system.
- + "USB:/DVD/" - For the PlayStation 2 system.
- + "USB:/CD/" - For the PlayStation 2 system.

Note 1: If disabled, it will only list the applications or ISOs that are within the internal directories of RETROLauncher (for PS2, DVDs/CDs in the tray will still be displayed).


Note 2: It requires that the settings be saved in order to be applied.

Show numerical index next to the games:

To see a numerical index next to the games and applications found, hover over the "Extra directories" option, then press "SELECT" and you can activate or deactivate the indexes in the lists.




Language (page 2):



In this option you can change the language of RETROLauncher; only three languages are available, although these can be modified or replaced by editing the code.

Available languages:

- + English.
- + Spanish.
- + Portuguese.



To change the language, select the "Language" option by pressing "X", then use the "Directional Pad" to switch between the available languages and finally press "Enter" to apply it.

Note 1: Applying the change will kick you out of the settings menu and any unsaved changes will be restored.

Note 2: You can improve or replace these traditions by editing the "language.lua" file.

Note 3: Although most texts are translated, the translation is not one hundred percent reliable.

Reset all settings (page 2):

RESET ALL SETTINGS

This option restores all RETROLauncher settings to their defaults, as well as restoring RetroArch settings.

-RESET ALL SETTINGS?-
-DELETING SAVED STATES?-
L1 NO R1
□ RESET △ CANCEL

Note: There is an option to clear the save files stored in RetroArch. To do this, press "L1" or "R1" before confirming the reset. Be careful, as this option will delete save files from all systems.

Once the restoration has started, do not turn off or restart the console; wait for it to finish.

LOADING

-RESTARTING ALL SETTINGS-

Credits (page 2):

CREDITS

This option displays the credits for all the applications and media behind RETROLauncher.

Note: You can fast-forward the credits by holding down any button, with the exception of button "△", because if you press it you will be kicked out of the credits.

Save settings:

▶ SAVE SETTINGS



CHANGE



EXIT

To save the RETROLauncher configuration, simply press "START" and the settings made on both pages will be saved.

If changes are made and not saved, we will be asked to confirm the exit.

UNSAVED CHANGES. DO YOU WANT TO EXIT?
ALL CHANGES MADE WILL BE LOST UPON REBOOT.
□ EXIT △ CANCEL

Note 1: Do not disconnect the USB drive before or during saving, or you will get an error. The save will be complete when the game list is visible (it should be immediate).

Note 2: In the event that the configuration reading fails, the default options will be automatically restored and the configuration file will be recreated, replacing the previous one or creating it again if it does not exist.

How do I add covers and screenshots?

To add images to the games listed in RETROLauncher, simply copy the images to the directories corresponding to each system, respecting the names of each file and the necessary requirements.

Note: It is important to avoid having idle images without any associated gameplay, in order to prevent long loading times or excessively long pauses when switching between games.

Image requirements:

- + It must be an image in “.png” format.
- + The image must have a transparency mask, otherwise it will not be displayed.
- + The image name must be the same as the ROM/APPS name, respecting uppercase and lowercase letters.
Example: If the ROM is called "GaMe.nes", the image must be called "GaMe.png".
- + It is recommended to use resolutions lower than 320x240 (higher resolutions are possible, although it affects performance).
- + It is recommended to use “.png” images in 8-bit format with 256 colors (This greatly improves performance).
- + The smaller the image file size, the smoother the system will run.
- + The image must be in the directory corresponding to the ROM emulator.

Example:

Game: "USB:/RETROLauncher/Roms/Roms Sega Megadrive/Example.bin"

Cover: "USB:/RETROLauncher/Multimedia/Covers/Covers Sega Megadrive/Example.png"

Screenshots: "USB:/RETROLauncher/Multimedia/Screenshots/Screenshots Sega Megadrive/Example.png"

Image directories:

Atari 2600:

Cover: "USB:/RETROLauncher/Multimedia/Covers/Covers Atari 2600/"

Screenshots: "USB:/RETROLauncher/Multimedia/Screenshots/Screenshots Atari 2600/"

Atari Lynk:

Cover: "USB:/RETROLauncher/Multimedia/Covers/Covers Atari Lynk/"

Screenshots: "USB:/RETROLauncher/Multimedia/Screenshots/Screenshots Atari Lynk/"

Neo Geo Pocket:

Cover: "USB:/RETROLauncher/Multimedia/Covers/Covers Neo Geo Pocket/"

Screenshots: "USB:/RETROLauncher/Multimedia/Screenshots/Screenshots Neo Geo Pocket/"

Nintendo Famicom:

Cover: "USB:/RETROLauncher/Multimedia/Covers/Covers Nintendo Famicom/"

Screenshots: "USB:/RETROLauncher/Multimedia/Screenshots/Screenshots Nintendo Famicom/"

Nintendo Game Boy:

Cover: "USB:/RETROLauncher/Multimedia/Covers/Covers Nintendo Game Boy/"

Screenshots: "USB:/RETROLauncher/Multimedia/Screenshots/Screenshots Nintendo Game Boy/"

Nintendo Game Boy Color:

Cover: "USB:/RETROLauncher/Multimedia/Covers/Covers Nintendo Game Boy Color/"

Screenshots: "USB:/RETROLauncher/Multimedia/Screenshots/Screenshots Nintendo Game Boy Color/"

Nintendo Game Boy Advance:

Cover: "USB:/RETROLauncher/Multimedia/Covers/Covers Nintendo Game Boy Advance/"

Screenshots: "USB:/RETROLauncher/Multimedia/Screenshots/Screenshots Nintendo Game Boy Advance/"

Nintendo Super Famicom:

Cover: "USB:/RETROLauncher/Multimedia/Covers/Covers Nintendo Super Famicom/"

Screenshots: "USB:/RETROLauncher/Multimedia/Screenshots/Screenshots Nintendo Super Famicom/"

Sega Game Gear:

Cover: "USB:/RETROLauncher/Multimedia/Covers/Covers Sega Game Gear/"

Screenshots: "USB:/RETROLauncher/Multimedia/Screenshots/Screenshots Sega Game Gear/"

Sega Master System:

Cover: "USB:/RETROLauncher/Multimedia/Covers/Covers Sega Master System/"

Screenshots: "USB:/RETROLauncher/Multimedia/Screenshots/Screenshots Sega Master System/"

Sega Megadrive:

Cover: "USB:/RETROLauncher/Multimedia/Covers/Covers Sega Megadrive/"

Screenshots: "USB:/RETROLauncher/Multimedia/Screenshots/Screenshots Sega Megadrive/"

Sega SG-1000:

Cover: "USB:/RETROLauncher/Multimedia/Covers/Covers Sega SG-1000/"

Screenshots: "USB:/RETROLauncher/Multimedia/Screenshots/Screenshots Sega SG-1000/"

PlayStation:

Cover: "USB:/RETROLauncher/Multimedia/Covers/Covers PlayStation/"

Screenshots: "USB:/RETROLauncher/Multimedia/Screenshots/Screenshots PlayStation/"

Note 1: If no Covers are found in the RETROLauncher directories, the search will be performed in the "ART" folder at the root of the USB drive. This search will be conducted respecting the naming format for applications:

"executable_name.elf_COV" and "executable_name.elf_SCR".

Note 2: The images in the "ART" folder must be in ".png" format.

PlayStation 2:

Cover: "USB:/RETROLauncher/Multimedia/Covers/Covers PlayStation 2/"

Screenshots: "USB:/RETROLauncher/Multimedia/Screenshots/Screenshots PlayStation 2/"

Note 1: If no covers are found in the RETROLauncher directories, the search will be performed in the "ART" folder at the root of the USB drive. This search is only valid for ISOs whose names include "XXXX_XXX.XX", as it uses this part of the name to locate the covers in the "ART" folder.

Note 2: The images in the "ART" folder must be in ".png" format.

APPS:

Cover: "USB:/RETROLauncher/Multimedia/Covers/Covers APPS/"

Screenshots: "USB:/RETROLauncher/Multimedia/Screenshots/Screenshots APPS/"

Note 1: If there are no Covers in the RETROLauncher directories, it will look in the "ART" folder at the root of the USB.

Note 2: The images in the "ART" folder must be in ".png" format.

How do I add text fonts?

To add text fonts to RETROLauncher, simply copy the fonts to the corresponding directory, respecting the necessary requirements.

Text font requirements:

- + It must be a font with the extension ".ttf" or ".otf".
- + It can have any name as long as the extension is ".ttf" or ".otf" (Short names are recommended).

Text font directory: "USB:/RETROLauncher/Multimedia/Others/Font/"

Note 1: To change the fonts, you must enter the RETROLauncher settings, change the fonts, and save the settings.

Note 2: The font names will not be reflected in the settings; they will only be assigned a number.

Note 3: The text fonts may not adjust correctly in RETROLauncher. To fix this, once you've selected the font in the settings menu, press "SELECT" on the "Font type" option to access the text adjustment menu. Once there, follow the on-screen instructions to try to achieve a better font fit.

Note 4: If I accidentally configure a font that is too small or illegible, simply deleting the fonts from the directory will automatically load the default font.

How do I add wallpapers?

To add wallpapers to RETROLauncher, simply copy the images to the corresponding directory, respecting the necessary requirements.

Wallpaper requirements:

- + It must be an image in ".png" format.
- + The image must have a transparency mask, otherwise it will not be displayed.
- + It is recommended to use ".png" images in 8-bit format with 256 colors.
- + Fixed backgrounds can have any name as long as the extension is ".png" (Short names are recommended).
- + Animated backgrounds require the nomenclature "_ANI" at the end of their name to be considered as animations (review the background settings section for more information).
- + Layered animated backgrounds require the nomenclature "_LAY" at the end of their name to be considered as animations (refer to the background settings section for more information).
- + The maximum tested resolutions are those with a difference of 280 pixels between height and width for the PAL format (760x480 and 480x760) and a difference of 460 pixels for the NTSC format (940x480 and 480x940); if these differences are exceeded, the program will fail.

Wallpaper directory: "USB:/RETROLauncher/Multimedia/Others/Background/"

Note 1: If the background is not visible, it may not have a transparency mask.

Note 2: Ideally, images should have a maximum difference of 280 pixels between height and width to be compatible with PAL and NTSC.

Note 3: Regardless of the image resolution, it will always automatically adapt to "640x448" for NTSC and "640x512" for PAL.

Note 4: The name of the funds will not be reflected in the settings; only a number will be assigned to them.

How do I add sound effects?

To add sound effects to RETROLauncher, simply replace the sound effects in the corresponding directory, respecting the necessary requirements.

Sound effects requirements:

- + It must be sounds in ADPCM format.
- + They must have the extension “.adp”.
- + If you have an audio file with the extension “.adpcm”, simply rename it to “.adp”.
- + The names of the sounds should be the following:
 - + “back.adp” / Audio to go back and change image.
 - + “move.adp” / Audio for navigating through menu items.
 - + “next.adp” / Audio for the emulator change.
 - + “run.adp” / Audio for the execution and activation of elements.

Sound effects directory: “USB:/RETROLauncher/System/Medios/Sound/Menu/”

Note 1: Playback problems may occur if the audio is poorly encoded or if it is too large.

Note 2: There is an extra audio track that serves as background music. If you do not wish to hear this extra audio, you can disable it from the RETROLauncher settings menu (or replace it).

- + music.adp / Audio with background music.

Extra audio directory: “USB:/RETROLauncher/System/Medios/Sound/Background/”

Note 3: To create sound effects, you can use the OPL tool “WAV to ADP converter for OPL”. This tool will allow you to convert “.wav” files to “.adp” as long as the “.wav” format required by the application is respected.

PlayStation 1 game settings menu

All the settings in this menu are based on the POPStarter documentation created by ShaolinAssassin, and on the POPStarter patch documentation created by Hugopocked.

Prerequisites:

To have all the configuration functions, some requirements must be met:

- + Create the folder “**Hugopocked Fixes**” inside the POPS folder.
- + Download the Hugopocked POPStarter patch pack from their official channels (check the credits).
- + Unzip the “**POPS Game Fixes**” and “**POPS General Fixes**” folders into the previously created folder: “USB:/POPS/Hugopocked Fixes/”.

They should look like this:

“USB:/POPS/Hugopocked Fixes/POPS Game Fixes/”

“USB:/POPS/Hugopocked Fixes/POPS General Fixes/”

Note 1: It is recommended that all individual game patches from the “**POPS Game Fixes**” folder that are contained in a subfolder be extracted to the previous directory. This will ensure that when the list of patches is sorted alphabetically, they are ordered by the game title and not by the name of the folder containing it, making it easier to find the patch for your game.

Note 2: Do not alter the names of the internal folders in “**POPS General Fixes**” as the descriptions of these patches are associated with the names of those folders.

Note 3: The settings menu will only be available for games whose “vcd” file is on the USB drive (POPStarter executables will not be able to access the settings menu).

POPStarter settings menu:

To access the POPStarter settings menu, hover over the game you want to configure, press and hold "Ⓐ" to see the extra options in the main menu, then press "△" and the POPStarter settings menu will open (only available for games whose VCD is on the USB drive).

Note: At the bottom of the menu, you will be able to see the items located within the game folder that is currently being configured.

Install patches for specific games:


INSTALL PATCHES FOR SPECIFIC GAMES

If patches are found in the directory "USB:/POPS/Hugopocked Fixes/POPS Game Fixes/" a submenu will be displayed where we can see the list of patches found.



If you wish to install some of the game-specific patches, simply press "X" on it.

Note: The patches will be listed with the name of the folder that contains them; try to verify if the patch you are applying is the correct one for the game you are configuring.




You will be asked to confirm the patch installation. Since this is a game-specific patch, all previous patches in the game folder will be removed.

Install general patches:

INSTALL GENERAL PATCHES


If patches are found in the directory “USB:/POPS/Hugopocked Fixes/POPS General Fixes/” a submenu will be displayed where we can see the list of patches found.

Note: General purpose patches are patches that can be applied to any game, with the aim of trying to fix problems that occur during emulation.



If you wish to install some of the general patches, simply press “X” on it.

Note: If the name of the folder containing the general patch has been respected, pressing “□” will show a short description of the patch's behavior and purpose.



You will be asked to confirm the patch installation. As this is a general-purpose patch, it will only replace patches with the same name within the game folder.

Install "CHEATS.TXT" file:


INSTALL "CHEATS.TXT" FILE

If "CHEATS.TXT" files are found in the "USB:/POPS/Hugopocked Fixes/POPS Game Fixes/" directory, a submenu will be displayed where we can see the list of items found.

Note: Some "CHEATS.TXT" files come with cheats disabled by default, so once you install a "CHEATS.TXT" file, go into the cheat settings to enable them.



If you wish to install any of the "CHEATS.TXT" files found, simply press "X" on it.



You will be asked to confirm the installation of "CHEATS.TXT". If a "CHEATS.TXT" file already exists in the game folder, the new file will replace the existing one.



Extra Settings:

EXTRA SETTINGS

If a "CHEATS.TXT" file is found in the game directory, the codes it contains will be read and added to the codes that POPStarter has by default; otherwise, a new "CHEATS.TXT" file will be created containing the configuration codes that POPStarter has by default.

Note 1: Codes belonging to POPStarter will be detected and organized at the beginning of the file under the tag "**// POPSTARTER CODES //**", while extra codes (usually game cheats) will be placed below the POPStarter codes under the tag "**// EXTRA CODES //**", for this reason it is recommended that you use tags on the lines that contain cheats to know what function each code performs.

Note 2: Unactivated POPStarter codes will be removed from the "CHEATS.TXT" file, while anything that is not a POPStarter code will remain intact (the only change is its movement to the "**// EXTRA CODES //**" area).



To activate or deactivate any of the codes found, simply press "X" on the code. You can see its status to the right of the code. Once you activate the desired cheats, press "START" to save the codes (you will be asked to confirm the save).

Note: By pressing "D" on the POPStarter codes, you will be able to see a short description of how it works.

Clear game settings:

CLEAR GAME SETTINGS

In this option we can clean all active game patches and codes.

CRASH TEAM RACING
CLEAR SELECTED SETTINGS?
ONLY PATCHES
ONLY CODES
ALL CONFIGURATIONS
X CLEAN O CANCEL

Once inside the submenu you can select between:

- + Clean only the patches.
- + Clean only the codes.
- + Clean both the patches and the code.

Note: In the case of cheats, the "CHEATS.TXT" file will not be deleted, but all the cheats it contains will be deactivated.

Create executable for POPStarter games:

If you only have the ".VCD" file but not the game's executable, you'll be asked where you want to create it. There are two locations: the POPS folder itself and the APPS folder. If you choose the latter, the necessary files will be created so the game will also appear in the list of all applications that can handle "Title.cfg" files.

-WHERE TO CREATE THE GAME EXECUTABLE?-
DIRECTORY "POPS"
DIRECTORY "APPS"
□ SELECT △ CANCEL

PlayStation 2 game settings menu

Starting with Revision 2, RETROLauncher uses unique configuration files for Neutrino. This means that all configurations have been consolidated into a single file, named after the game to which they apply. Therefore, all previous configuration files such as ".mode", ".vmcd", and ".mgsm" are no longer compatible with this revision.

Note: These configuration files can still be created manually, but now all commands must be in a single file named after the game. This practice is not recommended, as errors can occur due to misspelled commands, causing the game to fail.

Neutrino settings menu:

To enter the PlayStation 2 settings menu, place the cursor over the game you wish to configure, hold down "O" to view the extra options in the main menu, then press "△" and the Neutrino settings menu will open.

Note: This menu will only be available for physical ISOs and game shortcuts located on other media; it will not be available for games located in the CD/DVD tray.

Configure VMC (Neutrino):




RETROLauncher will automatically list the "VMC" files found in the "USB:/VMC/" directory. If a shortcut is being configured, the "VMC" files with the same source as the shortcut will be listed.

Activate the "Use virtual memory card" option and then select the "VMC" you want to assign to the game.

Note: The game may fail to run if the "VMC" cannot be opened or if it is fragmented.


Configure compatibility modes (Neutrino):



Here you can activate the different compatibility modes for Neutrino. Before activating the different modes, please investigate whether your game requires any of these modes to function correctly.

Note: Some games may fail when compatibility modes are enabled; please check the Neutrino documentation and its compatibility list.

Configure GMS (Neutrino):



Here you can switch between the different "GSM" modes that can be applied. To change the modes, press "Right" and "Left" on the "Directional Pad" or the "Left Analog Stick".

Note: It does not convert games from PAL to NTSC or vice versa, it only forces video output; not all games are compatible with "GSM", check the Neutrino documentation.

Save game settings (Neutrino):



To save the game settings, simply press "START" and wait for the settings to be created.

Note: RETROLauncher will create the configuration files for each game inside the folder "USB:/RETROLauncher/Roms/ISOs PlayStation 2/Configs/" to keep the game folders cleaner.


Open PS2 Loader settings menu:



To enter the Open PS2 Loader configuration menu, place the cursor over the game you wish to configure, hold down "C" to view the extra options in the main menu, then press "A" and the Neutrino configuration menu will open, once there press "R1" to switch to the Open PS2 Loader menu.

Note 1: This menu will only be available for physical ISOs located on the USB drive.

Configure VMC (OPL):



RETROLauncher will automatically list the "VMC" files found in the "USB:/VMC/" directory.

Enable the "Use virtual memory card" option and then select the "VMC" file you want to assign to the game.

Note: The game may fail to run if the "VMC" cannot be opened or if it is fragmented.

Configure compatibility modes (OPL):



Here you can activate the different compatibility modes for OPL. Before activating the different modes, please investigate whether your game requires any of these modes to function correctly.

Note: Some games may fail when compatibility modes are enabled; please check the OPL documentation and its compatibility list.

Configure GMS (OPL):



Here you can switch between the different "GSM" modes that can be applied within OPL. To change modes, press "Right" and "Left" on the "Directional Pad" or the "Left Analog Stick".

Note: Not all games are compatible with "GSM", check the OPL documentation.

Save game settings (OPL):



To save the game settings, simply press "START" and wait for the settings to be created.

Note: RETROLauncher will only modify those options shown in the OPL configuration menu itself; if your game configuration contains other OPL-specific settings, these will not be modified.

WARNING: It is not recommended to use RETROLauncher to modify game configurations created by Open PS2 Loader, because conflicts may arise between RETROLauncher's internal settings and different versions of Open PS2 Loader. The best option is always to configure games directly from your specific Open PS2 Loader version, not only to ensure compatibility but also to keep your configurations up-to-date. Since Open PS2 Loader is constantly evolving, settings are added, modified, or removed, which may become incompatible with those used by RETROLauncher.

How do I run PS2 games from MX4SIO? (Experimental)

To add games located on the MX4SIO, you must create an empty text file on the USB drive in the same directory as the game's ".ISO" file on the MX4SIO. Give this file the same name as the game's file on the MX4SIO and change the extension from ".txt" to ".mx4". This empty file with the ".mx4" extension will tell RETROLauncher that the game is being run from the MX4SIO.

Example 1:

Game inside MX4SIO: "MX4SIO:/DVD/game.iso"

Direct access to the game on the USB: "USB:/DVD/game.mx4"

Example 2:

Game inside MX4SIO: "MX4SIO:/CD/game 2.iso"

Direct access to the game on the USB: "USB:/CD/game 2.mx4"

Note 1: Place the shortcuts on the USB drive in the same directory as your games on MX4SIO.

It is important to respect the shortcut directory; if a shortcut is placed in the folder "USB:/DVD/" and the game is located in the directory "MX4SIO:/CD/", the game will not run.

Note 2: The only two directories where shortcuts will be searched are "USB:/DVD/" and "USB:/CD/".

Note 3: If the name is misspelled and does not match the game on MX4SIO, or if it is not found, Neutrino will not run it.

Note 4: Compatibility modes are fully functional and configurable from RETROLauncher.

VMC for gaming on MX4SIO

In order to load a VMC when running a game from MX4SIO, it is mandatory that the VMC is located in the MX4SIO's own directory ("MX4SIO:/VMC/"). Although RETROLauncher can assign a VMC, these memories are located on the USB drive, so if you assign a VMC from the RETROLauncher menu and that memory is not located on the MX4SIO, the game will fail to run.

Add VMC to the game on MX4SIO

To add VMCs to games on MX4SIO, simply create a text file in the "USB:/VMC/" directory with the same name as the VMC located within the "MX4SIO:/VMC/" directory. Then, change the file extension from ".txt" to ".mx4". RETROLauncher will automatically recognize these files as VMCs that can be assigned to MX4SIO shortcuts.

Example:

VMC in MX4SIO: "MX4SIO:/VMC/generic_0.bin"

Direct access to VMC on USB: "USB:/VMC/generic_0.mx4"

Note 1: The created files will only be listed for MX4SIO shortcuts.

Note 2: If the VMC name is misspelled and does not match the VMC in MX4SIO, or if it is missing, Neutrino will not run the game.

Note 3: For the rest of the devices the configurations are the same, the only thing that changes are the file extensions, for HDD (only in exFAT format) the extension is ".hdd" and for MMCE the extension is ".mmc".

Note 4: Reports were received of its correct operation for both MMCE and MX4SIO, but I still don't know if it works with an internal HDD in exFAT format.


IMPORTANT: These modes were not tested and I am unfamiliar with their functionality; however, they were added to the code so that users with the necessary resources can experiment. The command configurations are based on the Neutrino documentation, so they should work if everything is configured correctly.

I don't have the means to verify this, so it will always be better to use more specific and convenient applications to launch PS2 games such as OPL/NHDDL/XEB+ Launcher/OSD-XMB.

RETROLauncher Shortcut Maker

Use this tool to create all your shortcuts automatically.

- + Run "RETROLauncher Shortcut Maker.bat".
- + Enter the number of the mode used to create the shortcuts.
- + Enter the drive letter of the source device (where the games and VMC will be searched for).
- + Enter the drive letter of the destination device (where the game shortcuts and VMC will be created).

A screenshot of a Windows command prompt window titled "RETROLauncher Shortcut Maker". The text inside the window shows the program's instructions and user input. It starts with a title bar, followed by instructions to create shortcuts for MX4SIO, HDD, or MMCE. The user enters '1' for MX4SIO. Then, it asks for the SOURCE drive letter (user enters 'f') and the DESTINATION USB drive letter (user enters 'g'). After a separator, it shows "RETROLauncher Shortcut Maker - MX4SIO" and reports that shortcuts were created for "DEMO GAME" and "DEMO UMC 'UMC'". It then says "Done. 1 shortcuts created for games." and "Done. 1 shortcuts created for UMC." Finally, it prompts "Press a key to exit." The window has a standard Windows XP-style title bar and a scrollbar on the right.

```
RETROLauncher Shortcut Maker
-----
To create MX4SIO shortcuts enter: 1
To create HDD shortcuts enter: 2
To create MMCE shortcuts enter: 3
-----
Enter the MODE number: 1
Enter the SOURCE drive letter: f
Enter the DESTINATION USB drive letter: g
-----
RETROLauncher Shortcut Maker - MX4SIO
-----
shortcut created for DEMO GAME
shortcut created for DEMO UMC "UMC"
-----
Done. 1 shortcuts created for games.
-----
Done. 1 shortcuts created for UMC.
-----
Press a key to exit.
```

How do I update the emulators and cores of RETROLauncher?

To update the applications used by RETROLauncher, simply replace all the corresponding files for each application with a new version of the application or with an older version.

WARNING: Enceladus has received significant updates that have also changed some commands and ways of working, so unfortunately RETROLauncher is no longer compatible with this update method. To use the new Enceladus features, you must edit all the lines and commands that are no longer compatible (some functions must be removed). However, it is worthwhile for those who own FAT consoles, since among the new features of Enceladus is native hard drive support.

Neutrino: Download Neutrino and replace all files located in the directory "USB:/RETROLauncher/System/RetroarchPS2/Sony PlayStation 2/Neutrino/".

Note: There is a possibility that Neutrino's commands may change during development, so it may fail to run after an update (the code must be modified in those cases).

wLaunchELF ISR: Download any version or variant of "wLaunchELF ISR.elf" and copy it to the following directory "USB:/RETROLauncher/System/RetroarchPS2/APPS/", finally rename it to "WLE.elf".

It should look like this:

"USB:/RETROLauncher/System/RetroarchPS2/APPS/WLE.elf"

OPL: Download any version or variant of OPL (command-compatible), and copy it to the following directory: "USB:/RETROLauncher/System/RetroarchPS2/Sony PlayStation 2/OPL/".

RetroArch Cores: Download RetroArch, copy the Core you want to update and replace the Core in the respective system folder within the directory "USB:/RETROLauncher/System/RetroarchPS2/".

Note 1: If you wish to add another system, you can do so by editing the code (From version 1.14.0 onwards, exFAT is supported in RetroArch for PS2).

Note 2: There are some conflicts with running RetroArch via command in certain Core versions. If updating or replacing the Core doesn't work and the screen remains black, try a different version of RetroArch.

How do I run RETROLauncher from exFAT?

To run RETROLauncher from a device formatted in exFAT, simply download the file **“EXFAT USB support - BDMAssault by israpps (Matías Israelson).rar”**, extract the folders, and copy them to the root directory of your Memory Card. These files are necessary for some applications used by RETROLauncher to function with the exFAT format.

Note: Both “TempGBA” and older RetroArch Cores are not compatible with exFAT.

Files needed on the Memory Card:

“mc0:/POPSTARTER/usbd.irx”

“mc0:/POPSTARTER/usbhdfsd.irx”

“mc0:/SYS-CONF/USBD.IRX”

“mc0:/SYS-CONF/USBHDFSD.IRX”

How to launch games through OPL?

Requirements for launching games through OPL:

- + You must have a version of OPL that is compatible with command-line execution.
- + It is recommended to use your own OPL or revisions compatible with your configuration, since launching games through OPL (regardless of the OPL version used to launch the game) will load the currently installed OPL configurations. Therefore, if you launch the game with an OPL version that is not compatible with your current OPL configuration, conflicts or crashes may occur.
- + Access to the game ID is required, so it is recommended to use the old naming method “XXXX_XXX.XX.Game name.iso”. If the game name does not contain the ID, the search will be attempted within the ISO. This process extends loading time and may not be as accurate.
- + When launched through OPL, all OPL-specific configurations that have been configured will be loaded.
- + Only games in ISO format that are located on the USB drive will be launched.
- + Shortcuts will be skipped and launched automatically with Neutrino (as well as in cases where the game ID cannot be found).

You can add multiple versions of OPL in the following directory:

“USB:/RETROLauncher/System/RetroarchPS2/Sony PlayStation 2/OPL/”.

Note 1: If multiple versions of OPL are detected, you will be asked which version to run the game with (try to use OPL versions that share configurations, otherwise you will get conflicts).

Note 2: It's always best to use OPL directly to launch PS2 games, as this method has many limitations. This feature was only added as an extra option for specific games that aren't compatible with Neutrino or for quickly testing official OPL revisions.

Known Problems with RETROLauncher:

Error starting RETROLauncher: Accompanied by a message in red, this is a runtime error in the program code; it is recommended to reinstall all of RETROLauncher.

Error starting RETROLauncher from OPL: Accompanied by a message in red, this is a runtime error in the program code. Download the file "Problems when running from OPL.rar" and extract the "RETROLauncher" folder to the same directory as "RETROLauncher", merging both folders. Then copy the line from the "conf_apps.cfg" file and paste it into your "conf_apps.cfg" file. This should allow it to start from OPL.

RETROLauncher freezes on the "LOADING" screen: This error occurs when a media file, such as images or text fonts, cannot be found. If game images are in an incompatible format, the system will also freeze. Delete any recently added images. If the problem persists, reinstall RETROLauncher.

Error starting RETROLauncher with two USB: Accompanied by a message in white, it indicates that there is more than one USB device connected to the PS2, follow the instructions in the message and restart RETROLauncher.

External hard drive does not start RETROLauncher: Some external hard drives pause when running Enceladus, causing an error when loading the program. Use another medium such as a USB flash drive or try different versions of Enceladus.

Black screen when running game: Check that the game is compatible with the emulator/core you are running. If you replace the core, it means it is not compatible with RETROLauncher. Try a different core or reinstall RETROLauncher.

The sound from the Cores is choppy: This happens on consoles set to PAL 50 Hz, and it's because RetroArch automatically configures games to the game's region. To fix this, simply open RetroArch's options once you're in a game, find the Core settings, and try to force the system to match your console's or configuration. If your console is set to PAL 50 Hz, force the games to PAL 50 Hz, and the audio speed will be corrected (the setting is saved for all games upon exiting, although you can assign individual settings to games). Do this for all Cores or games that have this problem. Ideally, everything should be set to NTSC or PAL 60 Hz. If you don't have a modchip to change your console to NTSC or PAL 60 Hz, you'll need to change the RETROLauncher video mode to PAL in the settings menu. This will correct the choppy audio, but at the cost of some screen tearing.

Game start error: Accompanied by a message in red, this is a runtime error in the program code. It is recommended to restart RETROLauncher and verify that the USB device is correctly connected. If the problem persists, reinstall RETROLauncher.

GBA Freezes: Not all games are compatible with the GBA Core, but compatibility improves significantly by placing the GBA BIOS in the correct directory. Some games fix the freezes, while others remain the same; it's a matter of trying different methods (TempGBA is not compatible with exFAT).

BIOS: "gba_bios.bin"

Directory: "USB:/RETROLauncher/System/RetroarchPS2/Nintendo Game Boy Advance/retroarch/system/"

Error saving configuration: Accompanied by a message in red, this is a runtime error in the program code. It is recommended to restart RETROLauncher and verify that the USB device is correctly connected. If the problem persists, reinstall RETROLauncher.

Images are not showing in the menu: Please verify that the image name is correct. RETROLauncher is case-sensitive. Please also verify that the image you uploaded has a transparency mask; otherwise, the image will be found and displayed, but it will be completely transparent.

The controller keeps vibrating: This sometimes happens when you perform a vibration motion while an image is loading. It should be fixed by performing another motion; otherwise, simply restart RETROLauncher.

Pauses and freezes when loading images: If the images used are very large or have high-quality encoding, it will cause long pauses while loading them. Long pauses also occur when there are many items in the same folder; checking if an image exists in a folder with 500 items is not the same as having to search for it in a folder with more than 1000 items. Make sure you comply with the image requirements explained in this document.

RetroArch won't open after restarting: If RetroArch settings have been altered, the process of opening RETROLauncher will be corrupted. To fix this, restore the problematic system settings in the RETROLauncher settings menu. This should resolve the issue. If the problem persists, reinstall RETROLauncher.

The menu sound is distorted or glitchy: This sometimes happens when the audio isn't loading correctly. It should be fixed by simply restarting RETROLauncher. If the problem persists, reinstall RETROLauncher.

Game names are not displayed correctly or are altered: This occurs when the game name contains a special character (for example, "Ñ") and RETROLauncher fails to display the name. To fix this, simply change the game name to one that does not contain special characters.

PS1 games won't run: There can be many causes, but the main ones are:

- + Defective VCDs. If you want to run a VCD, make sure it's converted correctly.
- + Ensure your game is compatible with POPStarter.
- + If patches are required, check that they were installed correctly.
- + If you are running PS1 games from an exFAT device, make sure you have the drivers on the Memory Card.
- + Verify that the binary file names are correct, respecting capitalization.

PS2 games won't run: There can be many causes, but the main ones are:

- + Corrupted ISOs: If you want to run an ISO of a title whose original format was CD, make sure to convert it correctly.
- + Ensure your game is not fragmented.
- + Neutrino will run the game on the same system as your console is configured. If it's not modded, it will have problems with games that are not from your console's region. You can use patches on the ISOs or GSM files to try to run those games.
- + If you manually set compatibility modes, check that the command is spelled correctly and without spaces, otherwise it will fail.
- + If this happens after updating Neutrino, then it's a problem with the commands. Reinstall RETROLauncher.

Overscan in RetroArch games: Some cores exhibit "overscan" due to the nature of different systems. To fix this, once you open a game, go to the RetroArch video options and enter "Scaling." There you can try different scaling modes. Once you select the one that best suits your screen, restart RetroArch and the configuration will be saved. This change must be made individually for each core since they do not share the same configuration.

RETROLauncher is slow: If the game lists are very large, performance is affected. Try to keep the number of ROMs per system to a minimum; be more selective with your ROMs (lists with fewer than 1000 games are recommended). The same applies to images; if they are large, you will experience pauses when navigating between game lists (memory fragmentation may be causing RETROLauncher to slow down; try a clean installation). Try the **"Force garbage collection"** and **"Free up remaining lists"** options in the RETROLauncher settings menu.

Blue screen when running APPS: If you get a blue screen when running an application, it means that the application could not be run. The blue screen is the wLaunchELF ISR menu. Select one of the menu options to return to RETROLauncher or exit to the PS2 system.

Freezing when starting with DVD/CD in tray: This error occurs when RETROLauncher is run from a launcher that has the ability to read the DVD/CD drive, a clear example of this is wLaunchELF with DVD/CD support. To fix this, place the DVD/CD in the tray once RETROLauncher has started, then update the game list in PS2 or APPS.

OPL Black or White Screen: This error occurs when running a game that is fragmented or when RETROLauncher failed to obtain the game ID correctly. Check the ID name and try renaming the ISO with the old naming format.

OPL keeps loading: This error occurs when you run a version of OPL whose configuration is not compatible with the OPL configuration currently on your system. Try using your own OPL or a version compatible with your configuration.

RETROlauncher not working on my PS2: RETROlauncher was tested on only one console model, the "**SCPH-77006 - NTSC - japanese**". If you have problems with a specific model or its variations, please edit this document or post your console model via another means. If your console has a modchip, please also include the model/version and the device on which you are running RETROlauncher. I also strongly encourage you to post whether RETROlauncher works correctly on your console.

Credits

Enceladus: Enceladus is an enhanced Lua environment for creating homebrew software for the PS2.
Created by Daniel Santos.

DanielSant0s X: <https://x.com/danadsees>

Youtube: <https://www.youtube.com/channel/UCIDx5TuDp-1IRTr5I5JSdw>

Project Link: <https://github.com/DanielSant0s/Enceladus>

License: Distributed under GNU GPL-3.0 License.

RetroArch PS2 Port: RetroArch is a frontend for emulators, game engines and media players.

Created by RetroArch contributor fjtrujy (Francisco J. Trujillo).

fjtrujy X: <https://x.com/fjtrujy>

RetroArch Link: <https://www.retroarch.com>

Licenses: There is software behind RetroArch that is protected by Non-Commercial licenses. It is important to respect the wishes of the developers and people behind the respective projects.

<https://docs.libretro.com/development/licenses/>

POPStarter: POPStarter is a launcher which lets you play your PS1 games in combination with PS1 emulator for PS2.

Created by developer krHACKen.

POPStarter Link: <https://www.psx-place.com/threads/popstarter.19139/>

Neutrino: Neutrino is a small, fast and modular PS2 device emulator that maximizes compatibility and performance.

Created by developer Maximus32 (Rick Gaiser).

Neutrino Link: <https://github.com/rickgaiser/neutrino>

License: Academic Free License "AFL" v. 3.0

wLaunchELF ISR: wLaunchELF ISR is an open source file manager and executable launcher for the PS2 console.

wLaunchELF 4.43x_ISR was created by developer israpps (Matías Israelson) and is a wLaunchELF mod.

israpps (Matías Israelson): <https://israpps.github.io/>

Youtube: https://www.youtube.com/@El_IsraPS2

wLaunchELF 4.43x_ISR Project Link: https://github.com/israpps/wLaunchELF_ISR

wLaunchELF Project Link: <https://github.com/ps2homebrew/wLaunchELF>

License: Academic Free License "AFL" v. 2.0

wLaunchELF / project by AKuHAK and SP193.

uLaunchELF / project by E P and dlanor.

LaunchELF / project by Mirakichi.

And to all the developers who contributed to uLaunchELF.

RadShell: RadShell is a command line client for PS2 created by developer "RadAd", that allows the automation of basic tasks within PS2.

RadShell Link: <https://archive.org/details/radshell>

Hugopocked Fixes for POPStarter: These are corrections made by Hugopocked for the POPStarter emulator that solve multiple problems presented in the emulation of PlayStation 1 titles, providing the possibility of better emulation and execution of them.

Created by developer Hugopocked.

Hugopocked Fixes Link: <https://www.psx-place.com/threads/hugopocked-fixes-for-popstarter.39750/>

TempGBA: TempGBA (GpSP) is a Game Boy Advance emulator ported to PS2.

Created by developer belek666.

belek666 GitHub: <https://github.com/belek666>

TempGBA(GpSP) - PS2 link: <https://www.psx-place.com/resources/gpsp-by-belek666.687/>

SNESsticle: SNESsticle is a SNES emulator that was ported by its creator, Icer Addis (Sardu), to several platforms, including PS2.

Source code: <https://github.com/iaddis/SNESsticle>

License: MIT License Copyright 2022 Icer Addis

BDMAssault: BDMAssault is a PS2 homebrew project created by israpps (Matias Israelson) that aims to bring USB EXFAT support to older closed-source homebrew applications that can load external USB controllers.

BDMAssault Project Link: <https://github.com/israpps/BDMAssault>

License: Academic Free License "AFL" v. 2.0

Open PS2 Loader: OPL is a 100% open source game and application loader for PS2 and PS3 devices, created by Ifcaro and jimmikaelkael in conjunction with a huge community of developers who are constantly improving it.

Open PS2 Loader Project Link: <https://github.com/ps2homebrew/Open-PS2-Loader>

License: Copyright 2013, Ifcaro & jimmikaelkael Licensed under Academic Free License version 3.0.

Original background: <https://www.artapixel.com/escp-art-midnight-sun-city-night-retrowave-cyberpunk.html>

Created by < e s c p > Art

Youtube: <https://www.youtube.com/@escp>

License: This Image is licensed under the Creative Commons Zero v1.0 Universal.

Free images by <https://www.artapixel.com>

Public Pixel: Retro video game style text font.

Designed by GGBotNet.

GGBotNet X: <https://twitter.com/ggbotnet>

Youtube: <https://www.youtube.com/channel/UCndkEE767CI7wTINJYKrTg>

Public Pixel Link: <https://www.ggbot.net/fonts/>

License: This Font Software is licensed under the Creative Commons Zero v1.0 Universal.

A special thank you to the entire **"PSX-PLACE"** community for their support and visibility of the program. We also thank all the YouTube channels and their communities for promoting and improving RETROLauncher with their supportive messages and constructive feedback.

Spaghetticode: I created RETROLauncher with the sole purpose of having a simple and editable graphical environment for retro PlayStation 2 game collections. I made it for myself and never imagined it would grow so much, much less be published. I thought it would be good to share it in case someone, somewhere, was looking for the same thing I was and couldn't find anything focused on retro gaming for our beloved PlayStation 2. At no point did I intend to offend or disrespect the developers behind the various applications used in this program. I tried to compile as much information as possible to give proper credit. If I've overlooked something or made a mistake, I apologize. RETROLauncher is a collaborative effort.

Thank you for using RETROLauncher.

Boon Tobias 

RETRO
Launcher

