



How to Connect PuTTY to Kali Linux

Step 1: Download PuTTY from the internet. Search for “PuTTY download for windows ‘x’”, open a trusted download link, and download the version that matches your computer system.



Alternative binary files

The installer packages above will provide versions of all of these (except PuTTYtel and pterm)
(You probably want the 64-bit x86 version. The 32-bit version is only for backward compatibil

putty.exe (the SSH and Telnet client itself)

64-bit x86:	putty.exe	(signature)
64-bit Arm:	putty.exe	(signature)
32-bit x86:	putty.exe	(signature)

pscp.exe (an SCP client, i.e. command-line secure file copy)

64-bit x86:	pscp.exe	(signature)
64-bit Arm:	pscp.exe	(signature)
32-bit x86:	pscp.exe	(signature)


psftp.exe (an SFTP client, i.e. general file transfer sessions much like FTP)

64-bit x86:	psftp.exe	(signature)
64-bit Arm:	psftp.exe	(signature)
32-bit x86:	psftp.exe	(signature)

puttytel.exe (a Telnet-only client)

64-bit x86:	puttytel.exe	(signature)
64-bit Arm:	puttytel.exe	(signature)
32-bit x86:	puttytel.exe	(signature)

Step 2: After downloading, install PuTTY and open it. You will see an interface like this.



Step 3: To use PuTTY, we need the IP address of the Kali Linux machine. Run the **ifconfig** command in the Kali Linux terminal to find the IP address.


```
(kali㉿kali)-[~]
$ ifconfig
eth0: flags=4163<UP,BROADCAST,RUNNING,MULTICAST> mtu 1500
    inet 192.168.71.133 netmask 255.255.255.0 broadcast 192.168.71.255
    inet6 fe80::53e3:31c5:e14f:b1b3 prefixlen 64 scopeid 0x20<link>
    ether 00:0c:29:a2:01:2d txqueuelen 1000 (Ethernet)
    RX packets 7 bytes 948 (948.0 B)
    RX errors 0 dropped 0 overruns 0 frame 0
    TX packets 31 bytes 3676 (3.5 KiB)
    TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0
```

Step 4: We also need to make sure that the SSH service is running on the Kali Linux machine. Check the SSH service status by running the **service ssh status** command. If the service is disabled or not running, start it by using the **service ssh start** command.

```
(kali㉿kali)-[~]
$ service ssh status
o ssh.service - OpenBSD Secure Shell server
   Loaded: loaded (/usr/lib/systemd/system/ssh.service; disabled; preset: disabled)
   Active: inactive (dead)
     Docs: man:sshd(8)
           man:sshd_config(5)

(kali㉿kali)-[~]
$ service ssh start
```

Step 5: After completing these steps, enter the IP address of the Kali Linux machine in the PuTTY interface and start the connection.



Step 6: Then, enter the Kali Linux username and password. After successful authentication, the connection will be established.



```
kali@kali: ~  
login as: kali  
kali@192.168.71.133's password:  
Linux kali 6.12.25-amd64 #1 SMP PREEMPT_DYNAMIC Kali 6.12.25-1kali1 (2025-04-30)  
x86_64  
  
The programs included with the Kali GNU/Linux system are free software;  
the exact distribution terms for each program are described in the  
individual files in /usr/share/doc/*/copyright.  
  
Kali GNU/Linux comes with ABSOLUTELY NO WARRANTY, to the extent  
permitted by applicable law.  
Last login: Sat May 16 15:26:06 2026 from 192.168.71.1  
(kali@kali)-[~]  
$ ls  
'AGEN assignment 160 NEW.pdf'  ctf.rep      'his 109.pdf'  rockyou-4.txt  
Alif                          CTF.rep      logs           rockyou-6.txt  
burp.save                     Desktop      logs1          Templates  
ctf.gpr                       Documents    Music          text.txt  
CTF.gpr                       Downloads    Pictures       Videos  
ctfh.gpr                      hash1.txt    Public  
ctfh.rep                      hash.txt     rockyou-12.txt  
  
(kali@kali)-[~]  
$
```