

Grenade Pickup

Introduction

This video will help you understand how to setup grenade pickup for the player.

Pickup Item

This script allows the player to pick up items in the game. Items can be picked up automatically or manually, and UI elements can display item information before pickup.



Fields	Info
AutoItemPickup	Picks the item automatically on player collision.
UIPickupPanel	A UI Panel to show the item information before picking it up.
ItemImage	The image UI element to display the item sprite.
UIButtonForPickUp	The button that allows manual item pickup when clicked.
ItemSprite	The sprite representing the item in the UI.
ItemImageScale	The scale of the item image in the UI panel.
RecievedText	Text UI element to display 'Item Received' notification.

RecievedTextInfo	The text displayed when an item is received.
DeactivateTextDelay	Time in seconds before hiding the received text notification.
ColliderToDisableOnPickup	The collider that gets disabled when the item is picked up.
UITextInfo	A list of UI texts to display additional information about the item.
PickupObj	The item object that will be picked up and deactivated upon collection.
ItemName	The name of the item being picked up.
ReactivatItem	If enabled, the item will respawn after a delay once picked up.
ReactivationDelay	Time in seconds before the item respawns if ReactivatItem is enabled.
TargetScript	The target script that will execute a specific function upon pickup.

Motion Controller

This script controls the movement and rotation of an object. It allows smooth oscillating movement along the X, Y, or Z axes and continuous rotation around these axes.



Fields	Info
moveX	Enable or disable movement along the X-axis.
moveY	Enable or disable movement along the Y-axis.
moveZ	Enable or disable movement along the Z-axis.
moveDistanceX	Distance to move along the X-axis.
moveDistanceY	Distance to move along the Y-axis.
moveDistanceZ	Distance to move along the Z-axis.
moveDuration	Duration for one complete movement cycle.
rotateX	Enable or disable rotation around the X-axis.
rotateY	Enable or disable rotation around the Y-axis.
rotateZ	Enable or disable rotation around the Z-axis.
rotationSpeedX	Rotation speed around the X-axis (degrees per second).
rotationSpeedY	Rotation speed around the Y-axis (degrees per second).
rotationSpeedZ	Rotation speed around the Z-axis (degrees per second).