


Charging Behaviour

Introduction


This video will help you understand how to achieve 'Charging' behaviour on the humanoid AI agent during combat state.

AI Charging

First enable 'Ai Charging' located in the combat state behaviour.[See the image below]



Enabling it will show Strafing options in the script which you can tweak to achieve the desired behaviour.



Fields	Info
Enable Sprinting	

	If unchecked, AI agent will perform assault by Walking/Running/Sprinting and shooting its target.
Min Sprint Distance	Minimal remaining distance to pursue point for the switch from walking or running to sprinting towards it.
Max Sprint Distance	Maximum distance for sprinting towards coordinate.
Min Run Distance	Minimal remaining distance to pursue point for the switch from walking or sprinting to running towards it.
Max Run Distance	Maximal remaining distance to pursue point for the switch from walking or sprinting to running towards it.
Min Closest Distance To Stop	Minimal closest distance to stop.
Max Closest Distance To Stop	Maximal closest distance to stop.
Open Fire Behaviour	Fields in this subsection are setting Ai agent's weapon firing behaviour while he is moving towards or between covers. This subsection is reused in 3 different combat related paragraphs: Ai Charging, Ai Covers, and Ai Firing Points. In each of these cases, this subsection defines Open Fire Behaviour in relation to the parent paragraph's subject.
Stop And Shoot Probability	This slider sets the probability of 'Stop And Shoot' behaviour while Ai agent is moving towards or between covers.
Strafing Probability	This slider sets the probability of 'Strafing' behaviour while Ai agent is moving towards or between covers.
Min Stop And Shoot Distance To Enemy Or To Cover	Minimal distance towards the cover to activate Stop&Shoot behaviour.
Max Stop And Shoot Distance	Maximum distance towards the cover to activate Stop&Shoot behaviour.

To Enemy Or To Cover	
Min Time Till Stop And Shoot Behaviour	Minimum time since Ai agent decided to go towards or between covers till he starts Stop&Shoot behaviour.
Max Time Till Stop And Shoot Behaviour	Maximum time since Ai agent decided to go towards or between covers till he starts Stop&Shoot behaviour.
Min Stop And Shoot Duration	Minimum duration in seconds of the Stop&Shoot behaviour.
Max Stop And Shoot Duration	Maximum duration in seconds of the Stop&Shoot behaviour.
Debug Distances	Values in this section will display the distance to target as well as random value between Min/Max SprintDistance and RunDistance.
Debug Distance To Target	Display the current distance to target.
Debug Sprint Distance	Display the random value of Min/Max SprintDistance.
Debug Run Distance	Display the random value of Min/Max RunDistance.