


Strafing

Introduction


This video will guide you on how to achieve 'Strafing' behaviour on the humanoid AI agent during combat state.

Agent Strafing

First enable 'Strafing' located in the combat state behaviour.[See the image below]



Enabling it will show Strafing options in the script which you can tweak to achieve the desired behaviour.



Fields	Info
Strafe Animations	Select the animation to play when Ai agent is moving forward, backward, right, left, etc., in combat state.
Force Custom Strafing	If enabled, Ai agent will move between Predefined Custom strafe directions specified in the field 'Custom Strafe Directions'. This becomes very useful when you want the Ai agent to strafe only in one or two directions, for example: strafing right or left.
Randomize Between Stop Or Strafe Cycles	If enabled, Ai agent will have a 50/50 chance of deciding whether to strafe and shoot or stop and shoot.
Min Time Between Stop Or Strafe Cycles	Minimum time to perform either Stop and shoot or Strafe and shoot cycles in case the checkbox named 'Randomize Between Stop Or Strafe Cycles' is enabled.
Max Time Between Stop	

Or Strafe Cycles	Maximum time to perform either Stop and shoot or Strafe and shoot cycles in case the checkbox named 'Randomize Between Stop Or Strafe Cycles' is enabled.
Min Time Till Next Strafe Direction	Minimum time to create a new strafe coordinate within the range specified above.
Max Time Till Next Strafe Direction	Maximum time to create a new strafe coordinate within the range specified above.
Enable Shooting Between Strafing	Combines shooting and strafing functionalities.
Enable Shooting Cycles	Enables strafing AI agent to have periods of aiming without actual shooting between shooting cycles. Otherwise, AI agent will continuously shoot at its target until this target is destroyed or no more ammo is left in the magazine, in which case AI agent will reload his weapon and continue firing at its target.
Shooting Probability	Adjust the slider value and decide what should be the shooting probability of this AI agent. The bigger the number, the higher the chances of the AI agent to consider shooting, and the smaller number will result in less chance of shooting.
Min Time Between Shooting Cycles	Minimal possible period of time for strafing and aiming weapon between shooting cycles (i.e., without actually firing it).
Max Time Between Shooting Cycles	Maximal possible period of time for strafing and aiming weapon between shooting cycles (i.e., without actually firing it).
	Minimal raycast checks to do if target is not in view during strafing.

Min Raycast When Enemy Lost	
Max Raycast When Enemy Lost	Maximum raycast checks to do if target is not in view during strafing.
Min Distance To Stop Charging At Enemy	Minimum distance to stop charging at enemy.
Max Distance To Stop Charging At Enemy	Maximum distance to stop charging at enemy.
Custom Strafing	Custom Strafing is based on a set of custom strafing points that allows to limit overall number and choice of available strafing directions for AI agent.
Strafe Points	This section stores all custom strafe points that represent their respective directions and define maximal possible strafing ranges (that can be limited by 'Min/Max time Till Next Strafe Direction' timer) by their actual distances from AI agent's root game object. Number of custom strafe points added to AI agent can be as low as one or two or all the way up to eight.
Procedural Strafing	This solution provides 360 strafing directions to AI agent. Actual distances of those directions will be also limited by 'Min/Max time Till Next Strafe Direction' timer same as custom strafe directions. Procedural strafing is more preferable for cases when AI agent is situated on small isolated Navmesh pieces as it will still allow AI agent to strafe within limited ranges like balcony, watch tower or a small roof or any enclosure of a small space.
Min Strafe Range	Minimum range to create a strafe coordinate for the AI agent to move from its current position.

Max Strafe Range	Maximum range to create a strafe coordinate for the Ai agent to move from its current position.
---------------------	---