

Weapon Firing Behaviour Part-2

Introduction

This is the Part-2 of Humanoid AI Weapon Firing Behaviour and in this part we have covered following topics - Shooting Options,Bullet spread,Projectiles Per Shot, Raycast Bullet Force and some important things to note.

Humanoid AI Weapon Firing Behaviour

Humanoid Ai Weapon Firing Behaviour (Script)

Script

HumanoidAiWeaponFiringBehaviour

Script Info

This script defines Ai agents weapon characteristics.

Projectile Name

AssaultRifleBullet

Projectiles Per Shot

5

Shooting Option

Raycast Shooting

▼ Bullet Spread

Enable Bullet Spread

☐

Min Bullet Spread Rotation Angle X

-3

Max Bullet Spread Rotation Angle X

3

Min Bullet Spread Rotation Angle Y

-3

Max Bullet Spread Rotation Angle Y

3

▼ Raycast Bullet Force

Add Raycast Force

☒

Min Raycast Force

200

Max Raycast Force

400

Min Upward Force

1

Max Upward Force

2

Min Right Force

0

Max Right Force

0

Min Left Force

0

Max Left Force

0

Min Backward Force

1

Max Backward Force

2

Min Forward Force

0

Max Forward Force

0

Fields	Info
Projectile Name	Copy and paste name of the projectile to be used with this weapon from the 'ObjectPooler' script into this field.
Projectiles Per Shot	

	Enter the number of the projectiles of the single shot of this weapon if you want this weapon to be shotgun. The spread of those projectiles is specified in 'BulletSpread' paragraph.
Shooting Option	Select one of the three available options for the kind of shooting that this weapon will utilise. RaycastShootingWithTracers is an option where those tracers are not dealing damage to targets and are there only for visuals.
Enable Bullet Spread	Toggle to enable or disable bullet spread for this weapon. When enabled, each shot will have a varying rotational offset as defined by the parameters below.
Min Bullet Spread Rotation Angle X	Negative value of the offset from the initial rotation of X axis in degrees.
Max Bullet Spread Rotation Angle X	Positive value of the offset from the initial rotation of X axis in degrees.
Min Bullet Spread Rotation Angle Y	Negative value of the offset from the initial rotation of Y axis in degrees.
Max Bullet Spread Rotation Angle Y	Positive value of the offset from the initial rotation of Y axis in degrees.
Add Raycast Force	If checked will apply raycast force to target.
Min Raycast Force	Minimal possible RayCastForce to be applied to target.
	Maximal possible RayCastForce to be applied to target.

Max Raycast Force	
Min Upward Force	Minimal possible RaycastForce to be applied to target in upward direction.
Max Upward Force	Maximal possible RaycastForce to be applied to target in upward direction.
Min Right Force	Minimal possible RaycastForce to be applied to target in right direction.
Max Right Force	Maximal possible RaycastForce to be applied to target in right direction.
Min Left Force	Minimal possible RaycastForce to be applied to target in left direction.
Max Left Force	Maximal possible RaycastForce to be applied to target in left direction.
Min Backward Force	Minimal possible RaycastForce to be applied to target in backward direction.
Max Backward Force	Maximal possible RaycastForce to be applied to target in backward direction.
Min Forward Force	Minimal possible RaycastForce to be applied to target in forward direction.
Max Forward Force	Maximal possible RaycastForce to be applied to target in forward direction.