

Air Support

Introduction

This video will guide you on how to setup the air support for the player.


Player Air Support Setup

Go to Tools < Mobile Action Kit < Player < Player < Create Air Support and assign the necessary gameObjects and components like shown in the video above. Your setup should look like this [See the image below].



Player Air Support Script

This script is responsible for 'CAS' (close air support) to player.



Fields	Info
AirSupportUIButton	Drag and drop the UI button from the hierarchy into this field.
PlayerCamera	Drag and drop player camera from player's hierarchy into this field.
TargetDesignatorRange	Range within which player can designate the target for close air support.
AirSupportPlanePrefab	Drag and drop the Jet prefab from the project into this field.
TargetDesignatorVisibleLayers	Specify the visible layers for raycasting.
JetSpawnAltitude	

	Air support spawn altitude from target point surface.
PayloadReleaseAltitude	Payload release altitude from target point surface.
MinSpawnPointDistanceFromHitPoint	Minimum distance from the target point at which the plane can be spawned.
MaxSpawnPointDistanceFromHitPoint	Maximum distance from the target point at which the plane can be spawned.
EnableDiveAttack	If checked, the plane will rotate on both X and Y axes to look at the target point until it reaches there. If unchecked, it will only rotate on the Y axis.
NumberOfPlanesToSpawn	Enter the number of planes to spawn.
MinPlaneSpawnDelay	Minimum delay before spawning the plane.
MaxPlaneSpawnDelay	Maximum delay before spawning the plane.
MinDistanceBetweenAircraft	If more than one plane is spawned, this specifies the minimum distance between them.
MaxDistanceBetweenAircraft	If more than one plane is spawned, this specifies the maximum distance between them.
MinTargetAreaRadius	If multiple planes are spawned, this sets the minimum offset from the target area to prevent collisions.
MaxTargetAreaRadius	If multiple planes are spawned, this sets the maximum offset from the target area to prevent collisions.
AttackTargetAreaFromTheRight	If checked, the plane will spawn from the right side of the player camera view.

AttackTargetAreaFromTheLeft	If checked, the plane will spawn from the left side of the player camera view.
AttackTargetAreaFromTheFront	If checked, the plane will spawn from the front side of the player camera view.
AttackTargetAreaFromTheRear	If checked, the plane will spawn from the rear side of the player camera view.
AirSupportButtonResetDelay	Duration (in seconds) before the UI button becomes interactable again after using air support.
ActivatedButtonColor	Specify the color of the UI button when it is interactable.
DeactivatedButtonColor	Specify the color of the UI button when it is not interactable.
AirSupportAvailabilityText	Drag and drop a 'TextMeshPro' text component from the hierarchy into this field to display the message of air support availability.
MessageIfAirSupportAvailable	Enter the message to display when air support is available.
MessageIfAirSupportUnavailable	Enter the message to display when air support is unavailable.
TextMessageDisplayDuration	Specify the duration (in seconds) for which the message will be displayed.