


This script regulates various parameters of player's grenade throwing functionality.



Fields	Info
GrenadeUtilizationType	Read-only. Type of grenade utilization, default is "Immediate Throw".
ImplementationOptions	Select one of the two implementation options for grenades: Instantiation or Object pooling.
NameInsideObjectPooler	This must be the exact same name as the one inside the Object Pooler.

KeepActive	Boolean field to keep the grenade system active.
DelayFirstThrowsOnly	Boolean field to delay only the first grenade throws.
PlayerCamera	Player camera from the hierarchy should be assigned to this field.
GrenadeAnimatorComponent	'GrenadeAnimations' GameObject with the respective Animator Controller from the player's hierarchy should be assigned.
GrenadeIcon	'Grenade' UI Image (icon) from the 2D Canvas should be assigned.
GrenadeThrowSound	'GrenadeThrow' AudioSource, which is a child of 'PlayerAudioSourceComponents' GameObject in the player's hierarchy, should be assigned.
GrenadePinSound	'GrenadePin' AudioSource, which is a child of 'PlayerAudioSourceComponents' GameObject in the player's hierarchy, should be assigned.
GrenadeSpawnPoint	'GrenadeSpawnPoint' child GameObject from the player's hierarchy should be assigned.
GrenadePrefab	Grenade prefab from the project tab should be assigned.
GrenadeSelectOrThrowUIButtons	List of UI buttons for selecting or throwing the grenade.
RequiredComponents	All required components should be placed into their respective fields.
PinSoundDelay	Specify the delay for pin removal sound playback.
GrenadeHandsActivationDelay	Delay for activating player's hands with grenade, regardless of the grenade utilization option (Immediate Throw or Selection).

GrenadeSpawnDelay	Specify the grenade prefab activation or instantiation delay to match the grenade throw animation.
MinAngle	Minimal possible angle for intended throw distance.
MaxAngle	Maximal possible angle for intended throw distance.
ForceToApply	Set the force to apply to the grenade prefab to achieve the desired throw distance.
ThrowPower	List of different throw ranges depending on the player's camera angle at the moment of the throw.
UiReactivationDelay	Delay before UI elements are reactivated.
UIDisabledColor	Color of the disabled UI image (e.g., Grey).
BeforeSelection	Specify UI elements to disable before the player's hands with a grenade appear (if 'Selection' was chosen in the grenade creation wizard).
UIToDisableBeforeThrow	Specify UI elements to disable during the grenade throw process (if 'Immediate Throw' was chosen in the grenade creation wizard).