

Simple Spawner

Introduction

In this tutorial you will learn how to setup simple spawner and spawn AI agents and any other gameObjects within a spawn point and collider volume.

Simple Spawner

Fields	Info
ShowGizmosInTheScene	Draw the spawning area gizmo in the Unity scene view.
GizmoColor	Set the color of the spawning area gizmos in the Unity scene view.
TriggeringGameObject	Drag & drop the game object (usually player) from the hierarchy into this field to trigger spawn events.
SpawnOnlyOnTriggerEnter	If checked, then the Spawnables will be spawned only if the player enters the trigger collider attached to the 'GeneralSpawner' game object.
SpawnableType	Choose one of the types of the Spawnable objects.
Spawnables	Assign game entities to be spawned by this spawner.
MinSpawnDelay	Minimum time between spawns.
MaxSpawnDelay	Maximum time between spawns.
SpawnWithinVolume	If checked, then AI agents or game objects will spawn within the volume of the trigger collider attached to the child game object of this 'GeneralSpawner' named 'SpawnVolume.' You will have to create it, add a trigger collider to it, and set up its dimensions to ensure that agents or game objects spawn only within certain rooms or other enclosed spaces.

SpawnVolume	Drag and drop 'SpawnVolume' child game object with the trigger collider attached to it into this field.
SpawnPoint	Drag and drop child game object named 'SpawnPoint' into this field.
AmountOfSpawnables	Number of agents this spawner script can spawn.
MinNonAiSpawnablesOffset	Minimal offset of non-AI 'Spawnables' from the spawn point along x, y, and z axis to space them out from each other.
MaxNonAiSpawnablesOffset	Maximal offset of non-AI 'Spawnables' from the spawn point along x, y, and z axis to space them out from each other.
AiSpawnPointRadius	Radius within which AI agents will be spawned.
AiUpdaterComponent	Drag and drop AI Updater game object from the hierarchy with 'AiUpdater' script attached to it into this field in case Spawnables of this spawner will be AI agents.

Simple Spawner

Static

Tag UntaggedLayer Ignore Raycast

Transform

Position

X25.4Y0.6677533Z-3.570557

Rotation

X0Y0Z0

Scale

X1Y1Z1

#

Simple Spawner (Script)

Script

SimpleSpawner

Script Info

This spawner can spawn any type of game entities (Ai or non Ai prefabs).And it starts functioning with the start of the game.

Show Gizmos In The Scene

Draw Wire Cube

Gizmo Color

Triggering Game Object

Player

Spawn Only On Trigger Enter

Spawnable Type

Game Object

Spawnables

1

Element 0

Mortar

+ -

Min Spawn Delay

1

Max Spawn Delay

2

Spawn Within Volume

Spawn Volume

Spawn Volume (Box Collider)

Spawn Point

Spawn Point (Transform)

Amount Of Spawnables

5

Min Non Ai Spawnables Offset

X-2Y0Z-2

Max Non Ai Spawnables Offset

X2Y0Z2

Ai Spawn Point Radius

5

Ai Updater Component

AI Updater (Ai Updater)

Box Collider

Edit Collider

Is Trigger

Material

None (Physic Material)

Center

X0Y0Z1.236664

Size

X5Y5Z15.76453

Add Component