Green Team Documentation
Team 11
The Grand-Master Association



Table of Contents

Accessing Public Website
Creating an Account
Placing an Order
Tracking Your Order
Administration SSH
Administrator Remote Desktop Protocol

Accessing public website

1. Click on firefox to open it. If it's not on the desktop, go to the search bar at the bottom or hit the windows key and search "Firefox"
2. In Firefox, go to the top address bar and type in "www.team11.isucdc.com"
3. This will take you to the home page of the website, it should look like the following:



Login to Customer

1. Follow all the steps listed in "Accessing public website" segment above before proceeding to step 3.

2. If you don't have an account, make sure to make one by following the steps listed in "Creating an Account" (you will already be logged in after completing "Creating an Account")
3. In the top right corner, hit the login button, it looks like the following:



4. Then, you should see a screen asking for your username and password, like the following:



5. Enter your username and password in their corresponding boxes
6. After filling out the form with your personal information, click the bright orange login button at the bottom.

Creating an Account

1. Follow the instructions in "Accessing public website" before proceeding.
2. In the top right corner, hit the login button, it looks like the following:



3. Then, you should see a screen asking for your username and password, click the link near the bottom of the from saying “Register here”, use the image below as reference:



4. you should then see the following screen:



5. Enter all your information and click register, you should then go to the instructions of “Login to Customer”, and complete your login.

Placing an Order

1. To place an order, after you log in, click on you name at the top right of the screen, next to the log out button. You should see the following screen:



(blue parts are redacted for privacy)

2. On this page, you need to scroll down and give it your address and card details. We use this information to place your order (cannot place an order without this information, so this step is important)
3. After filling out your information, submit it and hit the store button at the top of the screen as shown in the image below:



4. Then select any items you need and by adding them to cart (if you want more than 1 of something, click the add to cart more than once), as shown in the image below:



5. Then click the ready to checkout button on the left to proceed:



6. Then, just finalize your order and your order will be placed.

Tracking Your Order

1. Before you proceed, make sure you are logged in (if not go to “login to customer” and you have placed an order (if not go to “Placing an Order”)
2. Click orders in the top menu, like shown in the image below:



3. You should end up at a page like the one below, here you will be able to see any orders you have and track them (There is no order in this example image):



Administration SSH

1. For an IT admin to SSH into a machine, open the terminal by clicking on the windows button on the bottom right and typing terminal. Click terminal if in linux and command prompt if in windows. If you are already in the terminal, ignore this step.



2. After getting in to the Command Prompt, type in consecutively
   sudo systemctl start ssh
   sudo systemctl enable ssh
   Then type in sudo ssh (username)@ip address you want to connect to
   There is an ip address table below

Administrator Remote Desktop Protocol

1. For Linux Machines:
    a. Go to your terminal by searching “terminal” in the search bar.
    b. Type in the following, substituting your username, password, and the ip address of the machine you want to RDP into.
        i. “xfreerdp /u:USERNAME /p:PASSWORD /v:IP_ADDRESS”
2. For Windows Machines
    a. Go to your command prompt by searching “command prompt” in the search bar.
    b. Type in “mstsc /v:IP_ADDRESS” and substitute IP_ADDRESS for the ip of the machine you want to RDP into.



3. IP’s

Machine	IP
Active Directory	76.5.61.10

WWW	76.5.61.20/24
WMS	76.5.61.40/24
Label Printer	76.5.61.30
Database	76.5.61.50/24