

Cockpit parity · VM lifecycle ops

Disks, Compute & Devices

Attach disk · resize · CPU/memory · ISO · NIC · snapshots

Platform VM detail tabs for day-2 libvirt operations — not covered in Connect-hub decks 07–10.

Compute & Live usage

Overview tab — Cockpit-style metrics and hot topology edits.

Live usage panel

- CPU and memory bars (`vm-usage-bars`)
- Guest-agent metrics when QGA is online
- vCPU count shown in hero strip

Compute panel

- **Edit CPU** — topology modal (sockets/cores/threads)
- **Edit memory** — current vs maximum balloon sizing
- Live libvirt query: `cpu.memory.topology`

Action	Tab	API / libvirt
Change vCPU topology	Overview → Compute	<code>invokeVmLibvirt</code> CPU tune
Resize guest RAM	Overview → Compute	Memory balloon / max memory
View topology	Overview	<code>GET .../libvirt?action=cpu.memory.topology</code>

Attach, detach & **resize**

`?tab=disks · data-testid="vm-disks-panel"`

Libvirt inventory



Attach qcow2 path



Edit bus/cache



Resize GiB



Detach

Operation	UI	Notes
Attach disk	Path + target dev (vdb...)	<code>attachVmDisk</code> — requires managed VM
Detach disk	Per-row Detach	Queued libvirt detach by target
Resize block device	Select disk + GiB	<code>resizeVmDisk</code>
Edit disk	Bus, cache, readonly	<code>disk.tune</code> — virtio/sata/scsi/ide
CD-ROM insert / eject	Insert ISO panel + Eject on cdrom row	ISO scan, host browse, typed path; <code>cdrom.insert</code> / <code>cdrom.eject</code>
Platform disk records	Secondary list	<code>GET /vms/{id}/disks</code>

Platform Disks tab: ISO scan dropdown, host browse (`GET /browse/dir`), typed path, attach-disk browse — parity with classic VM detail CD-ROM dialog.

NIC, ISO & Passthrough

Network tab

- Live interface list from libvirt
- **Attach NIC** — libvirt network + model
- Hypervisor NAT panel (also on Access tab)
- `data-testid="vm-network-panel"`

Devices tab

- virtiofs shared directories
- Watchdog, vsock, TPM status
- USB / PCI passthrough inventory
- `data-testid="vm-devices-panel"`

ISO / install media

- Create VM from ISO: `/platform/create-iso`
- Advanced install wizard: storage + unattended
- Classic UI: insert/eject CD-ROM on running VM
- Security: path canonicalization on ISO paths

Advanced tab

- Host USB attach to guest
- PCI passthrough controls
- Domain XML editor (Settings/Advanced)

Snapshots, migrate & clone

Tab	Key operations
Snapshots	Create (disk-only / quiesce), revert, delete — <code>vm-snapshots-panel</code>
Settings	Live migrate pre-check + migrate; full/linked clone; retire VM
Backup	Export disk (qcow2), backup cards on Overview
Performance	Time-series CPU/memory/disk/network charts
Doctor / Guest health	GuestKit offline migration plan, QGA health

Tests & coverage gap

F01–F13 matrix covers Connect/Access only — disk/compute ops use separate suites.

Suite	Covers
<code>platform-cockpit-parity.spec.ts</code>	Edit CPU modal, usage bars, storage pools
<code>platform-live-vm-operations.spec.ts</code>	Attach disk, resize, Attach NIC, snapshots, migrate, devices
<code>platform-vm-lifecycle.spec.ts</code>	Lifecycle panels and API wiring
Decks 01, 03, 04, 05	High-level resize, ISO security, API endpoints

Extended matrix: **F14 Compute**, **F15 Disks**, **F16 Network/NIC**, **F17 Snapshots**, **F18 ISO/devices** — see deck 11.