

Alibutod, Rhina Mhay C.

Antonio, Clara Maris B.

De Vera, Ermhar A.

Ellio, James Young G.

Garcia, Cris Charles V.

Pasigan, Chineer R.

BASIC SERVER CONFIGURATION

Open Server Manager

- Server Manager usually opens automatically
- If not:
 - Click Start → Server Manager

Rename Server

1. Go to **Local Server**
2. Click Computer Name
3. Click **Change**
4. Enter new name (e.g., LAB-SERVER)
5. Restart computer

Configure IP Address (Static)

1. Go to:
 - Control Panel → Network and Sharing Center
2. Click **Change Adapter Settings**
3. Right-click Ethernet → Properties
4. Select **IPv4** → Properties
5. Set:
 - IP Address: 192.168.1.10
 - Subnet Mask: 255.255.255.0
 - Default Gateway: 192.168.1.1

USING SERVER MANAGER

Explore Server Manager

Observe:

- Dashboard
- Local Server
- Tools Menu

Task: List at least 3 features you see.

- **Dashboard** - can see the activated roles or the green ones and if unconfigured it is represented as red
- **Local Server- properties** which contain server's specification and information.
 - **Events** which show the warnings and errors in the local servers.
 - **Services** running micro services background for the server.
- **Tools Menu** - Shows all of the added roles and features in the server

INSTALLING SERVER ROLES

Add Roles and Features

1. Open **Server Manager**
2. Click **Manage** → Add Roles and Features
3. Click Next until **Server Roles**

Install DHCP Server Role

1. Check **DHCP Server**
2. Click Add Features
3. Click Next → Install

Configure DHCP

1. Go to Tools → DHCP
2. Right-click server → New Scope
3. Enter:
 - Name: LabScope
 - IP Range: 192.168.1.100 – 192.168.1.200
4. Activate scope

Install File Server Role

1. Go back to Add Roles
2. Select:
 - File and Storage Services
3. Install

FILE SHARING

Create Shared Folder

1. Create folder: C:\SharedFiles
2. Right-click → Properties
3. Go to **Sharing** tab
4. Click **Advanced Sharing**
5. Check:
 - Share this folder

Set Permissions

1. Click Permissions
2. Add:
 - Everyone → Allow Read/Write

Test Access (Client Side)

1. Open another PC
2. Press Windows + R
3. Type:

\\192.168.1.10

4. Access shared folder

VERIFICATION

✓ Check if:

- Server name is updated
- IP is correctly set
- DHCP is running
- File sharing works

AB QUESTIONS

1. What is the purpose of assigning a static IP?

To have a permanent address for easier access and manage reliably. It is also easier to organize and identify devices such as routers and servers.

2. What role does DHCP perform?


DHCP provides automatically assigning ip addresses to devices within the network. It eliminates the need to manually configure each device by automatically giving the correct information.



3. What happens if no server roles are installed?

If there are no server roles installed the server itself cannot provide services with other devices over the network.

4. Why is file sharing important in a network?

File sharing supports collaboration and centralization of a network. This promotes faster access and teamwork within a network.





RUBRIC

CriteriaPoints

Installation Completed	25
Configuration Correct	25
Roles Installed	25
Lab Questions	25
Total	100