■ NetApp

Get started

Astra

NetApp August 16, 2021

Table of Contents

| Get started | |
|---|--------------|
| Set up Microsoft Azure | |
| Register for an Astra Control account | |
| Start managing Kubernetes compute from Astra Co | trol Service |
| What's next? | |

Get started

Set up Microsoft Azure

A few steps are required to prepare your Microsoft Azure subscription before you can manage Azure Kubernetes Service clusters with Astra Control Service.

Quick start for setting up Azure

Get started quickly by following these steps or scroll down to the remaining sections for full details.



Review Astra Control Service requirements for Azure Kubernetes Service

Ensure that clusters are healthy and running Kubernetes version 1.17 or later, that node pools are online and running **Linux**, and more. Learn more about this step.



Register for Azure NetApp Files

Request access to the Azure NetApp Files service and then register the NetApp Resource Provider. Learn more about this step.



Create a NetApp account

In the Azure portal, go to Azure NetApp Files and create a NetApp account. Learn more about this step.



Set up capacity pools

Set up one or more capacity pools for your persistent volumes. Learn more about this step.



Delegate a subnet to Azure NetApp Files

Delegate a subnet to Azure NetApp Files so that Astra Control Service can create persistent volumes in that subnet. Learn more about this step.



Create an Azure service principal

Create an Azure service principal that has the Contributor role. Read step-by-step instructions.

AKS cluster requirements

A Kubernetes cluster must meet the following requirements so you can discover and manage it from Astra Control Service.

Kubernetes version

Clusters must be running Kubernetes version 1.17 or later.

Image type

The image type for all node pools must be Linux.

Cluster state

Clusters must be running in a healthy state and have at least one online worker node with no worker nodes in a failed state.

Azure region

Clusters must reside in a region where Azure NetApp Files is available. View Azure products by region.

Subscription

Clusters must reside in a subscription where Azure NetApp Files is enabled. You'll choose a subscription when you register for Azure NetApp Files.

VNet

- Clusters must reside in a VNet that has direct access to an Azure NetApp Files delegated subnet. Learn how to set up a delegated subnet.
- If your Kubernetes clusters are in a VNet that's peered to the Azure NetApp Files delegated subnet that's in another VNet, then both sides of the peering connection must be online.
- Be aware that the default limit for the number of IPs used in a VNet (including immediately peered VNets) with Azure NetApp Files is 1,000. View Azure NetApp Files resource limits.

If you're close to the limit, you have two options:

- You can submit a request for a limit increase. Contact your NetApp representative if you need help.
- When creating a new AKS cluster, specify a new network for the cluster. Once the new network is created, provision a new subnet and delegate the subnet to Azure NetApp Files.

Private networking

Private networking must not be enabled on a cluster.

External volume snapshot controller

Clusters must have a CSI volume snapshot controller installed. This controller is installed by default starting with K8s version 1.21, but you'll need to check on clusters running versions 1.17, 1.18, 1.19, or 1.20. Learn more about an external snapshot controller for on-demand volume snapshots.

Install a CSI volume snapshot controller

As noted in the list of requirements, Kubernetes clusters must have a CSI volume snapshot controller installed. Follow these steps to install the controller on your clusters.

Steps for K8s versions 1.17, 1.18, and 1.19

1. Install volume snapshot CRDs.

```
kubectl apply -f https://raw.githubusercontent.com/kubernetes-
csi/external-snapshotter/release-
3.0/client/config/crd/snapshot.storage.k8s.io_volumesnapshotclasses.yaml
kubectl apply -f https://raw.githubusercontent.com/kubernetes-
csi/external-snapshotter/release-
3.0/client/config/crd/snapshot.storage.k8s.io_volumesnapshotcontents.yam
l
kubectl apply -f https://raw.githubusercontent.com/kubernetes-
csi/external-snapshotter/release-
3.0/client/config/crd/snapshot.storage.k8s.io_volumesnapshots.yaml
```

2. Create the snapshot controller.

If you want the snapshot controller in a specific namespace, download and edit the following files before you apply them.

```
kubectl apply -f https://raw.githubusercontent.com/kubernetes-
csi/external-snapshotter/release-3.0/deploy/kubernetes/snapshot-
controller/rbac-snapshot-controller.yaml
kubectl apply -f https://raw.githubusercontent.com/kubernetes-
csi/external-snapshotter/release-3.0/deploy/kubernetes/snapshot-
controller/setup-snapshot-controller.yaml
```

Steps for K8s version 1.20

1. Install volume snapshot CRDs.

```
kubectl apply -f https://raw.githubusercontent.com/kubernetes-
csi/external-
snapshotter/v4.0.0/client/config/crd/snapshot.storage.k8s.io_volumesnaps
hotclasses.yaml
kubectl apply -f https://raw.githubusercontent.com/kubernetes-
csi/external-
snapshotter/v4.0.0/client/config/crd/snapshot.storage.k8s.io_volumesnaps
hotcontents.yaml
kubectl apply -f https://raw.githubusercontent.com/kubernetes-
csi/external-
snapshotter/v4.0.0/client/config/crd/snapshot.storage.k8s.io_volumesnaps
hots.yaml
```

2. Create the snapshot controller.

If you want the snapshot controller in a specific namespace, download and edit the following files before you apply them.

```
kubectl apply -f https://raw.githubusercontent.com/kubernetes-csi/external-snapshotter/v4.0.0/deploy/kubernetes/snapshot-controller/rbac-snapshot-controller.yaml kubectl apply -f https://raw.githubusercontent.com/kubernetes-csi/external-snapshotter/v4.0.0/deploy/kubernetes/snapshot-controller/setup-snapshot-controller.yaml
```

Register for Azure NetApp Files

Get access to Azure NetApp Files by submitting a waitlist request. After you're approved, you'll need to register the NetApp Resource Provider.

Steps

- 1. Submit a waitlist request to access Azure NetApp Files.
- 2. Wait for a confirmation email from the Azure NetApp Files team.
- Follow Azure NetApp Files documentation to register the NetApp Resource Provider.

Create a NetApp account

After you've been granted access, create a NetApp account in Azure NetApp Files.

Step

1. Follow Azure NetApp Files documentation to create a NetApp account from the Azure portal.

Set up a capacity pool

One or more capacity pools are required so that Astra Control Service can provision persistent volumes in a capacity pool. Astra Control Service doesn't create capacity pools for you.

Take the following into consideration as you set up capacity pools for your Kubernetes apps:

• A capacity pool can have an Ultra, Premium, or Standard service level. Each of these service levels are designed for different performance needs. Astra Control Service supports all three.

You need to set up a capacity pool for each service level that you want to use with your Kubernetes clusters.

Learn more about service levels for Azure NetApp Files.

• Before you create a capacity pool for the apps that you intend to protect with Astra Control Service, choose the required performance and capacity for those apps.

Provisioning the right amount of capacity ensures that users can create persistent volumes as they are needed. If capacity isn't available, then the persistent volumes can't be provisioned.

• An Azure NetApp Files capacity pool can use the manual or auto QoS type. Astra Control Service supports auto QoS capacity pools. Manual QoS capacity pools aren't supported.

Step

1. Follow Azure NetApp Files documentation to set up an auto QoS capacity pool.

Delegate a subnet to Azure NetApp Files

You need to delegate a subnet to Azure NetApp Files so that Astra Control Service can create persistent volumes in that subnet. Note that Azure NetApp Files enables you to have only one delegated subnet in a VNet.

If you're using peered VNets, then both sides of the peering connection must be online: the VNet where your Kubernetes clusters reside and the VNet that has the Azure NetApp Files delegated subnet.

Step

1. Follow the Azure NetApp Files documentation to delegate a subnet to Azure NetApp Files.

After you're done

Wait about 10 minutes before discovering the compute running in the delegated subnet.

Create an Azure service principal

Astra Control Service requires a Azure service principal that is assigned the Contributor role. Astra Control Service uses this service principal to facilitate Kubernetes application data management on your behalf.

A service principal is an identity created specifically for use with applications, services, and tools. Assigning a role to the service principal restricts access to specific Azure resources.

Follow the steps below to create a service principal using the Azure CLI. You'll need to save the output in a JSON file and provide it to Astra Control Service later on. Refer to Azure documentation for more details about using the CLI.

The following steps assume that you have permission to create a service principal and that you have the Microsoft Azure SDK (az command) installed on your machine.

Requirements

- The service principal must use regular authentication. Certificates aren't supported.
- The service principal must be granted Contributor or Owner access to your Azure subscription.
- The Azure subscription must contain the AKS clusters and your Azure NetApp Files account.

Steps

1. Identify the subscription and tenant ID where your AKS clusters reside (these are the clusters that you want to manage in Astra Control Service).

```
az configure --list-defaults
az account list --output table
```

2. Create the service principal, assign the Contributor role, and specify the scope to the entire subscription where the clusters reside.

```
az ad sp create-for-rbac --name http://sp-astra-service-principal --role contributor --scopes /subscriptions/SUBSCRIPTION-ID
```

3. Store the resulting Azure CLI output as a JSON file.

You'll need to provide this file so that Astra Control Service can discover your AKS clusters and manage Kubernetes data management operations. Learn about managing credentials in Astra Control Service.

4. Optional: Add the subscription ID to the JSON file so that Astra Control Service automatically populates the ID when you select the file.

Otherwise, you'll need to enter the subscription ID in Astra Control Service when prompted.

Example

```
"appId": "0db3929a-bfb0-4c93-baee-aaf8",
  "displayName": "sp-example-dev-sandbox",
  "name": "http://sp-example-dev-sandbox",
  "password": "mypassword",
  "tenant": "011cdf6c-7512-4805-aaf8-7721afd8ca37",
  "subscriptionId": "99ce999a-8c99-99d9-a9d9-99cce99f99ad"
}
```

5. Optional: Test your service principal.

```
az login --service-principal --username APP-ID-SERVICEPRINCIPAL --password PASSWORD --tenant TENANT-ID az group list --subscription SUBSCRIPTION-ID az aks list --subscription SUBSCRIPTION-ID az storage container list --subscription SUBSCRIPTION-ID
```

Register for an Astra Control account

Sign up to NetApp Cloud Central and then complete the registration process to obtain an Astra Control account.

Sign up to Cloud Central

Astra Control Service is integrated within NetApp Cloud Central's authentication service. Sign up to Cloud Central so you can access Astra Control Service and NetApp's other cloud services.



You can use single sign-on to log in to Cloud Central using credentials from your corporate directory (federated identity). To learn more, go to the Cloud Central Help Center and then click Cloud Central sign-in options.


Steps

- 1. Open your web browser and go to NetApp Cloud Central.
- 2. In the top right, click Sign up.

3. Fill out the form and click **Sign up**.



The email address that you enter in this form is for your NetApp Cloud Central user ID. Use this Cloud Central user ID when you sign up for a new Astra Control account, or when an Astra Control admin invites you to an existing Astra Control account.



- 4. Wait for an email from NetApp Cloud Central.
- 5. Click the link in the email to verify your email address.

Result

You now have an active Cloud Central user login.

Register for an account

Before you can log in to Astra Control, you need to complete a registration process to obtain an Astra Control account.

When you use Astra Control, you'll manage your apps from within an account. An account includes users who can view and manage the apps within the account, as well as your billing details.

Steps

- 1. Go to the Astra Control page on Cloud Central.
- 2. Click Sign up for the Free Plan.
- 3. Provide the required information in the form.

A few important things to note as you fill out the form:

- Your business name and address must be accurate because we verify them to meet the requirements of Global Trade Compliance.
- The Astra Account Name is the name of your business's Astra Control account. You'll see this name
 in the Astra Control user interface. Note that you can create additional accounts (up to 5), if that's
 required for your needs.

4. Click Submit.

If you're logged in to Cloud Central already, you'll see a registration status and then you'll be redirected to the Astra Control Dashboard. Otherwise, you'll be prompted to log in first.

Now that you're registered, you can access Astra Control directly from https://astra.netapp.io.

Start managing Kubernetes compute from Astra Control Service

After you set up your environment, you're ready to create a Kubernetes cluster and then add it to Astra Control Service.

Create a Kubernetes cluster

If you don't have a cluster yet, create one that meets Astra Control Service requirements for Azure Kubernetes Service (AKS).

Start managing Kubernetes compute

After you log in to Astra Control Service, your first step is to start managing compute.

What you'll need

or AKS, you should have the JSON file that contains the output from the Azure CLI when you created the service principal. Learn how to set up a service principal.

You'll also need your Azure subscription ID, if you didn't add it to the JSON file.

Steps

1. On the Dashboard, click Manage Kubernetes compute.

Follow the prompts to add the compute.

- Provider: Select your cloud provider and then provide the required credentials.
 - a. **Microsoft Azure**: Provide details about your Azure service principal by uploading a JSON file or by pasting the contents of that JSON file from your clipboard.

The JSON file should contain the output from the Azure CLI when you created the service principal. It

can also include your subscription ID so it's automatically added to Astra. Otherwise, you need to manually enter the ID after providing the JSON.

3. Compute: Select the compute that you'd like to add.


Pay careful attention to the Eligible tab. If a warning appears, hover over the warning to determine if there's an issue with the compute. For example, it might identify that the cluster doesn't have a worker node.

4. **Storage**: Select the storage class that you'd like Kubernetes applications deployed to this compute to use by default.

Each storage class utilizes Azure NetApp Files.

Learn about storage classes for AKS clusters.

5. Review & Approve: Review the configuration details and click Add compute.



Result

Astra Control Service creates an object store for application backups, creates an admin account on the cluster, and sets the default storage class that you specified. This process can take up to 5 minutes.

What's next?

Now that you've logged in and added compute to Astra Control, you're ready to start using Astra Control's application data management features.

· Start managing apps

- Protect apps
- Clone apps
- Set up billing
- Invite and manage users
- Manage cloud provider credentials
- Manage notifications

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.