

KDE Connect Manager - Quick Start Guide



Get Started in 5 Minutes

Step 1: Clone and Navigate

```
cd /home/ubuntu/kdeconnect-manager
```

Step 2: Run Installation

```
./scripts/install.sh
```

This will install all dependencies, configure firewall, and set up the system.

Step 3: Verify Installation

```
kdecm install check
```

Step 4: Start Using!

Option A: Web Interface (Recommended)

```
# Start the web server
kdecm server start

# Open browser to http://localhost:5000
```

Option B: Command Line

```
# List devices
kdecm device list

# Pair with a device
kdecm device pair DEVICE_ID

# Send a ping
kdecm device ping DEVICE_ID

# Check system health
kdecm health check
```



Pairing Your First Device

1. Ensure both devices are on the same network
2. Open KDE Connect on your phone/tablet
3. On your computer:

```
```bash
```

```
List available devices
kdecn device list

Pair with the device
kdecn device pair DEVICE_ID_HERE
...
```

4. **Accept the pairing request on your device**

5. **Done! Your devices are now connected**



## Common Commands

```
Device management
kdecn device list # List all devices
kdecn device info DEVICE_ID # Device details
kdecn device ping DEVICE_ID # Test connection
kdecn device battery DEVICE_ID # Check battery

Sharing
kdecn share file DEVICE_ID /path/to/file
kdecn share text DEVICE_ID "Your message"

Health
kdecn health check # Check system
kdecn health fix # Auto-fix issues
kdecn health restart # Restart daemon

Server
kdecn server start # Start web UI
```



## Web Interface Features

Access at **http://localhost:5000**

- 📱 **Devices Tab**: View and manage all devices
- ❤️ **Health Tab**: Monitor system health
- 📋 **Logs Tab**: View real-time event logs
- ⚙️ **Settings Tab**: Configure preferences



## Advanced Features

### Remote Management via SSH

```
Connect to remote machine and setup KDE Connect
python3 examples/remote_setup.py
```

## Screen Sharing

```
Auto-setup screen sharing
python3 -c "
from backend.screenshare.screen_manager import ScreenShareIntegration
screen = ScreenShareIntegration()
result = screen.setup_screen_sharing()
print(result)
"
```

## Health Monitoring

```
Start continuous monitoring
systemctl --user start kdeconnect-manager.service

View logs
journalctl --user -u kdeconnect-manager.service -f
```



## Troubleshooting

### Devices not showing up?

```
Check firewall
sudo firewall-cmd --list-all

Restart daemon
kdecm health restart

Check health
kdecm health check
```

### Pairing failed?

```
Unpair and try again
kdecm device unpair DEVICE_ID

Clear certificates
rm -rf ~/.config/kdeconnect/

Restart daemon
kdecm health restart
```

### Web interface not loading?

```
Check if running
systemctl --user status kdeconnect-manager.service

Restart
systemctl --user restart kdeconnect-manager.service

Check logs
tail -f logs/api.log
```

## Learn More

---

- **Full Documentation:** [README.md](#) (README.md)
- **API Reference:** [README.md#rest-api-endpoints](#) (README.md#rest-api-endpoints)
- **Examples:** `examples/basic_usage.py`
- **Configuration:** `config/config.example.yaml`

## Next Steps

---

1.  Pair your devices
2.  Explore the web interface
3.  Try sending files and notifications
4.  Set up automatic monitoring
5.  Configure screen sharing (optional)
6.  Explore remote management (optional)

---

**Need help?** Check the [README](#) (README.md) or run `kdecn --help`