
0
RESET N.O. Pushbutton
START
<Local:3:I.Data.14>
Part Feed Error Indicator
ERROR
<Local:4:O.Data.1>
STOP N.C. Pushbutton
STOP
<Local:3:I.Data.15>
Conveyor Motor
CONVEYOR
<Local:4:O.Data.0>
Conveyor Motor
CONVEYOR
<Local:4:O.Data.0>
(End)

Name	Value	Data Type	Scope
CONVEYOR	0	BOOL	Analog_Input
Conveyor Motor			
AliasFor:	Local:4:O.Data.0		
Base Tag:	Local:4:O.Data.0		
Constant	No		
External Access:	Read/Write		
OPC UA Access:	None		
CONVEYOR - Emulation/Emulate - 1(XIC), 9(XIC)			
*CONVEYOR - MainProgram/ConveyorControlRoutine - *0(OTE), 0(XIC)*			
ERROR	0	BOOL	Analog_Input
Part Feed Error Indicator			
AliasFor:	Local:4:O.Data.1		
Base Tag:	Local:4:O.Data.1		
Constant	No		
External Access:	Read/Write		
OPC UA Access:	None		
ERROR - MainProgram/ConveyorControlRoutine - 0(XIO)			
*ERROR - MainProgram/MainRoutine - *4(OTL), *5(OTU)*			
START	0	BOOL	Analog_Input
RESET N.O. Pushbutton			
AliasFor:	Local:3:I.Data.14		
Base Tag:	Local:3:I.Data.14		
Constant	No		
External Access:	Read/Write		
OPC UA Access:	None		
START - MainProgram/ConveyorControlRoutine - 0(XIC)			
STOP	1	BOOL	Analog_Input
STOP N.C. Pushbutton			
AliasFor:	Local:3:I.Data.15		
Base Tag:	Local:3:I.Data.15		
Constant	No		
External Access:	Read/Write		
OPC UA Access:	None		
STOP - MainProgram/ConveyorControlRoutine - 0(XIC)			
*Local:3:I.Data.15 - Emulation/Emulate - *0(OTL)*			


0
JSR
Routine Name Scale
1
JSR
Routine Name ConveyorControlRoutine
2
Part A N.O.
Proximity Switch
PART_A
<Local:3:I.Data.0>
Scaled EU Value from
Add On
GT
Source A HEIGHT
0
Source B PART_A_UPPER
45.0
Part A double part
PART_A_ERROR
3
Part B N.O.
Proximity Switch
PART_B
<Local:3:I.Data.1>
Scaled EU Value from
Add On
GT
Source A HEIGHT
0
Source B PART_B_UPPER
55.0
Part B double part
PART_B_ERROR
4
Part A double part
PART_A_ERROR
Part B double part
PART_B_ERROR
Part Feed Error
Indicator
ERROR
<Local:4:O.Data.1>
L
5
RESET N.O.
Pushbutton
RESET
<Local:3:I.Data.2>
Part Feed Error
Indicator
ERROR
<Local:4:O.Data.1>
U
(End)

Name	Value	Data Type	Scope
ERROR	0	BOOL	Analog_Input
Part Feed Error Indicator			
AliasFor:	Local:4:O.Data.1		
Base Tag:	Local:4:O.Data.1		
Constant	No		
External Access:	Read/Write		
OPC UA Access:	None		
ERROR - MainProgram/ConveyorControlRoutine - 0(XIO)			
*ERROR - MainProgram/MainRoutine - *4(OTL), *5(OTU)*			
HEIGHT	0	DINT	Analog_Input
Scaled EU Value from Add On			
Constant	No		
External Access:	Read/Write		
OPC UA Access:	None		
HEIGHT - MainProgram/MainRoutine - 2(GT), 3(GT)			
*HEIGHT - MainProgram/Scale - *0(Analog_In)*			
PART_A	0	BOOL	Analog_Input
Part A N.O. Proximity Switch			
AliasFor:	Local:3:I.Data.0		
Base Tag:	Local:3:I.Data.0		
Constant	No		
External Access:	Read/Write		
OPC UA Access:	None		
*PART_A - Emulation/Emulate - *11(OTE)*			
PART_A - MainProgram/MainRoutine - 2(XIC)			
PART_A_ERROR	0	BOOL	Analog_Input
Part A double part			
Constant	No		
External Access:	Read/Write		
OPC UA Access:	None		
*PART_A_ERROR - MainProgram/MainRoutine - *2(OTE), 4(XIC)*			
PART_A_UPPER	45.0	REAL	Analog_Input
Part A Upper Limit			
Constant	No		
External Access:	Read/Write		
OPC UA Access:	None		
PART_A_UPPER - MainProgram/MainRoutine - 2(GT)			
PART_B	0	BOOL	Analog_Input
Part B N.O. Proximity Switch			
AliasFor:	Local:3:I.Data.1		
Base Tag:	Local:3:I.Data.1		
Constant	No		
External Access:	Read/Write		
OPC UA Access:	None		
*PART_B - Emulation/Emulate - *12(OTE)*			
PART_B - MainProgram/MainRoutine - 3(XIC)			
PART_B_ERROR	0	BOOL	Analog_Input
Part B double part			
Constant	No		
External Access:	Read/Write		
OPC UA Access:	None		
*PART_B_ERROR - MainProgram/MainRoutine - *3(OTE), 4(XIC)*			
PART_B_UPPER	55.0	REAL	Analog_Input
Part B Upper Limit			
Constant	No		
External Access:	Read/Write		

PART_B_UPPER (Continued)

OPC UA Access:	None

PART_B_UPPER - MainProgram/MainRoutine - 3(GT)

RESET	0	BOOL	Analog_Input

RESET N.O. Pushbutton

AliasFor:	Local:3:I.Data.2
Base Tag:	Local:3:I.Data.2
Constant	No
External Access:	Read/Write
OPC UA Access:	None

RESET - Emulation/Emulate - 10(XIC), 11(XIO), 12(XIO), 14(XIC), 15(XIC)
RESET - MainProgram/MainRoutine - 5(XIC)


0
Add On Instruction
Tag for Analog
Scalling
Analog_In
Analog_In HEIGHT_SCALE ...
Raw_Max 32767
Raw_Min 0
EU_Max 100
EU_Min 0
Analog_Ch HEIGHT_SENSOR
<Local:5:I.Ch0Data>
0.0
EU_Value HEIGHT
0
(End)

Name	Value	Data Type	Scope
HEIGHT	0	DINT	Analog_Input
Scaled EU Value from Add On			
Constant	No		
External Access:	Read/Write		
OPC UA Access:	None		
HEIGHT - MainProgram/MainRoutine - 2(GT), 3(GT)			
*HEIGHT - MainProgram/Scale - *0(Analog_In)*			
HEIGHT_SCALE		Analog_In	MainProgram
Add On Instruction Tag for Analog Scalling			
Constant	No		
External Access:	Read/Write		
OPC UA Access:	None		
*HEIGHT_SCALE - MainProgram/Scale - *0(Analog_In)*			
HEIGHT_SCALE.EnableIn	1	BOOL	
Add On Instruction Tag for Analog Scalling Enable Input - System Defined Parameter			
HEIGHT_SCALE.EnableOut	1	BOOL	
Add On Instruction Tag for Analog Scalling Enable Output - System Defined Parameter			
HEIGHT_SCALE.Raw_Max	32767.0	REAL	
Add On Instruction Tag for Analog Scalling Maximum Bit Balue			
HEIGHT_SCALE.Raw_Min	0.0	REAL	
Add On Instruction Tag for Analog Scalling			
HEIGHT_SCALE.EU_Max	100.0	REAL	
Add On Instruction Tag for Analog Scalling			
HEIGHT_SCALE.EU_Min	0.0	REAL	
Add On Instruction Tag for Analog Scalling			
HEIGHT_SCALE.Analog_Ch	0.0	REAL	
Add On Instruction Tag for Analog Scalling			
HEIGHT_SCALE.EU_Value	0.0	REAL	
Add On Instruction Tag for Analog Scalling			
HEIGHT_SENSOR	0.0	REAL	Analog_Input
Height Sensor for Add On			
AliasFor:	Local:5:I.Ch0Data		
Base Tag:	Local:5:I.Ch0Data		
Constant	No		
External Access:	Read/Write		
OPC UA Access:	None		
*HEIGHT_SENSOR - Emulation/Emulate - *10(MOVE), *3(MOVE), *4(MOVE), *5(MOVE), *6(MOVE), *7(MOVE), *8(MOVE)*			
HEIGHT_SENSOR - MainProgram/Scale - 0(Analog_In)			

Signature Listing

Analog_In v1.0

Available Languages

Relay Ladder



Function Block



Structured Text

```
Analog_In(Raw_Max, Raw_Min, EU_Max, EU_Min, Analog_Ch, EU_Value);
```

Parameters

Required	Name	Data Type	Usage	Description
X	Analog_In	Analog_In	InOut	
	EnableIn	BOOL	Input	
	EnableOut	BOOL	Output	
X	Raw_Max	REAL	Input	Maximum Bit Balue
X	Raw_Min	REAL	Input	
X	EU_Max	REAL	Input	
X	EU_Min	REAL	Input	
X	Analog_Ch	REAL	Input	
X	EU_Value	REAL	Output	

Extended Description

Execution

Condition	Description
EnableIn is true	

Revision v1.0 Notes

Name	Default	Data Type	Scope
Analog_Ch	0.0	REAL	Analog_In
Usage:	Input Parameter		
Required:	Yes		
Visible:	Yes		
External Access:	Read/Write		
OPC UA Access:	None		
Analog_Ch - Analog_In/Logic - #1			
EU_Max	0.0	REAL	Analog_In
Usage:	Input Parameter		
Required:	Yes		
Visible:	Yes		
External Access:	Read/Write		
OPC UA Access:	None		
EU_Max - Analog_In/Logic - #4			
EU_Min	0.0	REAL	Analog_In
Usage:	Input Parameter		
Required:	Yes		
Visible:	Yes		
External Access:	Read/Write		
OPC UA Access:	None		
EU_Min - Analog_In/Logic - #5			
EU_Value	0.0	REAL	Analog_In
Usage:	Output Parameter		
Required:	Yes		
Visible:	Yes		
External Access:	Read/Write		
OPC UA Access:	None		
*EU_Value - Analog_In/Logic - *#7*			
Raw_Max	0.0	REAL	Analog_In
Maximum Bit Balue			
Usage:	Input Parameter		
Required:	Yes		
Visible:	Yes		
External Access:	Read/Write		
OPC UA Access:	None		
Raw_Max - Analog_In/Logic - #2			
Raw_Min	0.0	REAL	Analog_In
Usage:	Input Parameter		
Required:	Yes		
Visible:	Yes		
External Access:	Read/Write		
OPC UA Access:	None		
Raw_Min - Analog_In/Logic - #3			

Name	Default	Data Type	Scope
Analog		SCALE	Analog_In
Data Type for Add On Instruction			
Usage:	Local Tag		
External Access:	None		
OPC UA Access:	None		
*Analog - Analog_In/Logic - *#6*			
Analog.EnableIn	1	BOOL	
Data Type for Add On Instruction			
Analog.In	0.0	REAL	
Data Type for Add On Instruction			
*Analog.In - Analog_In/Logic - *#1*			
Analog.InRawMax	0.0	REAL	
Data Type for Add On Instruction			
*Analog.InRawMax - Analog_In/Logic - *#2*			
Analog.InRawMin	0.0	REAL	
Data Type for Add On Instruction			
*Analog.InRawMin - Analog_In/Logic - *#3*			
Analog.InEUMax	0.0	REAL	
Data Type for Add On Instruction			
*Analog.InEUMax - Analog_In/Logic - *#4*			
Analog.InEUMin	0.0	REAL	
Data Type for Add On Instruction			
*Analog.InEUMin - Analog_In/Logic - *#5*			
Analog.Limiting	0	BOOL	
Data Type for Add On Instruction			
Analog.EnableOut	0	BOOL	
Data Type for Add On Instruction			
Analog.Out	0.0	REAL	
Data Type for Add On Instruction			
Analog.Out - Analog_In/Logic - #7			
Analog.MaxAlarm	0	BOOL	
Data Type for Add On Instruction			
Analog.MinAlarm	0	BOOL	
Data Type for Add On Instruction			
Analog.Status	16#0000_0000	DINT	
Data Type for Add On Instruction			
Analog.InstructFault	0	BOOL	
Data Type for Add On Instruction			
Analog.InRawRangeInv	0	BOOL	
Data Type for Add On Instruction			

```
Analog.In := Analog_Ch;
Analog.InRawMax := Raw_Max;
Analog.InRawMin := Raw_Min;
Analog.InEUMax := EU_Max;
Analog.InEUMin := EU_Min;
SCL(Analog);
EU_Value := Analog.Out;
```