EOF-1 Basic definitions

telmich

2007-11-22 v0.2-train

Contents

1	Introduction 3					
	1.1	Changelog	3			
		1.1.1 v0.1 to v0.2	3			
		1.1.2 v0.1	3			
2	Ver	sions	3			
	2.1	Protocol	3			
	2.2	Major number	3			
	2.3	Minor number	3			
	2.4	Patchlevel	4			
	2.5	Valid from	4			
	2.6	Programs	4			
3	Cor	nnections	4			
J	3.1	Sockets	4			
	3.2	Stdin and stdout	4			
4	Environment 4					
	4.1	HOME	4			
	4.2	CEOF_DIR	4			
	4.3	CEOF_CLIENT_SOCKET	_			
5	Pat	hs	5			
	5.1	Ceof configuration directory	-			
	0.1	5.1.1 Default case				
		5.1.2 HOME is unset				
		5.1.3 CEOF_DIR is set				

	5.2	Ceof client socket	5
		5.2.1 CEOF_CLIENT_SOCKET is set	5
6	Dat	atypes	5
	6.1	ASCII numbers	5
	6.2	Binary numbers	5
	6.3	Strings	5
	6.4	Variable length strings	6
	6.5	Fixed length strings	6

1 Introduction

This document specifies the basic datatypes and connection methods used in EOF-1. The aim is to stop repeatition of datatype definition in other documents.

1.1 Changelog

1.1.1 v0.1 to v0.2

• Add versions specification

1.1.2 v0.1

• Initial release

2 Versions

This section clearifies the use of versions in the programs and protocols.

2.1 Protocol

The version of a protocol consists of

- major number,
- minor number and
- the patchlevel

An increment of either number must be reflected with a protocol version change within the protocol definition.

2.2 Major number

Within one major number the same aim should be followed. For instance version "'0.x.y"' could target the first release.

2.3 Minor number

Within one minor number the same functionality should be kept. For instance "'0.1.y"' contains basic functionality, "'0.2.y"' could contain complete new functionality.

2.4 Patchlevel

The patchlevels are used to correct mistakes, but do not change the API.

2.5 Valid from...

All protocol definitions (includings drafts) that are released after **20071122** should follow this version numbering scheme.

2.6 Programs

3 Connections

3.1 Sockets

Sockets are named Unix sockets.

3.2 Stdin and stdout

To make programming easier, communication between some parts in EOF-1 is realised using stdin and stdout.

4 Environment

Environment variable are set from the operating system or from the user. The following environment variables are used with EOF-1:

4.1 **HOME**

Home directory of the user.

4.2 CEOF_DIR

Ceof configuration directory.

4.3 CEOF_CLIENT_SOCKET

The socket that the clients (GUIs) should use. Relative to the directory specified by CEOF_DIR.

5 Paths

5.1 Ceof configuration directory

5.1.1 Default case

Normally, \$HOME is set and \$CEOF_DIR is not set. In that case the configuration directory defaults to \$HOME/.ceof.

5.1.2 HOME is unset

If the environment variable "'HOME" is not set, the directory named .ceof in the current directory will be used.

5.1.3 CEOF_DIR is set

If the environment variable "'CEOF_DIR" is set, its content will be used to refer to the configuration directory.

5.2 Ceof client socket

The client connects to a socket named *clients/socket*, relative to the configuration directory.

5.2.1 CEOF_CLIENT_SOCKET is set

If the environment variable CEOF_CLIENT_SOCKET is set, "'clients/socket"' should be replaced by its content.

6 Datatypes

6.1 ASCII numbers

ASCII numbers use the string representation of a number and 4 Byte, used when other programming langua Excluding 0

6.2 Binary numbers

Between some parts of EOF-1 are binary numbers (as in *uint32*) exchanged.

6.3 Strings

Strings are transmitted without termination (i.e. no new line, no 0 byte).

6.4 Variable length strings

Before variable length strings the length is submitted in a fixed size datatype.

6.5 Fixed length strings

Fixed length strings must be padded with 0 Bytes, if they are shorter than the defined length.