

nmcli Command cheatsheet



Usage

```
$ nmcli [OPITONS] OBJECT { COMMAND | help }
```

Display the command syntax and lists all available options

```
$ nmcli --help
```

General Commands

COMMANDS	DESCRIPTION
\$ nmcli general status	Show overall status of NetworkManager
\$ nmcli general permissions	Show permissions for controlling NetworkManager
\$ nmcli general reload	Reload NetworkManager's configuration
\$ nmcli device show	List all network devices
\$ nmcli device show <interface>	Show details of a specific interface
\$ nmcli device connect <interface>	Connect to a network using the specified interface
\$ nmcli device disconnect <interface>	Disconnect the specified interface
\$ nmcli	Show network status
\$ nmcli general hostname <hostname>	Set system hostname

nmcli Options

OPTION	DESCRIPTION
-a	Ask for missing parameters
-c	Whether to use colors in the output
-e	Escape columns separators in values
-f	Specify fields to output
-g	Shortcut for -m tabular -t -f
-h	Display help message and exit
-m	Output mode
-o	Overview mode
-p	Pretty output
-s	Allow displaying passwords
-t	Terse output
-w	Set timeout waiting for finishing operations



nmcli

Managing Connections

COMMAND	DESCRIPTION
\$ nmcli connection show	List all configured connections
\$ nmcli connection up <name>	Activate a connection
\$ nmcli connection down <name>	Deactivate a connection
\$ nmcli connection add type ethernet	Create a new Ethernet connection
\$ nmcli connection add type wifi ssid <name>	Create a new Wi-Fi connection
\$ nmcli connection delete <name>	Delete a connection
\$ nmcli connection add type <type>	Add a new connection (e.g., ethernet, wifi, vpn, etc.)
\$ nmcli connection modify <connection> <setting>	Modify a connection

Setting a Static IP Address

COMMAND	DESCRIPTION
\$ nmcli connection modify <connection> ipv4.addresses <address>/<prefix>	Set static IP address
\$ nmcli connection modify <connection> ipv4.gateway <gateway>	Set the gateway
\$ nmcli connection modify <connection> ipv4.dns <dns>	Set DNS server
\$ nmcli connection modify <connection> ipv4.method manual	Enable manual IP configuration
\$ nmcli connection modify <connection> ipv4.method auto	Enable automatic IP configuration



Important

When you modify a connection with nmcli, the changes take effect when the connection is reactivated. Simply modifying the connection settings doesn't immediately apply the changes to the device.

To ensure the changes take effect, run:

```
# List connections
$ nmcli connection show

# Deactivate the connection
$ nmcli connection down <connection-name>

# Reactivate the connection
$ nmcli connection up <connection-name>
```

Working with Wi-Fi

COMMAND	DESCRIPTION
\$ nmcli device wifi list	List available Wi-Fi networks
\$ nmcli device wifi connect <SSID> password <password>	Connect to a Wi-Fi network
\$ nmcli device wifi rescan	Rescan for available Wi-Fi networks
\$ nmcli device wifi show-password	Show the password for a Wi-Fi network
\$ nmcli connection add type wifi ssid <name>	Create a new Wi-Fi connection
\$ nmcli connection delete <name>	Delete a connection