/mode

Set agent role mode: /mode architect|coder|reviewer|debugger|tester|off|help

Overview

`/mode` switches the agent's role mode for the current session. Role modes bias the system prompt and tool emphasis toward a named discipline: architecture review, coding, code review, debugging, testing, or none. The chosen mode applies to subsequent turns until cleared or changed.

Input is lowercased before matching, so `/mode ARCHITECT` works. Two forms beyond the registry description are accepted by the dispatcher: `status` behaves like the bare form, and `normal` is an accepted alias of `off`.

Syntax

```
/mode                       # show the current mode
/mode status                # same as bare form
/mode architect|coder|reviewer|debugger|tester   # activate a mode
/mode off                   # clear the mode (alias: normal)
/mode help
```

Options / Subcommands

Form	Description
`/mode`	Show the currently active role mode
`/mode status`	Same as the bare form
`/mode architect`	Activate the architect role mode
`/mode coder`	Activate the coder role mode
`/mode reviewer`	Activate the reviewer role mode
`/mode debugger`	Activate the debugger role mode
`/mode tester`	Activate the tester role mode
`/mode off`	Clear the mode and return to normal
`/mode normal`	Accepted alias of `off`
`/mode help`	Print usage help

Examples

Check the current mode:

`/mode`

Switch to review work:

`/mode reviewer`

Switch to coding:

`/mode coder`

Clear the mode:

```
/mode off
```

Clear via the alias:

```
/mode normal
```

Case-insensitive selection:

```
/mode ARCHITECT
```

Output

Activation (mode icon varies by role):

```
<icon> mode: <label>
```

Clearing:

```
[ok] Role mode cleared - back to normal mode.
```

Unknown mode (the available list is echoed):

```
Unknown mode '<x>'. Available: architect coder reviewer debugger tester off
```

Bare form and `status` show the active mode name, or the normal-mode equivalent when none is set.

Related

- `/agent` - switch the whole agent preset (broader than a role mode)
- `/system` - override the system prompt directly
- `/plan` - delegate a planning task to the plan agent