

/goal

Set or clear the goal-driven loop goal (/goal set|clear|show|test)

Overview

/goal manages the goal used by the goal-driven agentic loop. In this build /goal set and /goal clear only print confirmations - the goal is not yet persisted to session storage - and /goal show and /goal test always report that no goal is set. See the limitations note below before relying on this command.

Syntax

```
/goal          Show the usage block
/goal set <description> Set the goal description
/goal clear    Clear the goal
/goal show     Show the current goal
/goal test     Test the goal condition
/goal help     Show the usage block
```

Options / Subcommands

Form	Description
/goal	Alias of the help form; prints the usage block, including the example goal and the note that the goal is evaluated after each turn
/goal set <description>	Builds a goal condition from the description and prints a confirmation
/goal clear	Prints a confirmation that the goal was cleared
/goal show	Prints the current goal state
/goal test	Evaluates the goal condition
/goal help	Alias of the bare form

Unknown subcommands print Usage: /goal set|clear|show|test|help.

Examples

```
/goal set Stop when all tests pass and the build succeeds
```

The example goal from the usage block; prints a confirmation.

```
/goal set Remove all compiler warnings in crates/ragent-config
```

Sets a custom goal description and prints the confirmation.

```
/goal clear
```

Prints the confirmation that the goal was cleared.

```
/goal show
```

Prints No goal is currently set.

```
/goal test
```

Prints `No goal is currently set to test.`

Output

- Bare form and help: the usage block with the example `/goal set Stop` when all tests pass and the build succeeds.
- `set / clear`: confirmation messages only.
- `show`: always prints `No goal is currently set.` in this build.
- `test`: always prints `No goal is currently set to test.` in this build.

Current limitations

- `/goal set` and `/goal clear` are confirmations only. The goal is **not** persisted to session storage in this build, so it does not survive a restart and is not consumed by the loop yet.
- Consequently `/goal show` and `/goal test` always report that no goal is set, regardless of whether a `/goal set` was issued earlier in the session.

Related

- `/loop` - the goal-driven agentic loop with verification gates
- Goal conditions are defined by `GoalCondition` in the `ragent-agent` crate