

/mode

Set agent role mode: `/mode architect|coder|reviewer|debugger|tester|off|help`

Overview

`/mode` switches the agent's role mode for the current session. Role modes bias the system prompt and tool emphasis toward a named discipline: architecture review, coding, code review, debugging, testing, or none. The chosen mode applies to subsequent turns until cleared or changed.

Input is lowercased before matching, so `/mode ARCHITECT` works. Two forms beyond the registry description are accepted by the dispatcher: `status` behaves like the bare form, and `normal` is an accepted alias of `off`.

Syntax

```
/mode                # show the current mode
/mode status         # same as bare form
/mode architect|coder|reviewer|debugger|tester  # activate a mode
/mode off            # clear the mode (alias: normal)
/mode help
```

Options / Subcommands

Form	Description
<code>/mode</code>	Show the currently active role mode
<code>/mode status</code>	Same as the bare form
<code>/mode architect</code>	Activate the architect role mode
<code>/mode coder</code>	Activate the coder role mode
<code>/mode reviewer</code>	Activate the reviewer role mode
<code>/mode debugger</code>	Activate the debugger role mode
<code>/mode tester</code>	Activate the tester role mode
<code>/mode off</code>	Clear the mode and return to normal
<code>/mode normal</code>	Accepted alias of <code>off</code>
<code>/mode help</code>	Print usage help

Examples

Check the current mode:

```
/mode
```

Switch to review work:

```
/mode reviewer
```

Switch to coding:

```
/mode coder
```

Clear the mode:

`/mode off`

Clear via the alias:

`/mode normal`

Case-insensitive selection:

`/mode ARCHITECT`

Output

Activation (mode icon varies by role):

`<icon> mode: <label>`

Clearing:

`[ok] Role mode cleared - back to normal mode.`

Unknown mode (the available list is echoed):

Unknown mode '`<x>`'. Available: `architect coder reviewer debugger tester off`

Bare form and status show the active mode name, or the normal-mode equivalent when none is set.

Related

- `/agent` - switch the whole agent preset (broader than a role mode)
- `/system` - override the system prompt directly
- `/plan` - delegate a planning task to the plan agent