

G.E.T.S. Manager

User Manual

Version 2.0.0

GreekSoft Technologies Pvt. Ltd.

Siddivinayak Arcade, 3rd floor,

Akruli Cross Road No. 1,

Kandivali (E),

Mumbai

Proprietary Notice


This document contains confidential information of GreekSoft Technologies Pvt. Ltd., which is provided for the sole purpose of permitting the recipient to application help document submitted herewith. In consideration of receipt of this document, the recipient agrees to maintain such information in confidence and to not reproduce or otherwise disclose this information to any person outside the group directly responsible for evaluation of its contents, except that there is no obligation to maintain the confidentiality of any information which was known to the recipient prior to receipt of such information from GreekSoft Technologies Pvt. Ltd., or becomes publicly known through no fault of recipient, or is received without obligation of confidentiality from a third party owing no obligation of confidentiality to GreekSoft Technologies Pvt. Ltd.

INDEX

- I. GMX CTCL Manager*
- II. Configuring Exchange Connection Settings*
- III. CTCL Client Communicator*
- IV. GMX Database*
- V. Message Re-download on exchange disconnection*


I. GMX CTCL Manager

G.E.T.S. Multiple Exchange (GMX) CTCL Manager is the server side application which manages the client requests, process with exchange and communicates back to client. The architecture of G.E.T.S. CTCL is depicted below.



GETS Manager is the main GUI from which all the server operations will be carried out. When the GETS Manager is started in BOD, first all the security master files will be uploaded automatically and then all other applications will be started. All applications that run on G.E.T.S. Manager are listed below.

- CTCL Client Communicator
- NSE Interactive
- NSE EQ Broadcast
- NSE FO Broadcast
- BSE Interactive
- BSE Broadcast
- GATS (GETS Automated Trading System)
- NCDEX Interactive (Optional as per setting in 'Style.txt')
- NCDEX Broadcast (Optional as per setting in 'Style.txt')
- MCX Interactive (Optional as per setting in 'Style.txt')
- MCX Broadcast (Optional as per setting in 'Style.txt')



All actions that the user can do from Manager Application are

Manager -> Upload Security / Contract – Upload Master files of selected exchanges

The screenshot shows a window titled "Upload contract & security". It contains four main sections for different exchanges:

- NSE:** Contains five rows, each with a checked checkbox, a label, a text box with a file path, and a "Path" button.
 - ☒ Contract: c:\contract.txt
 - ☒ Spd Contract: c:\spd_contract.txt
 - ☒ Security: c:\security.txt
 - ☒ Participant: c:\participant.txt
 - ☒ FO Participant: c:\fo_participant.txt
- BSE:** Contains two rows, each with a checked checkbox, a label, a text box with a file path, and a "Path" button.
 - ☒ Scrip: c:\SCRIP.MAS
 - ☒ Scrip Details: c:\SCRIPDET.MAS
- MCX:** Contains one row with an unchecked checkbox, a label, an empty text box, and a "Path" button.
 - ☐ MCXScripts
- NCDEX:** Contains two rows, each with an unchecked checkbox, a label, an empty text box, and a "Path" button.
 - ☐ Ncdex Contract
 - ☐ Ncdex Participant

An "UPLOAD" button is located at the bottom right of the window.

Manager -> Exchange Login & Logoff – To login & logoff from exchange for interactive

Tools -> Exchange Connection Setting – Set the interactive and broadcast settings

Tools -> Customized Setting – Customize the manager font and appearance settings

Tools -> Download Port setting – Define ports range on server side, on which client will communicate with manager

Tools -> License Information – Displays product license information

Tools -> Client Login Information – Displays client login across multiple products

Tools -> Delete Pending Orders – To delete pending orders across segments of the selected exchanges and user

Tools -> Pending Order Settings – Option to delete the pending orders of the selected exchanges upon manager logoff and login

Tools -> Stored Order Response – To store the exchange order response messages in database

Tools -> Refresh – To fill Greek Client Id for all trades

Tools -> Order Trade Ratio – Displays the Orders to Trades ratio dealer-wise in NSE

Utility -> Start Applications – Start all applications as mentioned above

Utility -> Stop Applications – Stop all applications as mentioned above


Utility -> Reset Connection – To reset the exchange connectivity, Disconnects the existing connections and makes the process ready for accepting fresh connections

II. Configuring Exchange Connection Settings

The user can access the settings dialog from Tools -> Exchange Connection Setting. All exchange parameters (interactive and broadcast), CTCL / IML IDs to be defined here.

NSE Setting

When the user calls the Connection settings, the dialog opens as below.



Market Segment – Equity / Derivatives

Login by – Trader

User ID – CTCL ID of the respective market segment

Member ID – Trading Member ID

Password – CTCL ID password

New Password – In case, if the user wants to change the CTCL ID password, he needs to click on 'Set new Password' button -> enter the new password -> Click Modify -> Enter security password -> OK -> Setting is Modified -> OK -> Cancel -> Enter Password -> Modify -> Enter security password -> OK -> Setting is Modified -> OK.

When the user clicks on details button, it will show all the connection parameters. He has to set the proper interactive and broadcast parameters.

Branch ID	NEAT Branch ID
Version No	NEAT Version (Update latest version, in case of version change in NSE)
Work Station No	Not required in case of TAP
Port No	Not required in case of TAP
Local Address	Not required in case of TAP
EICON Card	Not required in case of TAP
Receive Broadcast	Either X.25 Broadcast / NSE TAP Broadcast If X.25, input call data & host address If TAP, Enter Multicast address – Multicast IP configured on TAP Port – Input respective port to receive normal / fast broadcast, as per selected market segment IP Address – GETS Manager IP address
Interactive	Either X.25 / TAP IP If X.25, input call data & host address If TAP, Enter Server IP – TAP Server IP for the selected segment Host Address – Interactive Port as per selected market segment

Send Broadcast to Client

UDP Multicast	If client selects ALL broadcast mode Multicast Address – Define at server level Port – Define at server level
UDP Portfolio	If client selects Subscribed broadcast mode Multicast Address – Define at server level Port – Define at server level
Send to Client	Define the broadcast reception to client Yes – Send the broadcast to client for the selected exchange segment No – Do not send the broadcast to client for the selected exchange segment
TCP/IP	If client connects through internet Local IP Address – Define at server level Port – Define at server level

Connection Setting

NSE Setting | BSE Setting | MCX Setting | NCDEX Setting

Market Segment: EQUITY

Login by: ☐ Branch Manager ☒ Trader ☐ Corporate Manager

User Id: 26662 Member Id: 07782

Password: ***** New Password:

Branch ID: 41 Version no: 90900 Work Station no: 1234567 Port no: 1

Local Address: 1234567 Eicon Card: 1

Receive Broadcast

☐ X25 BroadCast ☒ NSE Server BroadCast

Call Data: Unknown Multicast Address: 233 . 1 . 2 . 10

Host Address: Port: 4501 IP Address: 192.168.206.61

Send Broadcast

UDP

Multicast Address: 234 . 1 . 2 . 6 Port: 9901

UDP Portfolio

Multicast Address: 232 . 1 . 2 . 6 Port: 9902

Send to Client

☐ Yes ☒ No

Interactive

☐ Only X25

Call Data: unknown Host Address:

☒ IP

Server IP: 192.168.206.61 Host Address: 9609

TCP/IP

Local IP Address: 192.168.206.61 Port: 50000

III. CTCL Client Communicator

CTCL Client Communicator is the key process of GETS which handles all communication between client and manager applications. Various messages that are processed through client communicator include

- Process login / logoff requests from clients
- Validate for proper license
- Verify / Update the database
- Validate for risk limits
- Process messages with exchange interactive processes
- Backup the database (Store data from GreekDB to SQL)
- Restore the backup (Store data from SQL to GreekDB)
- Disconnect any client
- Upload Open Position

If the 'GreekDB.db' file is deleted and also there is disconnection from exchange, then user must upload the existing trades from SQL database using utility -> restore database. Then all orders and trades information will be recorded to GreekDB.db file upon which he can login to exchange. This rules out the zero download of messages from NSE.

IV. GMX Database

There are two databases that are being managed by GETS Manager.

GreekDB Database – *Online resident database managed on daily basis (location C drive)*
MS SQL Database – *Online backend database maintains historical data*

All the messages will be updated simultaneously on both the databases.

GMX SQL database can be configured on Manager itself. All the user management information, surveillance information, orders and trades information, audit logs will be recorded and updated in the GMX SQL database online.

The SQL database machine IP address must be defined in 'database.txt' file under GMX manager folder. Below is the content of database.txt file.


InitialCatalog=GMX	<- GETS Database
DataSource=192.168.0.32	<- Database IP
Uid=sa	<- SQL User Name
Pwd=greek@123	<- SQL Password
DSN=N	<- DSN=Y, if configured, else DSN=N
DBPROCESS = Y	<- DBPROCESS must be Y

V. Message Re-download on exchange disconnection

Whenever there is a disconnection from exchange, the order and trade messages during the period can be downloaded by updating the number of seconds in the registry.

Go to run and type regedit which will open the registry. Expand HKEY_CURRENT_USER -> Software -> GREEK CTCL -> CTCL Manager -> Connection Settings -> EiconCard No 1 -> Port No 1. On right side pane, select the field NSESequenceNoDiff and right click Modify, which will open Edit String dialog. Enter Value Data as the number of seconds. For e.g., if the field value is set as 60, then after login to exchange the trades from last trade time recorded in the database less 60 seconds will be downloaded.

After updating the registry, the manager needs to be closed and started. Login to ADMIN terminal and login to exchange segments. This will start downloading the messages for the time updated in registry. After complete download, Manager will display message 'System Ready for Trading', after which all clients can login and start trading.



* If NSESequenceNoDiff field is not present in the registry, add the same by right click New -> String Value.

-----END OF DOCUMENT-----