

It's important to adjust your page setup as soon as possible so that the application can accurately display your document on the screen. (This feature, called What You See Is What You Get, or WYSIWYG, allows you to lay out your document on the screen and be sure that your final printout will look pretty much the same.)

The actual appearance of the Page Setup dialog depends on which printer you've selected in the Control Panel, since each printer supports different paper sizes and resolutions. We'll cover the ImageWriter Page Setup dialog (Figure 7D) in detail, then pointing out the parts of other such dialogs that differ from the ImageWriter dialog.

At the top of the Page Setup dialog you'll always see your printer's name and the port it's connected to. In this case, we've got an ImageWriter connected to the Printer port. (Other choices for the printer include StyleWriter, ImageWriter LQ, and Epson; other choices for the port include Modem port, Parallel Card, or AppleTalk. The LaserWriter Page Setup dialog simply says "LaserWriter.") If this information is not correct, use the DC Printer or Net Printer Control Panels to choose a printer. (More information on these Control Panels appears in Chapter 9.)

Next, the ImageWriter Page Setup dialog has a pop-up menu to select the paper size. The ImageWriter supports standard U.S. and international paper sizes, as well as #6 envelopes and a variety of labels. (Other printers may support fewer sizes and use radio buttons rather than a pop-up menu to choose among them.)

Below that is a pop-up menu to select the document's intended print size—either full-sized, or reduced to 50%. Some printers have more choices here—the ImageWriter LQ lets you select 33% or 66% sizes (but not 50%) and the LaserWriter has a line-edit field that lets you select any percentage reduction (less than 100%) or enlargement (greater than 100%). The Epson driver has a checkbox for 50% adjustment.

The two checkboxes below allow you to select No Vertical Gaps (blank space at the top or bottom of pages) and Vertical Condense. The IIGS screen doesn't have a square aspect ratio—that is, if you draw a square on the screen with exactly the same number of dots both horizontally and vertically, it will look like a tall rectangle because the dots aren't square.

If Vertical Condense is turned off, what appears on your printer will look just like what's on your screen—if you draw a circle that looks right on your screen, it will look right on the printer. However, most text will look too tall. If you turn on Vertical Condense, text will be the right size but graphics may look squashed.

The Epson driver displays radio buttons for selection of Normal or Condensed Vertical Sizing. These are the same as Vertical Condense off and on, respectively. The LaserWriter allows you to select Normal (same as Vertical Condense off), Intermediate (a compromise setting that squashes graphics a little and stretches text a little), and Condensed (same as Vertical Condense on). The StyleWriter supports Normal (Graphics) and Condensed (Text) settings.

Finally, in the ImageWriter Page Setup dialog, you can select upright (portrait) or sideways (landscape) printing modes. Most other printers (except for the StyleWriter) also print sideways or upright.