


```
zone "ducnhu.thi" IN {
type master;
file "ducnhu.thi.dns";
};

zone "8.8.8.in-addr.arpa" IN {
type master;
file "8.8.8.dns";
};
```



```
8.8.8.dns
                                ducnhu.thi.dns
       named.conf
TTL
 IN SOA ns.ducnhu.thi. root.ducnhu.thi. (
      1
      2
      3
      4
      5)
      IN NS ns.ducnhu.thi.
      IN MX 10 mail.ducnhu.thi.
      IN A 8.8.8.9
S
      IN A 8.8.8.9
ww
ail
      IN A 8.8.8.9
```

```
#mydestination = $myhostname, localhost.$mydomain, localhost
mydestination = $myhostname, localhost.$mydomain, localhost, $mydomain
   #mydestination = $myhostname, localhost.$mydomain, localhost, $mydomain,
           mail.$mydomain, www.$mydomain, ftp.$mydomain
   # REJECTING MAIL FOR UNKNOWN LOCAL USERS
 inet interfaces = all
 #inet_interfaces = $myhostname
 #inet interfaces = $myhostname, localhost
 #inet interfaces = localhost
 # Enable IPv4, and IPv6 if supported
 inet protocols = all
# The proxy_interfaces parameter specifies the network interface
 |mynostname - mart.uutnnu.tnr
  # The mydomain parameter specifies the local internet domain name.
  # The default is to use $myhostname minus the first component.
  # $mydomain is used as a default value for many other configuration
  # parameters.
  mydomain = ducnhu.thi
  # SENDING MAIL
 # DEFINENT TO HIVTEDOV
# The home_mailbox parameter specifies the optional pathname of a
  # mailbox file relative to a user's home directory. The default
  # mailbox file is /var/spool/mail/user or /var/mail/user. Specify
  # "Maildir/" for qmail-style delivery (the / is required).
  #home mailbox = Mailbox
  home mailbox = Maildir/
  # The mail spool directory parameter specifies the directory where
  # UNIX-style mailboxes are kept. The default setting depends on the
  # system type.
```