

Vivado SDK 2019.1 - JTAG Terminal

helloWorld_000.sdk - Debug - helloWorld_000/src/helloworld.c - Xilinx SDK

File Edit Source Refactor Navigate Search Project Run Xilinx Window Help

Quick Access

Debug

System Debugger using Debug_helloWorld_000.elf on Local (Local)

APU

- ARM Cortex-A9 MPCore #0 (Breakpoint: main)
 - 0x0010058c main(): ./src/helloworld.c, line 55
 - 0x001007f0 _start(): xil-crt0.S, line 138
 - ...
- ARM Cortex-A9 MPCore #1 (Suspended)

xc7z020

Variables Breakpoi... Registers XSCT Co... Emulatio... Modules

XSCT Process

```
xsct% jtagterminal
64088
xsct%
```

system.hdf system.mss helloworld.c

```
/* Copyright (C) 2009 - 2014 Xilinx, Inc. All rights reserved.

/*
 * helloworld.c: simple test application
 *
 * This application configures UART 16550 to baud rate 9600.
 * PS7 UART (Zynq) is not initialized by this application, since
 * bootrom/bsp configures it to baud rate 115200
 *
 * -----
 * | UART TYPE   BAUD RATE |
 * -----
 * uarts550     9600
 * uartlite     Configurable only in HW design
 * ps7_uart     115200 (configured by bootrom/bsp)
 */

#include <stdio.h>
#include "platform.h"
#include "xil_printf.h"

int main()
```

Outline

- stdio.h
- platform.h
- xil_printf.h
- main() : int

Console Tasks SDK Terminal Problems Executables

TCF Debug Virtual Terminal - ARM Cortex-A9 MPCore #1

SDK Log Memory

Monitors

Writable Smart Insert 55 : 1

C:\Xilinx\SDK\2019.1\bin\unw x + v - □ x

JTAG-based Hyperterminal.
Connected to JTAG-based Hyperterminal over TCP port : 64974
(using socket : sock712)
Help :
Terminal requirements :
 (i) Processor's STDOUT is redirected to the ARM DCC/MDM UART
 (ii) Processor's STDIN is redirected to the ARM DCC/MDM UART.
 Then, text input from this console will be sent to DCC/MDM's UART port.
NOTE: This is a line-buffered console and you have to press "Enter"
 to send a string of characters to DCC/MDM.