

Certificate Creation for accessing SDR User Interface and API's

Certificate can be created by using any one of the below two options.

- PowerShell
- Open SSL

Option 1: Certificate generation with Open SSL

- 1. Install the Open SSL.
- 2. Run the OpenSSL Command Prompt and set the directory to the folder where certificate to be stored.

```
Win64 OpenSSL Command Prompt

OpenSSL 3.0.3 3 May 2022 (Library: OpenSSL 3.0.3 3 May 2022)

built on: Ned May 4 02:41:48 2022 UTC

platform: VC-VIN64A

options: bn(64,64)

compiler: ci. /Z7 /Fdossl_static.pdb /Gs0 /GF /Gy /MD /W3 /wd4090 /nologo /O2 -DL_ENDIAN -DOPENSSL_PIC -D_USING_V110_SDK71_ -D_WINSOCK_DEPRECATED_NO_WARNINGS -D_WIN32_WINNT=
0x8502

OPENSSLDIR: "C:\Program Files\Common Files\SSL"

ENSINESDIR: "C:\Program Files\OpenSSL\lib\understands-3"

WOOLESDIR: "C:\Program Files\OpenSSL\lib\understands-3"

Seeding source: os-specific

CPUINFO: OPENSSL_32cap=0xfedaf383ffcbffff:0x1c2fbb

::\Users\hp\Desktop\certificate

C:\Users\hp\Desktop\Certificate>
```

3. Run the below command → provide **Enter PEM pass phrase** and save the pass phrase to provide it on the command to generate .pfx certificate.

openssl req -x509 -newkey rsa:4096 -sha256 -keyout my.key -out my.crt -subj "/CN=test.com" -days 600



4. Run the below command to generate the .pfx certificate

openssI pkcs12 -export -name "test.com" -out my.pfx -inkey my.key -in my.crt




Provide the below details

Enter pass phrase for my.key: Provide the pass phrase passed on step 3
Enter Export Password: Provide the password for .pfx certificate and save it for later use.

5. Exported .pfx certificate will be stored on the folder path provided on step 1.

Note: Share the .pfx certificate and the export password to get access to SDR API's.




Option 2: Certificate generation with PowerShell

1. Open PowerShell and run the below command to generate the self-signed certificate






2. To Export the certificate in .pfx format, go to run → type certmmgr.msc and click ok



3. In certificate manager go to personal → certificates → select the generated certificate and right click select All Tasks → Select Export.




4. In Certificate Export Wizard click Next to continue.






5. Select export the private key option and click next.




6. Leave the defaults and click next.






7. Provide the password for certificate and click next.




8. Select the path to save the certificate.





9. Click on Finish.



10. Exported .pfx certificate will be stored on the folder path provided on step 7.

Note: Share the .pfx certificate and the password provide on step 8 to get access to SDR API's.