



PREMIA **Version 11**

Masters **User Manual**

Copyright

Information used in this document is subject to change without notice. Companies, names, and the data used in the examples herein are fictitious – unless otherwise noted. No part of this document can be reproduced or transmitted in any format, by any means; electronic or mechanical, for any purpose, without permission of 3i Infotech Ltd.

Any documentation or information for external use such as advertising, press releases, or promotional materials requires prior written approval from 3i Infotech Ltd.

Copyright 2014. 3i Infotech Ltd. All rights reserved.

Disclaimer

This documentation has been produced to complement the software developed and marketed by 3i Infotech Ltd., a registered Indian company with limited liability. The document accompanies the software, made available through a license.

This document has been created with good intention, and the company does not take responsibility if it is put to for any malicious use.

The document is original in content and presentation and is protected by international copyright law. Hence, the company places restriction on any part of the written material being disclosed or reproduced.

Though the document has been written with utmost care and concentration, there may be a few typographical errors, technical or functional inaccuracies and omissions. The readers are requested to report these to the content development team at 3i Infotech Ltd. However, the company may not be held responsible for the damages that have been caused by following what is written in the document.

3i Infotech reserves the right to change in part or full, the contents of the document without prior intimation to its users. The users are also advised to closely relate the document's version to the software in use.

3i Infotech welcomes feedback to improvise the written material in of the document. However, we cannot give more than our appreciation to the effort input by the reader.

The products other than those developed by 3i Infotech mentioned in the document are mere references. They belong to their respective owners, and 3i Infotech does not take responsibility to inefficiencies in this software.

Screen shots provided are representative and may or may not contain all the fields explained in the user manual. All data displayed in the screenshots are meant for demonstration purposes and is not intended to refer to any existing person or organization.

Table of Contents

System Parameter	15
Codes Master	16
Welcome to Codes Master	16
General	18
State	19
Motor	20
Vehicle Make	22
Marine Cargo	22
Marine Hull	23
Fire	23
Engineering	24
Aviation	25
Bonds	26
Claims	26
Product Master	27
Surplus / Mudharabah Rule	28
Line of Business	30
Section Master	31
Policy Type	32
Cover Master	33
Condition Master	34
Deductible Master	35
Discount Master	36
Loading Master	37
Cover Group	39
SMI Master	40
SMI Group Master	41
Installment Pay Setup Master	42
Product Setup	43
Vehicle Query Mapping (Setting up vehicle or shipment query)	77
Vehicle Query Column Mapping (Dynamic mapping – risk Summary)	79
Customer	80
Customer Category	81
Customer Code Creation	83
Insured Code Creation	95
Rating	101
Section Parameter	102
Cover Parameter	104
Charges Setup	109
Premium Computation Sheet Setup	111
Short Period Rate Setup Master	113
VAT/Tax Master	115
Document Setup	117
Quotation	118

Policy	121
Endorsement.....	131
Claims	134
Claim Intimation.....	137
Document Number Generation	137
Account Setup	141
Premium Account Setup.....	142
Transaction Account Setup.....	145
Miscellaneous Account Setup.....	146
Customer Account Setup	148
Claims Account Setup	150
RI Account Setup.....	152
RI Premium Accounts Setup	152
RI Miscellaneous Account Setup	154
RI Claims Account Setup	157
Treaty Account Set Up	160
RI Treaty Account Setup.....	160
Claims OSLR Account Setup	164
UPR/IBNR Account Setup.....	166
Unearned Premium Reserve (UPR).....	166
Incurred but not reported (IBNR).	166
Account Document Flexi Field Setup.....	168
Config	168
Header.....	168
Detail	168
Mapping	169
Motor Certificate.....	170
Certificate Book Master	170
Marketing	172
Introduction.....	172
Agency Commission Setup	172
Agency Commission Variant.....	172
Agency Commission Rate.....	174
Cover Note.....	175
Cover Note Entry.....	175
Cover Note Transaction	177
Cover Note Issue to Office	179
Cover Note Receiving	180
Claims Master.....	181
Nature of Loss Master	182
Cause of Loss Master	183
Reserve Setup.....	184
Checklist.....	185
Definition	185
Master Setup	187

Variants.....	188
Flexi Setup.....	189
Loss Flexi / Product Flexi Definition.....	189
Event Code Master	190
Claim Status Master	191
Claim Close/Reopen Reason.....	192
Spare Parts Master	192
Court Detail Master.....	193
IDV (Insured Declared Value) Calculation Setup	194
Application Setup.....	195
UW Form Interface.....	196
LOV Definition.....	197
History Instance Copy.....	199
User	200
Reports	204
Header Block.....	205
User Approval Setup	207
User Group Id.....	212
Workflow / DMS Setup	213
Step 1 – Enable Workflow/DMS related System parameter	213
Step 2 – Define the Bucket Code based on Transaction.....	214
Step 3 – Map User's Approval	216
Step 4 – Map E-mail Id to respective User / User Group to trigger mails	216
Step 5 – Capture mobile number to trigger SMS to user / user group	216
Step 6 – Configure Workflow setup in DMS application	217
Workflow	218
Admin	221
Step 7 – Perform Workflow Transaction	225
Step 8 – Transaction Using DMS.....	226
Menu	228
Reinsurance.....	229
Masters	229
Setup.....	229
Admin and Tools	230
Menu Administration.....	230
User Group.....	230
User.....	231
Menu Parameter Maintenance.....	236
Menu Screens	236
User Group Privileges	238
Report Boiler Plate	239
User Profile	240
Program Registration Instances	242
Program Registration Process	242

Program Definition	243
Instance Definition.....	247
Instance Copy	261
PREMIA Product Configurator	262
Product Setup Tool	262
Product Changer.....	270
Product Changer Query	270
Najm Net Processing Masters	271
Najm-Net Applicable Product Mapping	271
Najm-Net Field Mapping.....	271
Najm Status Query	272
Business Rule Master.....	276
Business Rule Relation Master	276
Business Rule Definition Master.....	281

Table of Figures

Fig. 1 – Masters Menu	14
Fig. 2 – Parameter Setup Screen.....	15
Fig. 3 – Masters – Codes Masters	17
Fig. 4 – General Codes	18
Fig. 5 – State Master	19
Fig. 6 – Division.....	20
Fig. 7 – Motor Sub-menu	21
Fig. 8 – Vehicle Make.....	22
Fig. 9 – Marine Cargo Sub-menu.....	22
Fig. 10 – Marine Hull Sub-menu	23
Fig. 11 – Fire Master Sub-menu	24
Fig. 12 – Engineering Sub-menu	24
Fig. 13 – Medical Sub-menu	25
Fig. 14 – Bonds Sub-menu	26
Fig. 15 – Claims Sub-menu.....	26
Fig. 16 – Product Master	27
Fig. 17 – Surplus / Mudharabah Rule Master	28
Fig. 18 – Lines of Business	30
Fig. 19 – Section Master	31
Fig. 20 – Policy Type Master	32
Fig. 21 – Cover Master.....	33
Fig. 22 – Condition Master	34
Fig. 23 – Deductible Master	35
Fig. 24 – Branches	36
Fig. 25 – Discount Master	36
Fig. 26 – Loading Master	37
Fig. 27 – Cover Group.....	39
Fig. 28 – SMI Master	40
Fig. 29 – SMI Group Master	41
Fig. 30 – Installment Pay Setup Master	42
Fig. 31 – Product Setup	43
Fig. 32 – Applicable Divisions	46
Fig. 33 – Applicable Conditions	46
Fig. 34 – Applicable Deductibles.....	48
Fig. 35 – Applicable Discounts.....	49
Fig. 36 – Applicable Loading.....	51
Fig. 37 – Other Details	52
Fig. 38 – Illustration 1 – Section to one Product/Policy Type	57
Fig. 39 – Illus 2 –Policy Type within a product are mapped to multi sections	57
Fig. 40 – Section Tab	59
Fig. 41 – Block Definition	61
Fig. 42 – Single Record View.....	62
Fig. 43 – Multi Record View	63
Fig. 44 – Applicable Discounts.....	65
Fig. 45 – Applicable Loading.....	65

Fig. 46 – Field Definition	66
Fig. 47 – Mandatory Column.....	69
Fig. 48 – Applicable Validation.....	69
Fig. 49 – Applicable Cover	70
Fig. 50 – Field Value	73
Fig. 51 – Applicable SMI	74
Fig. 52 – Flexi Setup	75
Fig. 53 – Cumulative Bonus.....	76
Fig. 54 – IBNR.....	77
Fig. 55 – Risk Summary Detail	78
Fig. 56 – Dynamic Mapping – Risk Summary.....	79
Fig. 57 – Customer Menu.....	80
Fig. 58 – Customer Category	81
Fig. 59 – Default Tax.....	82
Fig. 60 – Customer Setup	83
Fig. 61 – Applicable Divisions	85
Fig. 62 – Residential Address	86
Fig. 63 – Office Address.....	87
Fig. 64 – Prompt Message for VAT Registration Number	87
Fig. 65 – Commercial Details	88
Fig. 66 – Currency.....	89
Fig. 67 – Agent.....	89
Fig. 68 – Broker.....	90
Fig. 69 – Surveyor	90
Fig. 70 – Advocate	91
Fig. 71 – Credit Details.....	91
Fig. 72 – EFT	92
Fig. 73 – Stop List	93
Fig. 74 – Tax	94
Fig. 75 – Insured Master Details	95
Fig. 76 – Residential Address	97
Fig. 77 – Office Address.....	98
Fig. 78 – Duplicate Insured Names.....	98
Fig. 79 – Employee Details	99
Fig. 80 – Credit Card Details.....	100
Fig. 81 – Commercial Details	100
Fig. 82 – Rating Setup	101
Fig. 83 – Section Parameter	102
Fig. 84 – Rating Cover Parameter Setup.....	104
Fig. 85 – Tariff/Rating Parameter.....	106
Fig. 86 – Premium Logic	107
Fig. 87 – Tariff Data	108
Fig. 88 – Taxes and Charges Setup Master	109
Fig. 89 – Premium Computation Sheet Setup	111
Fig. 90 – Premium Computation Sheet Setup – Cover.....	112
Fig. 91 – Premium Computation Sheet Setup – Product.....	112
Fig. 92 – Premium Computation Sheet Setup – Taxes and Charges.....	113
Fig. 93 – Short Period Rate Setup Master	113

Fig. 94 –	VAT/Tax Master	115
Fig. 95 –	Document Setup Menu	117
Fig. 96 –	Quotation Setup	118
Fig. 97 –	Policy Setup	121
Fig. 98 –	Applicable Branches	126
Fig. 99 –	Applicable Products	126
Fig. 100 –	Default Charges.....	127
Fig. 101 –	Applicable Section.....	127
Fig. 102 –	Print Setup.....	128
Fig. 103 –	Policy Level Conditions	129
Fig. 104 –	To Do List	130
Fig. 105 –	Endorsement	131
Fig. 106 –	Claims.....	134
Fig. 107 –	Schedule Setup	136
Fig. 108 –	Claim Intimation - First Notice Loss.....	137
Fig. 109 –	Document Number Generation	138
Fig. 110 –	Level Details	139
Fig. 111 –	Range Setup.....	141
Fig. 112 –	Account Setup Menu	141
Fig. 113 –	Premium Account Setup.....	142
Fig. 114 –	Advance Premium Details	144
Fig. 115 –	Transaction Code Setup.....	145
Fig. 116 –	Miscellaneous Account Setup	146
Fig. 117 –	Customer Account Setup	148
Fig. 118 –	Claims Account Setup	150
Fig. 119 –	RI Premium Account Setup	152
Fig. 120 –	RI Miscellaneous Account Setup.....	155
Fig. 121 –	RI Claims Account Setup	158
Fig. 122 –	RI Treaty Account Setup	160
Fig. 123 –	Claims OSLR/IBNR Account Setup.....	164
Fig. 124 –	UPR/IBNR Account Setup.....	166
Fig. 125 –	Config Screen.....	168
Fig. 126 –	Flex Field Mapping	169
Fig. 127 –	Motor Certificate Book Master	170
Fig. 128 –	Certificate Details	171
Fig. 129 –	Certificate – Product Details.....	172
Fig. 130 –	Marketing menu.....	172
Fig. 131 –	Agency Commission Set Up.....	172
Fig. 132 –	Agency Commission Variant	173
Fig. 133 –	Agency Commission Rate	174
Fig. 134 –	Cover Note Entry	176
Fig. 135 –	Cover Note Transaction	177
Fig. 136 –	Manual Cover Note – Issue/Return	179
Fig. 137 –	Manual Cover Note – Receipt	180
Fig. 138 –	Sub-menus – Claims Master	181
Fig. 139 –	Nature of Loss Master	182
Fig. 140 –	Cause of Loss Master	183
Fig. 141 –	Reserve Setup.....	184

Fig. 142 –	Checklist Sub-menu	185
Fig. 143 –	Checklist Definition	186
Fig. 144 –	Checklist – Checklist Master Setup	187
Fig. 145 –	Checklist Variants	188
Fig. 146 –	Loss Flexi Definition	189
Fig. 147 –	Hint Text	190
Fig. 148 –	Event Code Master	190
Fig. 149 –	Claim Status Master	191
Fig. 150 –	Reason Master	192
Fig. 151 –	Spare Parts Master	192
Fig. 152 –	Court Master	193
Fig. 153 –	IDV Master	194
Fig. 154 –	Application Setup	195
Fig. 155 –	UW Form ID	196
Fig. 156 –	LOV Definition	197
Fig. 157 –	History Instance Copy	199
Fig. 158 –	User	200
Fig. 159 –	Company	202
Fig. 160 –	Division	202
Fig. 161 –	Department	203
Fig. 162 –	Copy User	204
Fig. 163 –	Reports	204
Fig. 164 –	Reports Column Headings Tab	206
Fig. 165 –	Reports – Parameter Tab	206
Fig. 166 –	Parameter screen	207
Fig. 167 –	User Authorization Setup	207
Fig. 168 –	User Authorization – Underwriting	208
Fig. 169 –	User Authorization – Claims	210
Fig. 170 –	User Authorization – Reinsurance	211
Fig. 171 –	User Authorization – Applied Endorsement	212
Fig. 172 –	User Group ID	212
Fig. 173 –	Parameter Setup for Workflow	213
Fig. 174 –	Workflow/DMS Setup	214
Fig. 175 –	Bucket Code	214
Fig. 176 –	Work step Mapping	215
Fig. 177 –	Mail User Group	215
Fig. 178 –	Mail Group Id	216
Fig. 179 –	PREMIA DMS - Login screen	217
Fig. 180 –	PREMIA Workflow Menu	217
Fig. 181 –	E-Mail Template	218
Fig. 182 –	Success Message	218
Fig. 183 –	View E-mail History	219
Fig. 184 –	Filter Criteria	219
Fig. 185 –	Turn Around Time	220
Fig. 186 –	Shift Time and Turn Around	221
Fig. 187 –	Maintain User	222
Fig. 188 –	Maintain User – new user added	223
Fig. 189 –	Synchronize	224

Fig. 190 –	Upload User.....	224
Fig. 191 –	Mapping Folder(s) to User.....	225
Fig. 192 –	PREMIA Quotation Screen.....	225
Fig. 193 –	Transaction Screens for DMS	226
Fig. 194 –	Policy Transaction – Complete status	227
Fig. 195 –	DMS Dashboard	228
Fig. 196 –	DMS – Menu Listing	228
Fig. 197 –	Admin and Tools – Menus and Submenus	230
Fig. 198 –	Creating User Groups	231
Fig. 199 –	Creating New User Id	232
Fig. 200 –	User — Company Tab.....	234
Fig. 201 –	Creating New User — Branch Tab.....	234
Fig. 202 –	Creating New User — Department Tab	235
Fig. 203 –	Define New Parameter	236
Fig. 204 –	Menu Screen	237
Fig. 205 –	Menu Parameters Tab.....	238
Fig. 206 –	User Group Privileges	239
Fig. 207 –	Report Boiler Plate	240
Fig. 208 –	Create / View User Profile	240
Fig. 209 –	Program Registration Process	242
Fig. 210 –	Successful Registration of the Program	243
Fig. 211 –	Program Registration Screen	244
Fig. 212 –	Program Registration — Block Tab.....	245
Fig. 213 –	Program Registration — Field Tab.....	245
Fig. 214 –	Program Registration — Canvas Tab	246
Fig. 215 –	Program Registration — Menu Tab.....	246
Fig. 216 –	Program Registration — External Validation Tab	247
Fig. 217 –	Creating Instances	248
Fig. 218 –	Instance Registration — Block Tab	248
Fig. 219 –	Instance Registration — Field Tab	250
Fig. 220 –	Instance Registration — Canvas Tab	254
Fig. 221 –	Instance Registration — Menu Tab.....	255
Fig. 222 –	Instance Registration — Menu Control Tab	256
Fig. 223 –	Instance Registration — Menu Call Parameter Tab.....	257
Fig. 224 –	Instance Registration — External Validation Tab.....	258
Fig. 225 –	Instance Registration — LOV Tab.....	260
Fig. 226 –	Instance Copying.....	261
Fig. 227 –	Prompt Window 1	261
Fig. 228 –	Prompt Window 2	261
Fig. 229 –	Prompt Window 3	262
Fig. 230 –	Prompt Window 4	262
Fig. 231 –	Product Setup Tool.....	263
Fig. 232 –	Product - Tax & Charges.....	264
Fig. 233 –	Product - External Validation.....	264
Fig. 234 –	Product - Front End EV	265
Fig. 235 –	Product - Back End EV.....	265
Fig. 236 –	Product - Other Details.....	266
Fig. 237 –	Script Generator	266

Fig. 238 –	Product Copy.....	267
Fig. 239 –	Product – Section Details	267
Fig. 240 –	Product – Section level details	268
Fig. 241 –	Section level Copy.....	268
Fig. 242 –	Risk Details for the Product.....	269
Fig. 243 –	Product – Field Level details	269
Fig. 244 –	Product Changer	270
Fig. 245 –	Najm-Net Processing Masters.....	271
Fig. 246 –	Najm-Net Product Mapping	271
Fig. 247 –	Najm Net Field Mapping.....	271
Fig. 248 –	Najm Status Query	272
Fig. 249 –	Policy Tab.....	273
Fig. 250 –	Vehicle Tab.....	274
Fig. 251 –	Driver Tab.....	275
Fig. 252 –	Business Rule Master	276
Fig. 253 –	Business Rule Relation Master	277
Fig. 254 –	BR Relation Code.....	280
Fig. 255 –	Business Rule Relation Master – Claims	281
Fig. 256 –	BR Header.....	281
Fig. 257 –	Applicable Places	283
Fig. 258 –	BR Key Columns	284
Fig. 259 –	Cover Details	285
Fig. 260 –	Endt. Code.....	286
Fig. 261 –	Action.....	286
Fig. 262 –	Terms & Condition.....	288
Fig. 263 –	Business Rule Definition Master with Amend Button	289

Document Icon Library

Icons are used as easy indicators to draw your attention to certain important points.
 Use this Document Library to identify the icons and their descriptions in the user manual.

Field	Description
 Mandatory	Required field details that must be entered by the user before submitting the form
<u>Tabs</u>	Represents the Tab detail
 Button	Represents a Button
 Note	A note or additional information useful to the user
 Important	Information that is crucial to setting up proper functionality of PREMIA are separately written under important heading

Masters

PREMIA Masters Menu comprises of the following sub-menus:




Fig. 1 – Masters Menu

SYSTEM PARAMETER

Introduction

System Parameter is one of the most critical master menus available in PREMIA that drives the behavior of the application. The information stored in this screen is important and any change in the parameter might lead to adverse effects during application runtime. So, take utmost care while using this master.

For the various codes masters, this screen would act as the parameter master. All the system logics are driven through these parameters.

Example: For describing a logic called period and its sub-attributes like year, month, week and day, a parameter called Period is selected in the parameter code and its sub-attributes are described under the parameter sub code. Only the external parameter code names are viewed in this screen and all the respective codes are written in the back-end.

Click 'System Parameter' from the Masters menu to view the following screen.

The screenshot shows the 'System Parameter' screen for 'INSURANCE CO LTD'. It features a table with columns: Parameter Code, Parameter Sub Code, Parameter Name, Parameter Value, and Upd. The table lists various policy statuses like Cancelled, Endorsed, New Policy, Renewed, Quotation, Hold, Processed, and Active. A 'Remark' field at the bottom contains the text 'Status of the policy'.

Parameter Code	Parameter Sub Code	Parameter Name	Parameter Value	Upd
POL_STS	C	Cancelled	4	☐
POL_STS	E	Endorsed	5	☐
POL_STS	N	New Policy	2	☐
POL_STS	R	Renewed	3	☐
POL_STS	Q	Quotation	1	☐
POL_STS	H	Hold	6	☐
POL_STS	P	Processed	7	☐
POL_STS	A	Active	8	☐

Remark: Status of the policy

Fig. 2 – Parameter Setup Screen



The implementer handles System Parameter screen. Other users are restricted from using this screen.



Parameter Code

This field displays the Parameter Code.



Parameter Sub Code

The description pertaining to the Parameter Code is automatically displayed in this field.



Parameter Name

The description pertaining to the Parameter Code and sub code is automatically displayed in this field.

Parameter Value

User is allowed to modify the Parameter Value if it is an updatable parameter.

☒ Update

Select the check box to update/modify the parameter.


Parameters are of two kinds. Either the user is allowed to update the parameter or not. Parameters that are possible to update is identified by the 'Update' field check box. For example, the parameter CLMAUTO_APPR decides when the claim is to be approved during claims registration. If the value for this parameter is set to 1 then claim gets automatically

approved while saving the claim. If it is set to 0 then the user has to approve the claim manually by clicking the Approve button during claim registration.

Remark

This field is displayed with appropriate remarks, for a particular parameter code selected.

For NAJM, the system parameter setup as shown below:



If the Parameter Code is set as 1 – NAJM is applicable else it will not be applicable.

CODES MASTER

WELCOME TO CODES MASTER

All the generic codes that are used in the application are created in the Codes Master.

All the Codes generated in Codes Master are stored in a database, which in turn is displayed through the List of Variables (LOV) tables during runtime.

The usages of codes are multi-fold:

- ☐ Codes help in relating information to a transaction
- ☐ Codes save time. User can procure them as LOV's and use them wherever necessary
- ☐ One set of data reused across several transactions

Example – State Code used across many lines of business and different transactions.

The codes available in Codes Master are five types:

- ☐ General Codes
- ☐ Address Codes
- ☐ Line of Business Codes
- ☐ Miscellaneous Codes
- ☐ Applicable Codes

Explanation on the relevance and usage of these codes are explained in the concerned sections.

 Guidelines for using this section of the manual.

- ☐ Field entries for screens that are similar within a particular type of code have not been repeated. Instead, a sample screen has been taken and all the fields explained.
- ☐ Division button that appears in some of the screens has been explained as a single section. A note has been included to highlight the figure number

wherever required.

- ❑ Only specific code names that require a note have been explained. Generic code names like State, City, Country, Vehicle Name etc. have not been included.

Getting Started

On selecting '+' symbol placed before the Codes Master, the following screen is displayed.

The list of sub-menus available under Codes Master Menu is given below:

Masters		Underwriting
o	System Parameter	
-	Codes Master	
+	General	
+	Motor	
+	Fire	
+	General Accident	
+	Engineering	
+	Marine Cargo	
+	Marine Hull	
+	Aviation	
+	Claims	

Fig. 3 – Masters – Codes Masters

The usability of these sub-menus, their internal sub-menus and field level validations is explained in the respective sections.

The first sub-menu to select is 'General' Codes. Double click the + mark placed before this sub-menu name.

GENERAL

The 'General' menu comprises of the following sub-menus.

Masters		Underwriting
o	System Parameter	
-	Codes Master	
-	General	
o	State	
o	Limit Of Liability	
o	Plan Type	
o	Profession	
o	Qualification	
o	City	
o	Sex Master	
o	Cause Of Loss	
o	Surveyor Limit	
o	Nature of Loss	
o	Country	
o	Relationship Master	
o	Bank	
o	Insured's Interest	

Fig. 4 – General Codes

	❑ The field entries for the sub-menus within the General Codes (listed above) are similar to the fields displayed under 'State'. Only the first field name changes from screen to screen. ❑ In some sub-menus, user would notice a button named 'Branches/Division'. Its usage is mentioned under the respective section.
---	--

State

Click 'State' menu. The system displays the screen as shown below.

Fig. 5 – State Master



Code

Enter a new, unique state code in this field.

Description

Enter a valid name in this field.

Short Description

The data entered in the Description field is defaulted in this field.

Long Description

Enter the long description of the location code in this field, if required.

Code by Class

Select the checkbox to enter the class of business (for example, Fire, Motor.) for which this code is valid. If the checkbox is cleared then the application allows this code to be used across all classes of business.

Class

Select the Class from the LOV. The corresponding description is defaulted in the adjacent field.

Value

This field is mandatory, depending on the parameter type set in the system parameters. Enter a value for the City Code, if any. This value is used in the transactions.



Applicable Modules

Enter a code. The description of the code is defaulted in the adjacent field. The code entered in the City Code field is relevant to the module mentioned in this field.

Effective From and To Date

Enter or select the validity period upon which the code is in effect.



Branches

This button allows the user to map these codes to select few branches.

Click 'Branches' button to view the screen as shown below:

Office From*	Description	Office To*	Description	Include?
10	Division 10	100	Head Office	☒
				☐
				☐
				☐
				☐

Fig. 6 – Division

Office From and Office To

Enter the Office range from the LOV. These are the range of division offices for which the master code defined is applicable. The description for the chosen offices can be viewed in the division field. If the user needs to just select one office, click the same from and to range.

For example: Division codes 411200 to 411208 might refer to the accounts division within an insurance company. Instead of selecting one by one, user has the option of selecting it as a range.

Include?

Select this checkbox to include the range of offices. The user is allowed to select/unselect based on requirements.

MOTOR

Motor Codes allow the user to enter codes that are displayed across various fields in run time in the Motor underwriting module.

The 'Motor' menu comprises of the following sub-menus:

Masters		Underwriting
o	System Parameter	
-	Codes Master	
+	General	
-	Motor	
o	Vehicle CC	
o	Vehicle Make	
o	Vehicle Model	
o	Certificate Type	
o	Fuel Type	
o	Vehicle Type	
o	Driving Type	
o	Type Of License	
o	Vehicle/Plate Color	
o	Vehicle Usage	
o	Body Type	
o	Nationality	
o	Vehicle Weight	
o	Vehicle Cylinder	
o	Type Of Motor Trade	

Fig. 7 – Motor Sub-menu

	❑ The field entries for the sub menu within the 'Motor' master are similar to that of the 'State' master. Only the first field name changes from screen to screen. ❑ For field level explanation and details refer 'State' Master under General Codes.
---	---

Vehicle Make

Click 'Vehicle Make' menu. The system displays the screen as shown below:

Vehicle Make

Code* 001

Description ADMIRAL

Short Desc ADMIRAL

Long Desc ADMIRAL

Code By Class ☐

Class*

Value

Applicable Modules* 01 General Insurance

Eff From Date

Eff To Date

Bilingual Details

Description

Short Desc

Long Desc

Fig. 8 – Vehicle Make



The field entries for 'Vehicle Make' screen are similar to that explained under 'State'.
For field level explanation and details, refer '[State](#)' in General Codes.

MARINE CARGO

The 'Marine Cargo' menu comprises of the following sub-menus:

Masters		Policy Administration
o	System Parameter	
-	Codes Master	
+	General	
+	Motor	
+	Fire	
+	General Accident	
+	Engineering	
-	Marine Cargo	
o	Val Basis	
o	Packing Type	
o	Storage Period Unit	
o	Conveyance Type	
o	Vessel Name	
o	Port	
o	Ship Mode	
o	Marine Flag	
o	Transit Type	

Fig. 9 – Marine Cargo Sub-menu



The field entries for the sub menu within the 'Marine Cargo' master are similar to that of the 'State' master. Only the first field name changes from screen to screen.

For field level explanation and details refer '[State](#)' Master under General Codes.

MARINE HULL

The 'Marine Hull' menu comprises of the following sub-menus:

Masters		Policy Administration
o	System Parameter	
-	Codes Master	
+	General	
+	Motor	
+	Fire	
+	General Accident	
+	Engineering	
+	Marine Cargo	
-	Marine Hull	
o	Horse Power	
o	Measuring Unit	
o	Engine Type	
o	Vessel Classification	
o	Vessel Type	
o	Marine Flag	

Fig. 10 – Marine Hull Sub-menu



The field entries for the sub menu within the 'Marine Hull' master are similar to that of the 'State' master. Only the first field name changes from screen to screen.

For field level explanation and details refer '[State](#)' Master under General Codes.

FIRE

Fire Policy Codes allows users to enter codes that would be displayed across various fields in run time in the underwriting module.

To add a new code in the relevant internal sub-menu, select Fire Policy Codes from the Codes Master main menu.

The 'Fire' menu comprises of the following sub-menus:

Masters		Policy Administration
o	System Parameter	
-	Codes Master	
+	General	
+	Motor	
-	Fire	
o	Type Of Industry	
o	Indemnity Period Unit	
o	Risk Location	

Fig. 11 – Fire Master Sub-menu



The field entries for the sub menu within the 'Fire' master are similar to that of the 'State' master. Only the first field name changes from screen to screen.

For field level explanation and details refer '[State](#)' Master under General Codes.

ENGINEERING

The 'Engineering' menu comprises of the following sub-menus.

Masters		Policy Administration
o	System Parameter	
-	Codes Master	
+	General	
+	Motor	
+	Fire	
+	General Accident	
-	Engineering	
o	Location	

Fig. 12 – Engineering Sub-menu



The field entries for the sub menu within the 'Engineering' master are similar to that of the 'State' master. Only the first field name changes from screen to screen.

For field level explanation and details refer '[State](#)' Master under General Codes.

AVIATION

The 'Aviation' menu comprises of the following sub-menus:

Masters		Underwriting
o	System Parameter	
-	Codes Master	
+	General	
+	Motor	
+	Fire	
+	General Accident	
+	Engineering	
+	Marine Cargo	
+	Marine Hull	
-	Aviation	
o	Type	
o	License Type	
o	Engine Type	

Fig. 13 – Medical Sub-menu



The field entries for the sub menu within the 'Aviation' master are similar to that of the 'State' master. Only the first field name changes from screen to screen.

For field level explanation and details refer '[State](#)' Master under General Codes.

BONDS

The 'Bonds' menu comprises of the following sub-menus:

-	Bonds
o	Collateral Type
o	Region

Fig. 14 – Bonds Sub-menu

	The field entries for the sub menu within the 'Bonds' master are similar to that of the 'State' master. Only the first field name changes from screen to screen. For field level explanation and details refer 'State' Master under General Codes.
---	--

CLAIMS

The 'Claims' menu comprises of the following sub-menu:

-	Claims
o	Intimation Mode

Fig. 15 – Claims Sub-menu

	The field entries for the sub menu within the 'Claims' master are similar to that of the 'State' master. Only the first field name changes from screen to screen. For field level explanation and details refer 'State' Master under General Codes.
---	---

PRODUCT MASTER

Introduction

The Product Master deals with all the masters used in Set ups available in the application such as Lines of business, Covers, SMI and the Product.

The 'Product Master' menu comprises of the following sub-menus:

Masters		Policy Administration
o	System Parameter	
+	Codes Master	
-	Product Master	
o	Surplus Rule Master	
o	Line of Business	
o	Section Master	
o	Policy Type	
o	Condition Master	
o	Deductible Master	
o	Discount Master	
o	Loading Master	
o	Cover Master	
o	Cover Group	
o	SMI Master	
o	SMI Group Master	
o	Installment Pay Setup Master	
o	Product Set Up	
o	Vehicle Query Mapping	
o	Vehicle Query Column Mapping	

Fig. 16 – Product Master

SURPLUS / MUDHARABAH RULE

Surplus distribution process, widely practiced by the Takaful insurance companies, involves calculating the surplus amount or profit from the underwriting and investments, and sharing a percentage of profit with the policy holders; also known as Mudharabah amount in non Takaful Islamic Insurance practice.

In the Surplus Rule Master screen, user is able to enter the details only after defining the parameter (SUR_DIST_REQ) as '1' in the System Parameter screen.

This parameter implies that the surplus distribution process is applicable in the application. If set to '0', it means that it is not applicable and the surplus master or processing screen will not be applicable at all. Using surplus rule master, user can define surplus calculation rules for the products based on the class of business selected.

Surplus Rule Master

INSURANCE CO LTD

Class Code* **30** Marine

Product Code*	Surplus Applicable	Renewed	Expired	Cancelled	Commission	Exclude Policy	WHT Tax	Retakaful Deduction	Claim Ratio	Surplus Rate	Effective From Dt	Effective To Dt
Code*	Y/N	Y/N	Y/N	Y/N	Y/N	When	Y/N		Perc.	Perc.		
3001	Yes	Yes	Yes	Yes	No	Any Cl...	No			13.000	01/01/2013	
3002	Yes	Yes	Yes	Yes	Yes		Yes	None		9.500	01/03/2013	
3002	Yes	Yes	Yes	Yes	No	Excee...	Yes	None	60.000	11.500	01/01/2013	28/02/2013
3004	Yes	No	Yes	Yes	No	Excee...	Yes	None	85.000	7.500	11/01/2013	31/03/2013
3004	Yes	No	Yes	Yes	No	Any Cl...	No	None		12.500	01/01/2013	10/01/2013
3004	Yes	Yes	No	No	No	Excee...	No	FAC and...	50.000	5.000	01/05/2012	31/10/2012
3004	Yes	No	Yes	No	No	Excee...	No	None	80.000	19.000	01/01/2012	30/04/2012

Cut off limit

Min. Pay Out Limit

Surplus Method **Actual contribution by insured**

Product Desc. **Marine Cargo- Single Transit-Import/Export**

Fig. 17 – Surplus / Mudharabah Rule Master

In this master user needs to define the business type, class of business, products, consider commission Y/N, consider policies with claims, Exclude policy when, define fees/charges/taxes type and rate, cut off limit for effective periods, minimum pay-out limit, consider cancelled Policies Y/N, and Surplus/Mudharabah percentage to process the transaction and distribute the same.



Class Code

Select from the LOV, the class code to define rules for processing surplus calculation.



Product Code

Select from the LOV, the product associated with the business class. The LOV displays the rule details relevant to the selected class and product codes with the effective period for which the rules are valid. On selecting a valid product code, the relevant description is displayed in the 'Product Desc' field.



- ☐ User is allowed to create, update or delete rule details for the selected product code.
- ☐ The system restricts users to create multiple entries for the same product with the same effective date having the same set of values 'Surplus Applicable Y/N'.

Surplus Applicable YN

Select 'Yes' from the drop-down list, if surplus calculation is applicable for the product.

Renewed Y/N

Select 'Yes' from the drop-down list if the renewed policy is considered for surplus calculation. On selecting the checkbox, all the policies renewed and falling within the surplus calculation date range get selected for surplus distribution processing.

Expired Y/N

Select 'Yes' from the drop-down list if any expired policy is considered for surplus calculation. On selecting the checkbox, all the policies expired and falling within the surplus calculation date range get calculated for the surplus distribution.

Cancelled Y/N

Select 'Yes' from the drop-down list if the cancelled policy considered for surplus calculation. On selecting the checkbox, all the policies that are cancelled and fall with the surplus calculation date range are selected for the surplus distribution processing.

Commission Y/N

Select 'Yes' from the drop-down list if commission is considered for surplus calculation.

Exclude policy when

This field is applicable for Claims.

Select the appropriate value from the drop-down list if the policy with claim to be considered for the surplus calculation.

- ☐ Any claim exists – Exclude the policy for processing if any claim exists in the policy
- ☐ Except KFK (Knock for Knock) – Exclude the policy if other than KFK (Knock for Knock) claim exists
- ☐ Exceeds Claim ratio – Exclude the policy if claim ratio exceeds the defined %
- ☐ Exceeds Non-KFK claim ratio – Exclude the policy if non-KFK claim ratio exceeds the defined %
- ☐ None

WHT Tax YN

Select 'Yes' from the drop-down list, if tax charge is applicable for this rule.

Retakaful Deduction

Select the appropriate value from the drop-down list, if retakaful is applicable for this rule.

- ☐ Treaty including retention – Treaty and retention % will be applied and deducted
- ☐ Treaty excluding retention – Treaty % will be applied and deducted
- ☐ FAC – FAC % will be applied and deducted
- ☐ FAC and Treaty including retention – FAC, Treaty and retention % will be applied and deducted
- ☐ FAC and Treaty excluding retention – FAC & Treaty % will be applied and deducted
- ☐ None

Claim Ratio Percentage

This field is mandatory if 'Claim Y/N' and 'Surplus Applicable Y/N' fields are selected as 'Yes'. Enter the claim ratio percentage. Policies having claim ratio more than the ratio entered in this field is not considered for surplus processing.

Surplus Rate Percentage

This field is mandatory if user has selected 'Yes' in the 'Surplus Applicable Y/N' field. This rate is applied on the contribution and surplus amount is calculated for the policy holder.

	☐ Ensure that the value entered is: - o Non negative - o Non zero - o Less than 100 and - o upto 3 decimal places ☐ User is allowed to enter multiple rates for non –overlapping effective from and to date range.
---	---



Effective From and To Date

Enter the effective period for which the rule defined for the product is valid. The dates entered have to be within the valid dates defined for the product in the product setup. If the 'Effective To' date is left as blank, the system considers the current effective date for the product.

Cut off Limit

Enter the cut-off limit value.


Min Pay Out Limit

Enter the payout limit value.

LINE OF BUSINESS

Line of Business refers to classification of businesses/assets for insurance. Every Insured is registered to one or more of these lines. For example: Fire, Motor, and Marine are some of the lines (classifications) of business.

Click 'Line of Business' menu to create new line of business and map applicable departments to it. The system displays the screen as shown below:



Line of Business

LOB: 10

Description: Motor

Short Description: Motor

UPR Process Y/N: ☒ UPR Method: 1/24 Method Fixed Perc:

Effective From: 01/01/2000 Effective To: 31/12/2099

Applicable Departments

Dept Code*	Description
10	Motor

Fig. 18 – Lines of Business



Line of Business (LOB)

Enter a unique line of business code.

Description

Enter a suitable description for the Line of Business code.

Short Description

The words entered in the 'Description' field are defaulted in this field and that is modifiable.

☒ **UPR (Unearned Premium Reserve) Process Y/N**

Select the checkbox if the UPR Process is applicable for that LOB.

UPR (Unearned Premium Reserve) Method

Click the UPR method from the drop down list. The available options are:

- ☐ 1/365
- ☐ 1/24
- ☐ Fixed Method



The drop-down list will be enabled only when the 'UPR Process Y/N' checkbox is selected.

Fixed Percentage

If Fixed Method is the preferred UPR Method for a specific line of business, then enter the percentage for calculating the Un-earned premium reserve.

Effective From and To Date

Enter or select the effective period for this line of business in 'From' and 'To' dates using the calendar icon.

Applicable Departments



Department Code

Select the appropriate department code applicable for this line of business from the LOV. The corresponding description is defaulted in the adjacent field.

SECTION MASTER

Click 'Section Master' menu to create new sections for the Line of Business.

The system displays the screen as shown below:

Fig. 19 – Section Master



Section Code

Enter a new, unique section code.

Description

Enter a suitable description of the Section Code.

Short Description

The data entered in the Description field is defaulted.

Long Description

Enter the long description, if required.

Code by LOB

Select Code by LOB checkbox to enter the line of business (for example, Fire, Motor.) for which this code is valid. If the checkbox is cleared then the application allows this code to be used across all classes of business.



LOB

Select appropriate LOB from the LOV. The corresponding description is defaulted in the adjacent field.

Value

This field may be mandatory, depending on the parameter type set in the system parameters. Enter a value for the Condition code, if any. This value is used in the transactions.



Applicable Modules

This field specifies that the defined Section Code is applicable to General Insurance.

The description of the code selected is defaulted in the adjacent field.

Effective From and To Date

Enter or select the validity period upon which this section code is in effect.

POLICY TYPE

Click 'Policy Type Master' menu to create new policy types.

The system displays the screen as shown below:




Fig. 20 – Policy Type Master



Policy Type Code

Enter a new, unique policy type code.

Description

Enter a suitable description for the Policy Type Code.

Short Description

The data entered in the Description field is defaulted.

Long Description

Enter the long description for the code.

Code by LOB

Select the checkbox to enter the line of business (for example, Fire, Motor.) for which this code is valid. If the checkbox is cleared then the application allows this code to be used across all classes of business.



LOB

Select appropriate LOB from the LOV. The corresponding description is defaulted in the adjacent field.

Value

This field may be mandatory, depending on the parameter type set in the system parameters. Enter a value for the Condition code, if any. This value is used in the transactions.



Applicable Modules

This field specifies that the defined Policy Type Code is applicable to General Insurance. The description of the code selected is defaulted in the adjacent field.

Effective From and To Date

Enter or select the validity period upon which this policy is in effect.

COVER MASTER

Click 'Cover Master' menu.

The system displays the screen as shown below:

Fig. 21 – Cover Master



It is possible to use the same Cover Code in Discount and Loading Masters based on Cover Type like C, D, L.

Cover Code

Enter a new, unique Cover Code.



Description

Enter a suitable description for the Cover Code.

Short Description

The data entered in the Description field is defaulted.

Long Description

Enter the long description for the Cover Code in this field, if required.



Cover Type

Select the cover type from the LOV. The available cover types are:

- ☐ OD – Own damage
- ☐ TPL – Third party damage
- ☐ OTH – Others

The corresponding description is defaulted in the adjacent field. This helps to indicate if the cover defined is applicable for 'OD' policy only or for 'Third Party' policy or is a common one. This will also be of use as a filter criterion for reports or as criteria in rating or tariff definition.

Cover Escalation Y/N

Select the checkbox to allow the user during claim processing; to increase (by percentage value)

the sum insured value.

LOB

Select a LOB code from the LOV to map the Cover to a line of business.

Effective From and To Date

Enter or select the validity period upon which this cover is in effect.

Terrorism Y/N

Select the checkbox if the cover has to be identified as terrorism cover.

CONDITION MASTER

Condition refers to a provision in a contract that has the effect of modifying, suspending or revoking the principal obligation if an uncertain event happens or fails to happen in future.

Click 'Condition Master' menu. The system displays the screen as shown below:

Fig. 22 – Condition Master



Condition Code

Enter a new, unique Condition code.

Description

Enter a suitable description for the Condition Code.

Short Description

The data entered in the Description field is defaulted here.

Long Description

Enter the long description of the Condition Code in this field, if required.

☒ Code by LOB (Line of Business)

Select this checkbox to enter the line of business (for example, Fire, Motor.) for which this code is valid. If the checkbox is cleared then the application allows this code to be used across all classes of business.

LOB (Line of Business)

Select the appropriate LOB from the LOV. The corresponding description is defaulted in the adjacent field.

Value

This field may be mandatory, depending on the parameter type set in the system parameters. Enter a value for the Condition code, if any. This value is used in the transactions.



Applicable Modules

This field specifies that the defined condition type code is applicable to General Insurance. The description of the code selected is defaulted in the adjacent field.

Effective From and To Date

Enter or select the validity period upon which this condition is in effect.

DEDUCTIBLE MASTER

An insurance policy provision that specifies an amount to be deducted from any claim and making the company liable, only for the balance amount.

Click 'Deductible' menu. The system displays the screen as shown below:

Fig. 23 – Deductible Master



Code

Enter a new, unique code for the Deductible.

Description

Enter a suitable description for the code in this field.

Short Description

The data entered in the Description field is defaulted in this field.

Long Description

Enter the long description for the code, if required.

Code by Class

Select the checkbox to enter the line of business (for example, Fire, Motor.) for which this deductible is valid. If the checkbox is cleared then the application allows this code to be used across all classes of business.

Class

Select appropriate line of business from the LOV. The corresponding description is defaulted in the adjacent field.

Value

This field may be mandatory, depending on the parameter type set in the system parameters. Enter a value for the Condition code, if any. This value is used in the transactions.



Applicable Modules

This field specifies that the defined deductible code is applicable to General Insurance. The

description of the code selected is defaulted in the adjacent field.

Effective From and To Date

Enter or select the validity period upon which this deductible is in effect.

Branches

In some instances, only a few divisions are used for certain codes.

For example: Account related codes such as Ledger; Balance sheet. The 'Branches' button allows the user to map these codes to select few divisions.

Click 'Branches' button. The system displays the screen as shown below:

Fig. 24 – Branches

Office 'From' and 'To'

Enter or select 'Office From' and 'Office To' from the LOV. The LOV displays codes set in the Office/Division Master. Once the codes are selected, the description is defaulted in the respective fields.

☒ Include

If this field is checked, it signifies that the defined product is applicable to the specified division range. If left unchecked, the division range is excluded.

DISCOUNT MASTER

Click 'Discount Master' menu. The system displays the screen as shown below:

Fig. 25 – Discount Master



It is possible to use the same Cover Code in Cover Master and Loading Master.

Discount Code

Enter a new, unique discount code in this field.



Description

Enter a suitable description for the Discount Code.

Short Description

The data entered in the Description field is defaulted here and it is editable.

Long Description

Enter the long description of the City code in this field, if required.



Type

Select the type from the LOV. The available discounts are:

- ☐ FEA discount (Fire Extinguisher Appliances Discount)
- ☐ OD discount (Own Damage discount)
- ☐ Others discount
- ☐ TP discount (Third Party discount)

The corresponding description is defaulted in the adjacent field. The type selected indicates whether the discount is a FEA or an OD/Third Party discount or any other discount.

LOB Code

Select LOB Code from the LOV to map the discount to a line of business.

Effective From and To Date

Enter or select the validity period upon which this discount is in effect.

LOADING MASTER

Click 'Loading Master' menu. The system displays the screen as shown below:

Fig. 26 – Loading Master



It is possible to use the same Cover Code in Cover Master and Discount Master.

Loading Code

Enter a new, unique Loading Code.



Description

Enter a suitable description for the Loading Code.

Short Description

The data entered in the Description field is defaulted in this field and it is editable.

Long Description

Enter the long description for the Loading Code, if required.



Type

Select the type of cover from the LOV. The available covers are:

- ☐ OD – Loading
- ☐ OTH – Other loading
- ☐ TP – TP loading
- ☐ UL – User loading

The corresponding description is defaulted in the adjacent field. This indicates whether the loading is for Third Party cover /policy or OD cover/policy or a tailor made one defined by user.

Cover Escalation Y/N

Select checkbox to allow the user, during claim processing, to increase (by percentage value) the sum insured value.

Class Code

Select a LOB code from the LOV to map the loading to a line of business.

Class Code

Class code refers to the Line of business. Select a code from the LOV to map the discount to a line of business. Some of the options are listed below.

- ☐ 20 – Fire
- ☐ 40 – Engineering
- ☐ 70 – Bonds
- ☐ 30 – Marine

If the loading is required only for specific class of business, the required option can be selected here and the loading will be applicable only for that class of business.

Effective From and To Date

Enter or select the validity period upon which this loading is in effect.

Terrorism Y/N

Select the checkbox if the loading has to be identified as terrorism loading.

COVER GROUP

The user is allowed to create a Cover Group code using this sub-menu. A Cover Group is formed by combining individual covers and grouping them.

For example: Grouping Cover A, Cover B, Cover C, the user is allowed to form a cover group, called 'Cover Group 1'.

Click 'Cover Group' menu. The system displays the screen as shown below:

Fig. 27 – Cover Group



Code

Enter a new, unique Cover Group Code.



Description

Enter a suitable description for the Cover Group Code.

Short Description

The data entered in the Description field is defaulted here and it is editable.

Long Description

Enter the long description of the Cover Group Code, if required.



Product Code

Select a product code from the LOV. The corresponding description is defaulted in the adjacent Product Description field.

Section Code

Select a Section Code from the LOV. The corresponding description is defaulted in the adjacent Section Description field.

Cover Code

Select a Cover Code from the LOV. The corresponding description is defaulted in the adjacent Cover Description field.



Cover Level

Enter or select the cover level from the LOV. The available options are:

- ☐ F – Field level
- ☐ S – Section level
- ☐ P – Product level

☐ CVR – Cover level

☐ SMI – SMI level

The LOV displays all the covers available for the selected Product Code. The description of the cover is displayed in the Cover Description field.



Cover Type

Enter or select the cover type for the selected cover from the LOV.

	☐ The list of covers, discounts and loadings selected would form part of the cover group further used for rating definition. ☐ Either the cover group Sum Insured (total of all the included covers' Sum Insured) or the premium (total of all the included covers' premium) can be used for the rating definition.
--	---

SMI MASTER

Subject Matter Insured (SMI) refers to a set of objects to be insured against future risks. For example: Glass panes, television, stereo system, and display boards.

Click 'SMI Master' menu. The system displays the screen as shown below:

Fig. 28 – SMI Master

	Please refer to 'Deductible Master' section of this manual for field level explanations.
--	---

SMI GROUP MASTER

User is able to create a subject matter insured group code by combining the SMIs and grouping them together to form a SMI Group. For example: If 100 computers are to be insured, each computer is the SMI and 100 computers form the SMI Group.

Click 'SMI Group Master' menu.

The system displays the screen as shown below:

Product Code*	Product Description	Section Code*	Section Description	SMI Code*	SMI Code Description
2009	Industrial All Risks	200201	Fire Material Damage	020100	FLEX SMI
2009	Industrial All Risks	200201	Fire Material Damage	22001	Building

Fig. 29 – SMI Group Master



Code

Enter a new, unique SMI Group Code.



Description

Enter a suitable description of the SMI Group Code.

Short Description

The data entered in the Description field is defaulted in this field which is editable.



Product Code

Select a Product Code from the LOV. The corresponding description is defaulted in the adjacent Product Description field.



Section Code

Select a Section Code from the LOV. The corresponding description is defaulted in the adjacent Section Description field.



SMI Code

Select appropriate SMI Code from the LOV. The corresponding description is defaulted in the adjacent SMI Description field.

INSTALLMENT PAY SETUP MASTER

The Installment Pay Setup Master enables the user to setup a payment plan with each installment percentage and due date. User is also able to define the due dates for each installment, based on which, the due date is calculated.

Click 'Installment Pay Setup Master' menu. The system displays the screen as shown below:

Inst. No.	Inst. %	Period*	Description	Date Arrived From*	Description	No. of Days	Renew Date Arrived From*	Description	Renew No. of Days
1	50.00	3	Month	01	Policy Effective From Date	0	01	Policy Effective From Date	0
2	50.00	3	Month	04	Previous Installment Date	6	04	Previous Installment Date	6

Total % 100.00

Fig. 30 – Installment Pay Setup Master

Press F8 to query the Installment Method. The installment details are automatically displayed based on the method selected. User is allowed to modify the following:

- ☐ Installment Number
- ☐ Installment %
- ☐ Period
 - o1 – Day
 - o3 – Month
- ☐ Date Arrived From – The option can be set as required by the user
 - o01 – Policy Effective From Date
 - o02 – Policy Issue Date
 - o03 – Policy Approval Date
 - o04 – Previous Installment Date
- ☐ Number of days
- ☐ Renew Date Arrived from –
 - oPolicy Effective From Date
 - oPolicy Issue Date
 - oPolicy Approval Date
 - oPrevious Installment Date
- ☐ Renew number of days
- ☐ Total %

PRODUCT SETUP

PREMIA has been developed to support the concept of a single version of the product with an easy-to-use product configurator that masks the complexity of the architecture. The Product Configurator allows the insurance companies to define their products by setting up the elements whose combination makes up a product and discriminate it from the rest.

To configure a product, the user can set up the type of covers and risk details that need to be captured. Dynamic data elements are defined to capture tariff and non-tariff based data. All these data specified are required to compute the premium. Complex validation rules are setup for the defined data elements. The Tariff engine is closely integrated with the product configurator and is used to set up the premium rating computations for each product.

Product Setup is an integral part of PREMIA. This is used to define the functions of various products for the different classes of business. The transaction screens, in real time, will display/function according to the setups done here. Before the user enters a Product Setup, all the relevant masters have to be entered.

Header Block

The Product Setup screen that the user sees below is divided into various segments. The first segment is called the 'Header'. In this segment, the type of product, Class of Business, effective period, validations and flow required for the product at the underwriting level are defined. Applicable 'Conditions', 'Discounts', 'Deductibles' and 'Loading' at the product level are also defined. The 'Product Setup' screen is displayed as shown below.



Most of the fields and functionalities in the Product Setup screen are provided to take care of the nuances and requirements of various geographies. Some functionality may not be applicable to some geography.

The system displays the screen as shown below:

Fig. 31 – Product Setup



Product Code

All products are given a unique code for identification. This code is used across the PREMIA application. Enter the description for the code in the adjacent field.

For example, for code 1001 enter the description as Motor Commercial.

Short Description

The description entered in this field is used for internal reports. This field automatically defaults

the description entered for the product code here which is editable. User may alter this field, if necessary.



Class Code

Class code refers to the Line of business. Use this field to attach the product to its respective line of business. The pre-defined Class Codes are available through the List of Values (LOV) provided. Once the code is selected, the description is automatically displayed in the adjacent field.

An example is, Class Code: 10 with description as Motor.



Refund type

This field defines the effective date from when the premium refund, if any, is calculated.

Select the required option, from the drop-down list. The options are:

☐ Exclude Effective From Date

☐ Include Effective From Date

Example – When cancellation of a policy requires refund of premium, based on the option selected, the system calculates the refund amount, to account for or exclude the actual date of cancellation.

Inward Commission

Select the required inward commission type from the drop-down list. The available options are:

☐ Inward Commission to be deducted from Premium

☐ Inward Commission not to be deducted from Premium

Minimum Premium (LC1)

This field value is used to set the minimum premium applicable (in local currency) for the product. The application accepts a premium above the minimum premium defined in this field in transactions. Else, an error message is raised; or the premium is automatically increased to this amount, based on the option defined for system parameter MIN_MAX_ERR.

Maximum Discount Percentage

Enter the maximum discount percentage given for the product, while issuing the policy. During policy administration, PREMIA verifies that the total percent of all discounts together are not greater than the percentage entered in this field.

Effective From/To date

Enter or select the validity period upon which this Product Code is in effect.

Product Duration Type

Select the duration type of the product from the drop-down list as one of the following. The Premium Computation is based on duration and duration is based on time-stamp.

☐ Afternoon – By selecting the Product Duration Type as 'Afternoon' for the applicable product, after user enters the FROM date with time, the system defaults the To date with time. For example, – if 'From Date' is entered as 01-01-2013 12:00 hrs, then the system defaults the 'To Date' with 01-01-2014 11:59 hrs.

☐ Evening - After user enters the FROM date with time, for Example, if 'From Date' is 01-01-2013 16:00 hrs, then the system defaults the 'To Date' as 01-01-2014 15:59 hrs.

☐ First Day – After user enters the FROM date with time, for Example, if 'From Date' is 01-01-2013 00:00 hrs, then the system defaults the 'To Date' as 01-01-2014 00:00 hrs

☐ Midnight – After user enters the FROM date with time, for Example, if the 'From Date' is 01-01-2013 00:00 hrs, then the system defaults the 'To Date' as 01-01-2014 23:59 hrs

☐ Midnight previous day – After user enters the FROM date with time, for Example, if 'From Date' is 01-01-2014 10:00 hrs, then the system defaults the 'To Date' as 31-12-2014 23:59 hrs

☐ Next Day – For Example, if 'From Date' is 01-01-2013 00:00hrs, then the system defaults

the 'To Date' as 02-01-2014 23:59 hrs

- ☐ Normal – If the 'From Date' is entered as 01-01-2014 10:00 hrs, then the system defaults the the 'To Date' as 31-12-2014 9:59 hrs

☒ **Tariff Applicable**

Select this checkbox if premium calculation is to be based on pre-defined tariff rates. During underwriting, calculation of premium happens based on the logic defined in the rating setup

☒ **Annual Product Y/N**

If the policy period for the product is of one-year duration, select this field. Premium calculation for products valid for a year is of the Annual/Normal type.

☒ **IBNR Process Applicable Y/N**

Specify whether IBNR process is applicable or not.

- ☐ The system parameter IBNR method has to be set as 01 for Premium Calculation method.
- ☐ The system parameter IBNR method has to be set as 02 for Outstanding Calculation method

Bilingual Details

Enter the bilingual Description and Short Description details.

Min Max SI

Define min/max Cover SI applicable for the product as one of the following that will be taken during premium calculation:

- ☐ Error Message – Select this option to display error message when the entered Cover SI is below the minimum or above the maximum cover SI defined for the product in Cover parameter
- ☐ Default SI – Select this option to default the Cover SI value. User is allowed to override the value during underwriting
- ☐ Error on Overriding – When the loaded/discounted or defaulted (minimum or maximum) Cover SI is overridden, system displays an error message while tabbing out after overriding and does not allow the user to proceed with the policy approval

Min. Max. Premium

Define minimum /maximum premium applicable for the product at the product setup. The available options are:

- ☐ Error Message - Select this option to display error message when the premium calculated for the product or cover is below the minimum or above the maximum premium defined for the product or covers
- ☐ Default loading/discount – When the premium calculated for the product/cover is less than the minimum premium defined for the product/cover or more than the maximum premium defined, the system defaults a loading (for minimum premium) or a discount (for maximum premium) with the difference amount. During overriding, the system proceeds with approval with the overridden amount
- ☐ Error on Overriding – When the loaded/discounted or defaulted (minimum or maximum) premium for the product or cover is overridden, system displays an error message while tabbing out after overriding and does not allow the user to proceed with the policy approval

Min Max Charge

Define min/max charge applicable for the product as one of the following that will be taken during premium calculation:

- ☐ Error Message – Select this option to display error message when the entered charge is below the minimum or above the maximum Tax/Charges defined for the product in Taxes/Charges Setup Master
- ☐ Default SI – Select this option to default the Charge value. User is allowed to override the

value during underwriting

- ☐ Error on Overriding – When the loaded/discounted or defaulted (minimum or maximum) charge applicable is overridden, system displays an error message while tabbing out after overriding and does not allow the user to proceed with the policy approval



Division (Product Level)

Click this button to define the applicable office/division for the product where the policy can be issued to those specific offices/divisions only.

PREMIA gives user the option of making the insurance product available to all applicable divisions by defining the range of divisions in this block. If the product is applicable across all divisions, enter 0 in the Division From field and zzzzzz in the Division To field.

Office From*	Description	Office To*	Description	Include?
100	Head Office	100	Head Office	☒
				☐
				☐
				☐
				☐

Fig. 32 – Applicable Divisions

Applicable Offices defined for

Displays the field based on the product code selected in the header block.

Division From and To

Select the range of divisions to which this product is applicable from the LOV, which displays codes set in the Division master. Once the codes are selected, the description is automatically displayed in the respective fields.

Include/Exclude

Select the checkbox to indicate that the defined product is applicable to the specified division range. If left unselected, this product is excluded for that division range.



Conditions (Product Level)

All applicable conditions for a particular line of business are pre-defined in the Conditions master. Conditions are set at any level for the product.

Enter applicable conditions required in this screen. These conditions are defaulted during underwriting, if the default option is selected in this screen.

Code*	Description	Short Description	Condition Type	Effective From	Effective To	Default
7152	Exclusion Clause 01/10/90 (Cargo)	Exclusion Clause 01/10/90 (Cargo)	06			☐
7153	Labels Clause	Labels Clause	06			☐
7154	Accessories Clause	Accessories Clause	06			☐
7155	Cutting Clause	Cutting Clause	06			☐
7156	Pairs and Sets Clauses	Pairs and Sets Clauses	06			☐

Long Description: Labels Clause Description: Conditions

Long Desc 2: Subject to Labels Clause

Bi-Lingual Details

Description: Subject to Labels Clause Short Description: Subject to Labels Clause

Long Description: Subject to Labels Clause

Fig. 33 – Applicable Conditions



Code

The applicable condition codes for the product are set here. Codes are picked up from the LOV.

Description/Short Description/Long Description

Based on the purpose of usage, PREMIA gives user the option of entering descriptions.

- ☐ Description – The description entered in this field is used in general reports and schedules
- ☐ Short description – The description is defaulted and is modifiable. It is used for referring or indicating the conditions included in internal reports
- ☐ Long description – The description entered in this field is used for specific reports that require printing of the actual full text

Condition Type

Enter one of the condition types available to differentiate whether it is Exclusion, Warranty or the Extension. The condition types are defined in the condition master, and they include:

- ☐ Warranty Clauses
- ☐ Extension Clauses
- ☐ Exclusion Clauses

The application differentiates the conditions according to whether it is exclusion, warranty or the extension, and the condition specified here is identified to be printed in the schedule.

Effective From and To Dates

If certain conditions are to apply only for a certain period, set the validity period here. Enter or select the 'From' and 'To' dates from the calendar accessed using the LOV.

Default

Select this checkbox if the condition is to default in the Conditions block during underwriting.

Bilingual Details

Listed below are the bilingual details:

- ☐ Description – Enter the Bilingual Description in the prescribed language to be used in general reports and schedules
- ☐ Short Description – Defaults the description or allows to enter description in that second language to be used for internal reports
- ☐ Long description – Enter the short description to be used for specific reports that require printing of the actual text



Deductibles (Product Level)

All applicable deductibles for a particular line of business are pre-defined in the Deductibles master. Use this block to enter applicable deductibles at the product level.

These deductibles are defaulted during underwriting, if the default option is selected in this screen. Deductibles are validated at the time of claims. The system displays the screen as shown below:

Fig. 34 – Applicable Deductibles

Deduction Code

Set the deductible codes applicable for the product. These codes are picked up from the LOV. Three description fields have been provided in this block also. These fields have been explained earlier.



Deductible Type

Set the deductible type for the applicable deductible code. Based on the selected type, the deductible value is calculated during claims. Options available are:

- ☐ % of Sum Assured
- ☐ % of Claim
- ☐ Fixed Value
- ☐ Number of Days
- ☐ % of AOA (Any One Accident)
- ☐ Others
- ☐ Hours
- ☐ % Subject to Max Value

Deductible Value

Enter the actual value to be deducted during claims.

For example, on selecting the Percentage of Sum Assured in the Deductible Type field and enter 5 in the Deductible Value field, it implies that 5% of Sum Insured is to be deducted from the claim amount.

If the default option is selected in this screen then during underwriting, the code, type and value (if any) are defaulted automatically. Otherwise, the same is enabled when the deductible is picked up from the LOV.

Effective From and To Dates

Set the validity period if certain deductibles are to apply only for a certain period. Enter or select the 'From' and 'To' dates from the calendar using the LOV.

☒ Default

Select this checkbox if the deductible is to default in the 'Deductibles/Excess' block during underwriting.



- ☐ Enter the Bilingual Details as in the Conditions block.
- ☐ PREMIA also provides the option of setting specific conditions for a deductible. To do this, click the **Conditions** button available in this screen. This screen is the same as explained at the header level.

Discount (Product Level)

All applicable credits/discounts for a particular line of business are pre-defined in the Discount master. Enter the applicable discounts required at the product level in this screen. These discounts are defaulted during underwriting if the default option is selected here.



☐ It is possible to attach the same Discount code at any levels such as – Product, Section, Risk and Cover

☐ User is also allowed to create the same code for Cover, Discount and Loading, based on Cover Type.

Applicable Discounts

Discount Code*	Description	Rate Per	Round To*	Mandatory	Default	Refund Allowed	Default on Renewal	Broker Commission Applicable	Separate AC Entry	NCB Disc	Effective From	To
4001	Special Discount	100.00	00	☐	☐	☒	☐	☒	☐	☐		
4002	General Discount	100.00	00	☐	☐	☒	☐	☒	☐	☐		
				☐	☐	☒	☐	☐	☐	☐		
				☐	☐	☐	☐	☐	☐	☐		
				☐	☐	☐	☐	☐	☐	☐		

ADD RI Y/N ☐ Rate Modify Y/N ☐

Round To Rate Key

Short Description Long Description

Mutual Excl. Group ID

Short Description

Bi-Lingual Details

Description

Fig. 35 – Applicable Discounts

Discount Code

Set the discount codes for the applicable product. Codes are picked from the LOV. Three description fields have been provided in this block also. These fields have been explained earlier.

Rate Per

Set the rate per/denominator for the rate for calculation of the actual discount. The rate is set in the Discount block of the 'Other Details' block for the product, during underwriting.

Round To

Enter the rounding off method (number of decimal places) to which the taxes and charges amount is to be rounded off. The description of the method is automatically displayed in the field provided for the same.

☒ Mandatory

Select this checkbox if a particular discount is to be made mandatory for the product. If set as mandatory, the policy is not issued without the selection of this discount.

☒ Default

Select the checkbox, if the discount is to default in the Discount block during underwriting.

☒ Refund Allowed

Select the checkbox if refund is applicable on the discount.

☒ Default on Renewal

Select the checkbox if the discount is to be defaulted during renewal of the policy.

☒ Broker Commission Applicable

Select the checkbox if broker commission is applicable on the discount. If selected, broker commission is calculated for the discount amount entered during underwriting.

☒ Separate AC Entry

Select the checkbox if the credit or discounts applicable is to be accounted separately and not along with the premium. This allows the system to pass a separate accounting entry for

discounts offered in the policy.

☒ **NCB Discount Entry**

Select the check box if the discount is defined as a No claim Discount.

☒ **Add RI YN**

Select this checkbox if the discount to be considered for RI allocation. By default this checkbox is selected, implying that the discount will be applicable for reinsurance premium calculation. If this is not selected, the discount will not be applicable for reinsurance premium calculation and only the premium before deduction of discount will be allocated.

☒ **Rate Modify YN**

If this check box is selected, the discount calculated as per the tariff rate is modifiable. The rate itself will be modifiable. Otherwise it will not be modifiable in the transaction.

Effective From and To Dates

Set the validity period if certain discounts are to apply only for a certain period.

	☐ PREMIA also provides the option of setting specific conditions and deductibles for a discount. To do this, click the Conditions and Deductibles buttons available in this screen. These screens are the same as explained earlier at the header level. ☐ This means that if the discount is selected, these conditions or deductibles would be applicable for the transaction.
---	--

Delete (Product Level)

Click this button to delete the product when there is no transaction available in the system. Sometimes, lots of sample products are configured in the systems which are not required at later stage. The user is allowed to select any existing product from the system and delete the same with proper controls and warnings.

	This facility is available for selective users only.
---	---

Loading (Product Level)

All applicable loadings for a particular line of business are to be pre-defined in the Loading master. Enter applicable Loadings required at the product level. These loadings are defaulted during underwriting if the default option is selected.

	It is possible to attach the same Loading at Section, Risk, Block and Cover levels ☐ It is possible to attach the same Loading Code at any levels such as – Product, Section, Risk and Cover ☐ Based on Cover Type, User is allowed to create the same code for Cover, Discount and Loading.
---	---

Loading Code*	Description	Rate Per Round To*	Mandatory	Default	Refund Allowed	Default on Renewal	Brok. Comm. Appl.	Sep. AC Entry
5001	Special Loading	100.00 00	☐	☐	☒	☐	☒	☐
5004	General Loading	100.00 00	☐	☐	☒	☐	☒	☐
5012	Overage Loading	100.00 00	☐	☐	☒	☐	☒	☐

☐ Add RI Y/N ☒ Rate Modify Y/N

Effective From: Effective To:

Round To:

Short Description: Long Description:

Short Description: Mutual Excl. Group ID:

Bi-Lingual Details:

Fig. 36 – Applicable Loading



Loading Code

Set the applicable loading codes for the product. Codes are picked from the LOV. Three description fields have been provided in this block also. These fields have been explained earlier.

Rate Per

Set the rate per/denominator for the rate for calculation of the loading amount. The rate is set in the Loading block of the 'Other Details' block for the product, during underwriting.



Round To

Enter the rounding off method (number of decimal places) to which the taxes and charges amount is to be rounded off. The description of the method is automatically displayed in the field provided for the same.

☒ Mandatory

Select this checkbox if a particular loading is mandatory for the product. Once set as mandatory, the policy will not be issued without adding loading.

☒ Default

Select this checkbox if the loading is to default in the Loading block during underwriting.

☒ Refund Allowed

Select this checkbox if the refund is applicable for the loading.

☒ Default on Renewal

Select this checkbox if the loading is to be defaulted during renewal of the policy.

☒ Broker Commission Applicable

Select this checkbox if broker commission is applicable for the loading. If selected, broker commission is calculated for the loading amount entered during underwriting.

☒ Separate AC Entry

Select this checkbox if the loading applicable is to be accounted separately and not along with the premium. This allows the system to pass a separate accounting entry for the policy loading.

Effective From and To Dates

Set the validity period if certain loadings are to apply only for a certain period. Enter or select the 'From' and 'To' dates from the calendar using the LOV.

Others

Click this button to define the following for Product Setup:

The screenshot shows the 'Product Setup' window with the following sections:

- Long term:** Renewal Long Term Type (No), Min. Long Term Period (empty).
- Renewal:** Renewal Notice Day (365), Auto Ren Proc Day (365), Ren Ident Proc Day (365).
- Others:**
 - Terrorism Applicable (checkbox), Terrorism for All Risk* (checkbox), Lapsation Process Applicable (checkbox).
 - Extn. Allowed for Short Period Policy (checkbox), RA Appl Y/N (checkbox), RA At* (checkbox), Link Policy Applicable (checkbox).
 - Combine Link Alloc (checkbox), Check Mandatory Cols For All Fields (checkbox), Advice Date Applicable (checkbox).
 - Cum. Bonus Applicable (checkbox), Cum. Bonus Refund Applicable (checkbox), Max. Cum. Bonus Perc (empty).
 - Date Entry Allowed For Advice Date (checkbox), Restrict Covers in Open Certificate Y/N (checkbox), Prem-Charge Check Req. (checkbox).
- Claims:**
 - Loss Date Validation Req (checkbox), Reinstatement Validation Req (checkbox), Claim Intimation Days (180).
 - Cover Breakup Validation Req (checkbox), Claims Ratio Years (empty), Claim Close Proximity Days (5).
 - Retroactive Date Validation Req (checkbox), Duration For Survey Report (empty).
- IDV:** IDV Calculation Req (checkbox), IDV Calc Type (empty).
- Installment:** Installment Allowed (checkbox), Months Prior To Policy Expiry (empty).
- RI:**
 - RI Treaty Basis (Risk), RI Prem Type (On Net Premium(Total P...), Endt RI Treaty Basis (Normal Basis), Ceding Basis (On Gross Rate (Total Pr...)).

A 'Back' button is located at the bottom center.

Fig. 37 – Other Details

Long Term



Renewal Long Term Type

This field is applicable more popularly for Fire Class of Business.

Selection of a particular type of method results in long term discount being applicable/not applicable as well as cause changes in the calculation logic.

Select the renewal long-term type from the drop-down list. The options available are:

- ☐ **Method A** – Premium calculation will follow this logic [(1 yr premium * 10 years) - Long term Discount)]. SI is fixed for the policy period. SI maybe incremented by a certain % every year during the period of the policy. This incremented SI is taken during the time of renewal or claim.
- ☐ **Method B** – Premium is calculated on the fixed sum insured for the policy period. No increase in sum insured is allowed every year as available in Method A. Discount is applicable on premium as per the tariff defined for it, for example as indicated in the sample tariff below:

Duration of Policy	Premium to be Charged
3 years policy	3 years premium in advance less 15% discount
4 years policy	4 years premium in advance less 20% discount
5 years policy	5 years premium in advance less 25% discount
6 years policy	6 years premium in advance less 30% discount
7 years policy	7 years premium in advance less 35% discount
8 years policy	8 years premium in advance less 40% discount
9 years policy	9 years premium in advance less 45% discount
Policy for 10 years and above	Entire premium in advance less 50% discount.

☐ **No** – Long Term not applicable

Minimum Long Term Period

Specify the minimum long term period.

Renewal

Renewal Notice Day

Specify the number of days before which, the renewal notice has to be sent for the policy.

Auto Renewal Process Day

Specify the number of days up to which automatic renewal process is allowed if the policy is qualified for renewal.

Renewal Ident Process Day

Specify the number of days up to which renewal identification process is allowed prior to policy expiry.

Others

☒ **Lapsation Process Applicable**

Select this checkbox to view or modify the status of lapsed quotations/policies. When this checkbox is selected, the status of lapsed quotations/policies is modified to 'Expired' by a single 'Lapsation Processing' step.

This is done to indicate that the policy has been lapsed and cannot be renewed with all renewal benefits. User can issue only as a new policy.

☒ **Extn Allowed for Short Period Policy**

Select this checkbox to allow extension of the cover for a short period policy. This is to be carried out in the transaction level as an endorsement.

Extension of short period policies is not allowed as an endorsement if this checkbox is not selected.

☒ **RA Applicable YN**

If RA Applicable is set as 'Yes', then risk accumulates for this product. This allows user to enter the RA Group ID at section level with combination of accumulation criteria defined, for example, as 'Type of Industry and Risk Location' or 'Type of Industry, Occupation and Risk Location'.

RA At

Specify the level at which the RA is applicable as one of the following:

- ☐ Automatic Risk Accumulation Allocation
- ☐ Manual Risk Accumulation Allocation
- ☐ Both Automatic & Manual Risk Accumulation Allocation applicable

Check Mandatory Columns for all Fields

Situations arise where some information is missing at the time of generating a policy, but nevertheless the policy needs to be issued to the customer.

In such situations, PREMIA takes care by generating a System Generated Cover Note (SGN). This note is issued in lieu of the policy, but the risk coverage takes effect only after the requisite details are made available.

These mandatory fields are defined in the mandatory block of the 'Block Definition' screen from the Product Setup. The policy is issued once the required details are entered.

Select this checkbox to enable the application to automatically prompt the user during underwriting, that a SGN is issued.

☒ **Advice Date Applicable**

Select this checkbox to enable the display of a similar checkbox at underwriting transaction level for the policy.

This enables the user to provide a provisional period for a policy if the correct period of insurance is not available at the time of issuance of policy. The provisional period will be substituted with the correct period subsequently, as first endorsement of the policy.

☒Cumm. Bonus Applicable

Select the check box to specify if cumulative bonus is applicable.



This is applicable only for health policies. On checking this field, the 'Cumulative Bonus' Tab is enabled in the Details Block.

☒Cumm Bonus Refund Applicable

Select the check box to specify if refund is applicable for the cumulative bonus.

Max Cum Bonus Percentage

Depending on the property set in the Cumulative Bonus Applicable field, enter the maximum limit for the cumulative bonus percentage. The value entered here is validated during transactions. For example, if the maximum cumulative bonus percentage is set as 50% and the bonus percentage or deduction percentage in the Cumulative Bonus block is set as 5% then at every renewal, PREMIA automatically increments or decreases the cumulative bonus sum insured by 5%. This increment is up to the limit of 50% of the previous policy sum insured for increase or till it reaches the zero level in case of decrease. If the maximum cumulative bonus percentage is set as 50% and the deduction percentage in the Cumulative Bonus block is set as 5% then at every renewal, PREMIA automatically decreases the cumulative bonus sum insured by 5%.

☒Date Entry Allowed For Advice Date

Select the check box to allow the user to enter the date for advice date policies.

☒Restrict Covers in Open Certificate YN

On selecting this check box the covers selected in Open Cover only will be allowed to select in Open Certificate.

☒Premium Charge Check Req

Select this check box if the tax and charge amount should exceed the premium amount for the new policy.

Claims

☒SI Validation Required

Select this checkbox, if the Policy Sum Insured is to be validated at the time of claims registration and settlement.

If selected, the initial reserve amount is verified against the sum insured and if it is found greater, that claim is not registered.

☒Reinstatement Validation Required

Select this checkbox once the claim is made, if the reinstatement validation on the sum insured is required. At the time of claim settlement, PREMIA automatically validates whether the sum insured is reinstated to its original value. The claim is settled only after reinstatement.

Claim Intimation Days

During Claim Registration the system checks whether the claim intimated date lies within a reasonable time which is set in this field. If a claim is reported beyond the maximum number of days within which it needs to be reported, a pop-up warning message during claims transaction prompts the user either to reject the claim or continue with its registration after proper authorization.

☒Loss Date Validation Required

Select this check box if the loss date validation is required for claim setup. Based on this check box value (if set to Y), the system will validate if the loss date is within the policy effective from

and to dates.

Claims Ratio Years

Enter the number of years. This is the number of years of previous claim history to be taken into consideration, while calculating claims profit and loss statistics.

Claim Close Proximity Days

Enter the number of days to be considered as the close proximity period. This value is used to alert the user if a claim is registered within 'n' days of the policy inception date. For example, if user enters 7 in this field and a claim is registered within seven days of issuing the policy, a warning message alerts the user that a claim has been registered within seven days of issue of the policy.

☒ Cover Breakup Validation Required

During claims settlement, based on the various covers selected, user has the option of breaking up the settlement value.

Select this checkbox, if the sum insured against each cover of the policy is to be validated with the values entered in Break Up by Covers block during claims settlement.

☒ Retroactive Date Validation Required

	This field is normally applicable for liability policies.
---	---

Select this check box if a claim is to be allowed to be registered on the transaction, before and after the current policy period (renewal). This is based on the inception date of the previous policy/ies.

Duration For Survey Report

This field refers to claims and the number of days from the date of appointment of the surveyor. Based on this value, for any claim on this product, the Surveyor Report has to be submitted. For example: A surveyor gains credit, when submitting a report within the specified date.

Insured Declared Value (IDV)

☒ IDV Calculation Required

This field is applicable only in the case of auto products.

Select this checkbox if the Insured Declared Value (IDV) calculation is applicable for the product. This is the sum insured value of the vehicle. This is also applicable for renewal policies.

This value is decided based on certain criteria such as the current date, market value, year of manufacture of the vehicle, and the depreciation percentage applicable for the number of years the vehicle is in use. Based on these criteria the new IDV is arrived at. The deciding criterion is stored in the IDV master.

IDV Calculation Type

Select the calculation type as one of the following:

- ☐ Expiring Policy IDV – Depreciation percentage will be applied on the original policy SI to arrive at the renewal policy IDV SI
- ☐ Invoice value of the vehicle – Depreciation percentage is applied on the invoice value to arrived at the renewal policy IDV for the year

Installment

☒ Installment Allowed

Select this check box if installment option is allowed for payment of premium.

Months Prior To Policy Expiry

If installment is applicable then enter the number of months prior to the expiry of the policy

before which the final installment is to be collected.

For example: If user enters 3 in this field, the final installment amount is to be collected three months prior to the policy expiry date.

RI

RI Treaty Basis

Set the Reinsurance Treaty Basis for the product. By default, the system sets the RI treaty basis at the Risk level. During underwriting, treaty allocation is based on the RI treaty basis defaulted from this setup. The available options are:

- ☐ Risk – Allocation is done for every risk
- ☐ Policy – Allocation is done at the policy level, i.e., for the policy Sum Insured and premium
- ☐ Top SI – Allocation is done for all the risks in the transaction in the same proportion as the allocation for the top SI
- ☐ Top PML / SI – Allocation is done for all the risks in the transaction in the same proportion as the allocation done for the risk with the highest PML SI

RI Premium Type

Select the RI Premium Type as one of the following:

- ☐ On Gross Premium (total premium) – the gross calculated for the policy premium (before considering any policy level discount or loading) is allocated to RI
- ☐ On Net Premium (Total Premium – Discounts + Loadings) – net premium is allocated to RI

Endorsement RI Treaty Basis

Set the endorsement reinsurance treaty basis for the product. By default, this basis is set at the Normal Basis level. During underwriting, endorsement treaty allocation is based on the treaty RI basis defaulted from this setup.

The available options are:

- ☐ Unearned Premium Basis – On selecting this option, PREMIA follows the following process.
 - o The endorsement premium along with the unearned premium of the policy or risk is allocated on approval of the endorsement. For this, the unearned premium is calculated for the policy or risk
 - o A reverse entry is passed for the already allocated sum insured
 - o A reverse entry is also automatically passed for the earlier premium allocation
 - o A re-allocation of the Total sum insured (Policy SI + Endorsement SI) and (Endorsement Premium + Unearned Premium) is done
- ☐ Normal Basis – On selecting this option, PREMIA follows the following process:
 - o No calculation of earned or unearned premium or reversal on earlier sum insured & Premium.
 - o Limits of allocation are validated based on Total sum insured (Policy SI + Endorsement SI)
 - o Allocation is on the Total sum insured & Endorsement Premium alone

Ceding Basis

By default the option is set on the On Gross Rate basis in the Master. If ceding basis is On Net Rate, then the application deducts the agency commission from the premium and only the net is taken for allocation.

The available options for ceding basis are:

☐ On Gross Rate (OGR) – Total premium (i.e., agency commission calculated for the policy is not deducted)

☐ On Net Rate (ONR) – (Total premium – Agency commission)

Section – Policy Type Screen

The Product Setup is defined at two levels in PREMIA – Product Level and Section/Policy Type Level. This facility is provided for greater flexibility and depth. Details entered at the product level are applicable for the product as a whole. The Section/Policy Type level is provided to handle variations in the products such as Package Policies. Sections and Policy Types are pre-defined in the respective masters before attaching them to the product. This is better explained through the following illustrations:




Fig. 38 – Illustration 1 – Section to one Product/Policy Type

In the above illustration, the Product and Policy Type are the same. The section is in-built within the product. If the product has only one section, define a mandatory default value for the Section and Policy Type.




Fig. 39 – Illus 2 –Policy Type within a product are mapped to multi sections

In the above illustration, single policy type is defined for a product, which is mapped to the multi section. This block becomes relevant for any package/umbrella policy. Each section is defined with its own Coverage, Conditions, Deductibles, Loadings, Discounts, and so on.

In PREMIA:

- ☐ All products are linked to a section
- ☐ There is only one unique combination of a Section and Policy type
- ☐ If the Product and Policy types are the same, then mapping is on a one-to-one basis within the section
- ☐ All applicable Conditions/Coverage, and so on are defined for a combination of product and section codes

TAB Section

Click this tab to define the applicable sections for the product. This block becomes relevant for any package/umbrella policy.

For example, consider a product type named 'Office Multi Cover'. The various sections under this product type would include:

- ☐ Standard Fire Policy
- ☐ Personal Accident
- ☐ Money Insurance
- ☐ Fidelity Guarantee Insurance
- ☐ Workmen's' Compensation Insurance
- ☐ Public Liability

Based on the section selected, the details of the risks can be entered along with the applicable covers. For example, on selecting 'Standard Fire Policy' section, the risk details applicable for fire are displayed allowing the user to enter the Material Damage Risk details for Fire product.



For all non-package policies the user has to define a mandatory default value for the section and policy type. This value needs to be set in the Section Master and Policy Type Master for the particular product.

Click 'Section' tab to view the screen shown below:

Fig. 40 – Section Tab



Section Code

Attach the applicable section code/s for the product from the LOV. The description of the code is automatically displayed. These sections appear in the Section tab screen during underwriting.



Policy Type

Set the policy type for the selected combination of Section and Product code from the LOV. Once the code is entered, the description is automatically displayed. The policy types set here are displayed in the LOV of the Policy Type field in the header block of the underwriting screen.



- ☐ The combination of Section Code and Policy Type is unique.
- ☐ In some products, premium calculation is also based on the sum insured of the subject matter to be insured. In such cases, the rate indicator for it is to be defined separately. This field is enabled or disabled through the Instance Definition.

RA Group ID

If RA Applicable is set as 'Yes' (in the 'Others' block), then risk accumulation is applicable for the product. This allows the user to enter the RA Group ID at section level.

Select from the LOV, the RA Group ID. The LOV displays the combination of fields applicable for risk accumulation for example,

- ☐ 000012 - Type of Industry, Risk Location
- ☐ 000010 - Type of Industry, Occupation, Risk Location



For Example:

- ☐ For Fire the Accumulation Limit is based on Location id/Postal code
- ☐ For Marine the Accumulation Limit is based on the Vessel code
- ☐ For Bond Accumulation Limit is based on Guarantor
- ☐ For Personal Accident Accumulation is based on Individual id

SMI Rate Indicator

If premium calculation is based on the sum insured of the SMI, set the rate indicator for the calculation of the premium. The method of populating the rate during underwriting is set here. The options are:

- ☐ Derived from Tariff – Pre-defined rates set in the Rating master
- ☐ Derived from Tariff and Modified – Rates pre-defined in the Rating master, which are modified during underwriting
- ☐ User entered Rate – User enters the rate
- ☐ No Rate, User entered Premium – No rate is required, and user enters the premium amount directly

☒ Duplicate Subject Matter Insured Allowed

Based on the requirement, through the instance definition, this field is also enabled or disabled. Select this checkbox, if for a combination of product/section/policy type, duplication of the subject matter to be insured is to be allowed during underwriting.

Minimum Premium

This field is used to set the minimum premium applicable for the particular risk. The application, accepts a premium for the individual risk only if it is above the minimum premium defined in this field. Else, based on the value defined for system parameter MIN_MAX_ERR an error message is raised or the premium automatically increased to this amount.

- ☐ Subject Matter Insured is setup only at the Section/Policy Type level
- ☐ Coverage is setup for a Section/Policy Type as also for a Block
- ☐ User is allowed set default a deductible value at SMI level during claim registration by selecting SMI-Deductible block and selecting % (percentage) of claim as the deductible type and entering the Deductible Value. During Claims Registration and Processing, this deductible value is validated against the estimate amount and is displayed in the deductible block

Block Definition – Dynamic Risk Blocks

One outstanding feature of PREMIA is the ability to configure the Risk blocks for a product as well as product-specific data items. This functionality helps users for relating to their requirement in contrast to the situation where the user is loaded with various data blocks and data items common across products.

This is helpful for the operator to glide through the application entering data without worrying about applicability of that data for a product or not. For the administrator, this provides the functionality to add a data item in the product setup, whenever a sudden requirement comes up and it is available instantly for all the application users. All blocks come with a set of pre-defined fields that takes care of requirements to enter Code and Description, Number values, Yes or No values, and so on.



User is able to set multiple blocks for a section and also set the level / order of appearance of each of these blocks. For multiple section policies user is allowed to set multiple blocks for each section.

Click on the Section code for which the user needs to configure the Risk blocks and then click on the 'Block' tab. The Product and Section codes and the relevant Table Name are automatically displayed on entering this screen. In PREMIA, all blocks are defined under one table structure. Data for all fields under a selected block are stored in the specific table name.

This table name is automatically displayed in the Table Name field.

Block (Section Level)




Fig. 41 – Block Definition

Level No

Level Number 1 is automatically defaulted on opening the 'Block Definition' screen. If multiple blocks are required for the section, set the necessary levels for each of these blocks.



Levels that define here determine the flow and position of the various blocks within the section during underwriting.


Serial Number

Serial Number 1 is defaulted on opening the 'Block Definition' screen. The correlation between the Level and Serial fields is as follows:

A single level has a maximum of five serial numbers defined under it. This is useful when there are multiple blocks. The serial number specifies the logical position of the block for the level number. The level and serial number set for blocks is reflected in the Underwriting screen.

- ☐ All level number and serial number combinations are unique
- ☐ A maximum of 25 blocks (combination of level and serial numbers) are used for a particular product/section
- ☐ The combination of Product Code/Section Code/Level Number/Serial Number should be unique

Level Number – Serial Number Schematic



Block Name

This field links the selected block to the section and the way fields are displayed for the block. Pre-defined block names are accessed through the LOV. Blocks support both Single Record view and Multi-Record view. These are pre-defined in the table structure. There are twenty blocks available in PREMIA. These are:

Single Record View (sample screen)

The sample screen shows the 'Vehicle Info' section with various fields for vehicle details. The fields are organized into a grid-like structure with labels and input fields. The fields include:

- Vehicle No. (001)
- License Plate Number
- Vehicle Type (001)
- Misc. Vehicle Description
- Rented Motor Home
- Recon. Vehicle
- Customized Van/Truck
- Factory Installed
- Value of Customized equipment
- Desc. of Customized equipment
- Customized report attached?
- VIN Verified
- VIN (003)
- Vehicle Year (1995)
- Vehicle Trade (009)
- Vehicle Model (020)
- Body Type (009)
- Cylinders (6)
- Engine Size (2310)
- Restriant System
- Turbo
- Age (9)
- Symbol
- One Ton
- Four Wheel Drive
- Cost (20000)
- Business Use Class* (002)
- Size Class* (001)
- Fleet*
- Radius Class* (001)
- IRPM* (1)
- Age Group* (006)
- Vehicle Classification* (001)
- Zone Rated*
- Comp. Deductible Amount* (500.00)
- Collision Deductible Amount* (1,000.00)
- Original Cost* (20,000.00)
- Limit of Liability* (18)

Fig. 42 – Single Record View

Multi Record View (sample screen)

Sl.No.	Accdt. Date	Accdt. Desc	At Fault	BI Amt.	PD Amt.	OTC Amt.	COLL Amt.	Total Points

Fig. 43 – Multi Record View

Link Level Number


The link level number is automatically defaulted based on the entered level number. This link number is the level number of the higher-level block to which, the current block is attached. The link level number is always one less than the level number.

Link Serial Number

The link serial number specifies the serial number of the parent block serial number to which, this block is to be linked. A Parent-Child relationship is established through this linking.

Link Block Name

For a parent-child combination, the name of the parent block is displayed in this field. The correlation between level and serial number is explained with the following example. Consider the risk requirements of Fire Policy.



Block Type

In certain cases, multiple risks are defined for the same policy with each risk having the same set of risk details to be captured. This is possible through a single record block where on pressing the DOWN ARROW key when in the first field of the Risk details block of the underwriting screen so as to enable the entry of multiple risks.

Choose the right block type through the Product Setup master to restrict the entry of records in a single record block. Select the type from the drop-down menu options available:

- ☐ Single Record – If this is set, only one record is entered for a particular risk
- ☐ Multi Record – If this is set, multiple records are entered for the same risk by using the DOWN ARROW key

☒ **SMI Attached**

Select this checkbox, if the Subject Matter Insured (SMI) button is to be attached to this particular block for the product in the Underwriting screen. The SMI button is displayed in the Risk block of the Underwriting screen. Characteristics of this button are:

- ☐ This button is attached only once for a product
- ☐ This button is attached at any level number, but the serial number is always 1

☒ **Discount/Loading Attached**

Select this checkbox if discounts/loadings are applicable for this risk block. The Discount/Loading button in this screen is enabled once this field is selected and the applicable Discount/Loadings are defined for the block.

Select this checkbox to enable the Discount/Loading button in the Risk block of the underwriting screen also. This button is attached at any Level number and Serial number.

☒ **Deduction Attached**

Select this checkbox if deductibles are applicable for this risk block. The Deductibles button in this screen is enabled once this field is selected and the applicable deductibles are defined for the block. Select this checkbox to enable the Deductibles button in the Risk block of the underwriting screen also. This button is attached at any Level number and Serial number

Label

Enter the label or caption of the block. This is the name that is visible in the risk section of the Underwriting screen.

☒ **Cover Attached**

In PREMIA, covers are attached only at Level number 1 Serial number 1.

Select this check box if covers are applicable for the risk block. The Cover button is enabled in the risk section of the Underwriting screen for this block. Characteristics of this button are:

- ☐ This button is attached only once for a section

☒ **Display Built-in Cover**

Select this check box if the built-in covers are to default for the block during underwriting.



Cover (Block>Section Level)

At Applicable cover level, on clicking 'Discount' or 'Loading' button; it is possible to attach an existing Discount/Loading Codes with multiple Cover Codes.



Discount /Loading (Block>Section Level)

Click this button at the section level to enter the applicable discounts for that product at section level. If the 'Default' check box in the 'Applicable Discount' screen is checked, the records are defaulted during the transaction risk level.

Block Definition
Product: 1001 Motor Commercial
Table Name: PGIT_POL_RISK_ADDL_INFO
Block Type: Multi Record
Section: 100101 Motor Commercial
Block Name*: PGIT_POL_RISK_ADDL_INFO_01
Level No: 1
Serial No: 1

Applicable Discounts Version No: V-10.10.00

Discount Code*	Description	Rate Per Round To*	Mandatory	Default	Refund Allowed	on Renewal	Brok. Comm. Appl.	Sep. AC Entry	NCB Disc	Effective From	To
4001	Special Discount	100.00 00	☐	☐	☒	☒	☒	☐	☐		
4005	No Claim Bonus/Discount	100.00 00	☐	☐	☒	☒	☒	☐	☐		
4006	Upfront Discount	100.00 00	☐	☐	☒	☐	☒	☐	☐		
4007	Fixed Discount	100.00 00	☐	☐	☒	☐	☒	☐	☐		

Add RI Y/N ☒ Rate Modify Y/N ☒ Rate Key:
Long Description: Special Discount
Round To:
Short Description: Special Discount
Mutual Excl. Group ID:
Short Description:

Bi-Lingual Details

Fig. 44 – Applicable Discounts

Block Definition
Product: 1001 Motor Commercial
Table Name: PGIT_POL_RISK_ADDL_INFO
Block Type: Multi Record
Section: 100101 Motor Commercial
Block Name*: PGIT_POL_RISK_ADDL_INFO_01
Level No: 1
Serial No: 1

Applicable Loadings Version No: V-10.10.00

Loading Code*	Description	Rate Per Round To*	Mandatory	Default	Refund Allowed	on Renewal	Brok. Comm. Appl.	Sep. AC Entry	Claim Loading	Effective From	To
5007	Claim Loading	100.00 00	☐	☐	☒	☒	☒	☐	☐		

Add RI Y/N ☒ Rate Modify Y/N ☒ Effective From:
Effective To:
Round To:
Short Description: Claim Loading
Long Description: Claim Loading
Short Description:
Mutual Excl. Group ID:

Bi-Lingual Details

Fig. 45 – Applicable Loading



The same Discount/Loading Cover Code cannot be defaulted at Risk Level.

TAB Field Definition

The Field Definition screen is used to define all the required fields for a risk block and to set the field properties. If multiple blocks exist for the section then multiple field definitions are set. The X and Y positions, order of appearance, field attributes and properties for each field are set here. The fields defined here appear in the block during Underwriting.

Fig. 46 – Field Definition

Field Name

Field names are pre-defined in the application and are picked from the LOV.

The application provides both static and dynamic fields. For example, Data, Number, Description, Y/N, Code, and Date are some of the dynamic fields available. Fields such as PRAI_PML_AMOUNT, and PRAI_AOA_LIMIT are the static fields defined to take care of certain functional requirements. All fields follow the same naming notation.

A new field name cannot be created/entered in this field

Data Type

Set the applicable data type for the field. Options are:

- ☐ Date
- ☐ Number
- ☐ Text
- ☐ Yes/No

Display Length

Enter the display length for the field. The length set here defines the length of the field for data entry during underwriting.

Tariff Type

Set the tariff type for the field. The type set here defines the rate parameter to be used during underwriting. Options are:

- ☐ Data Element – This is only for data capture. No validations and calculations are associated with this type
- ☐ Data Element and Tariff – By setting this option, rate parameters/validations are applicable for this field during underwriting. The Rate Range check box is enabled and

user is allowed to set the rate range for the field. The range set here is used in the Rating masters to arrive at the rate

☒ **Tariff Range**

If 'Data Element and rate' are set as the rate type, this field is enabled.

Select this checkbox if a rate range is to be set for this particular field. If selected, the values of 'From' and 'To' range fields are automatically defaulted in the Rate Section Parameter Setup master under the Rating master. Once the range is defined in the above master, it is used in the Rate Cover Parameter Setup master to arrive at the rate for a particular cover.

Table Type

Select the table type for the field from the drop-down menu. Options are:

- ☐ Base Table – information in the field is stored in the database
- ☐ Non-Base Table – these are memory variables also used as the second table whenever required

Serial Number

This serial number determines the sequence in which the fields appear in the block during underwriting. This field is automatically populated in a running serial number order starting from '1'. User may alter it if necessary.

Boiler Plate Text

Enter the boilerplate text or caption for the field. This text is displayed for the field during underwriting.

Hint

A hint is a prompt to the user and explains the needed value to be entered in that field during runtime. That prompt is displayed at the bottom of the Underwriting screen.

Default Value

If a constant or default value is to be populated for this field during underwriting, enter the value here.

X and Y Position

Set the X and Y position coordinates for the fields as they need to appear in the Underwriting screen.

☒ **Hide**

Select the checkbox if the field is to be hidden from the user during underwriting. This is later reversed. A hidden field is neither mandatory nor editable.

☒ **Mandatory**

Select this checkbox if the field is to be made mandatory during underwriting. A mandatory field automatically becomes editable. However, the reverse is not true.

☒ **Enterable**

Select this checkbox if the user is allowed to navigate to this field during underwriting. If cleared, the TAB key navigation to this field does not work at runtime.

☒ **Updatable**

Select this checkbox if the user is to be given rights to modify the data entered in this field during underwriting

☒ **Claims Lookup**

Select this checkbox if the value entered in this field during underwriting is to be called during claims.

☒ **Correction YN**

Select this check box if the user wants to modify the details in the Policy correction screen.

Function Id

Capture the ID specific to the function that is defined by a coding 'Procedure'. This field is user enterable and is not mandatory.

Format Mask

Set the format mask for date and number data type fields. For example, for the date field set the format mask as mm/dd/yyyy. Once the format mask is set, during underwriting no other format mask is specified.

Number Range From and To

Set the number range for a number type field. Enter the From and To ranges for the number. Once set here, user is not allowed to enter numbers that do not fall within this specified range during underwriting.

Date Range From and To

Set the range of date for a date type field. Enter the From and To ranges of the date. Once set here, user is not allowed to enter any date that does not fall within this specified range during underwriting.

☒ RA Appl Y/N

If this check box is set as 'Yes', then risk accumulation happens for this product. This allows the user to enter the RA Group ID at section level.

In the RA group ID some fields are specified based on which the risk accumulates.

On selecting a particular RA group ID in the Section level, the fields defined for it in the 'RA Group ID' get defaulted in this block as fields and only for those fields the 'RA Appl Y/N' is checked by default.



User cannot un-check it.

☒ IDV Appl. Y/N

On selecting this field, the fields are defaulted in the IDV Master. In the IDV Master, the IDV is provided for various combinations such as vehicle makes, age and so on. During policy creation, based on the vehicle make and age, the system takes the IDV details from this master.



This field is also available at SMI level and Cover level. If it is checked then the IDV is updated in the respective SMI or Cover levels during the policy creation.

☒ IDV Sequence no

Define the IDV sequence number for each data element. Based on the number entered here the fields are displayed in the IDV Master in the ascending order. If two fields have the same sequence number then the system displays the records as per the number generated in the 'Serial Number' field.

TAB

Mandatory Columns Block

Click this tab to specify a field to be set as the mandatory field. Fields entered in this block are validated at the time of transaction. For example, if two fields are entered in this block and leave them as blank in the transaction screen, a System Generated Cover Note (SGN) is created. This note is issued in lieu of the policy, but the risk coverage takes effect after the requisite details are made available.



System Generated Cover Note is converted to a policy only if values are entered in these mandatory fields.

Field Name*	Effective From	Effective To
Premium Display	29/11/2013	29/01/2014

Fig. 47 – Mandatory Column

Field Name

Set the mandatory field name from the LOV. The LOV displays those field names already defined in Field Definition. Fields set here are validated at the time of transaction.

Effective From and To Dates

If the mandatory property for the field is to be set for a certain period, set the From and To dates from the calendar icon.

TAB Validation

Click this tab to view the uniqueness of values in particular fields or a combination of field's that needs to be validated. This facilitates the user to avoid duplication of data in multi-record blocks for a specific field.

Enter the required fields and set the order in which the validation is required. The system displays the screen as shown below.

Field*	Field Sl. No
Premium Display	1

Fig. 48 – Applicable Validation

Field

Enter or select the field name from the LOV. The LOV displays codes that have already been defined in Field Definition.

Field Serial Number

Enter in this field, the order in which the validations are to be carried out. For example, if the field 'License' has a field serial number "2" and another field 'Vehicle Code' has a field serial number "1", this implies that the 'Vehicle Code' field is validated before the 'License' field is validated.

Once the user has completed defining the block and the fields, click on the buttons to the right of the block screen to set applicable covers, conditions, discount, loadings, etc at the block level.

Click 'Close' button to close the block definition screen and return to the section block.

Cover (Section Level >Block)

Applicable covers for a particular line of business are pre-defined in the Coverage master. Covers set here are defaulted or available in the LOV of the Coverage block for the section during underwriting.




Fig. 49 – Applicable Cover

Cover Code

Set the applicable cover code for the section. This is accessed from the LOV. Three description fields have been provided in this block also. These fields have been explained earlier.

☒ Basic Cover

Select this checkbox if the selected cover is the basic cover for the product. During underwriting the policy cannot be issued unless this cover is selected. If this field is selected, the Default Cover and Mandatory Cover fields in this screen are also selected automatically but appear disabled. The Mid-Term Cover field is automatically disabled.

☒ Summary Cover

Covers that require showing sub-totals in the Premium Computation Sheet or reports but are not required for any calculation of premium are termed as summary covers. Summary cover stores the premium values to be displayed. They are generally used in situations where summation of covers, loadings, and discounts are required.

Peril Class Code

Multiple covers are grouped and placed under a single Peril Class Code. Based on this Peril Class, reinsurance allocation takes place. Set the required peril class code from the LOV. Peril class codes are pre-defined in the Peril Class master.

☒ Mandatory Cover

Select this checkbox if the selected cover is to be mandatory for the product during underwriting. Once set as mandatory, the Mid-Term field in this screen is disabled.

☒ Mid Term Covers

Select this checkbox if a cover is to be included during the term of the policy. This inclusion is possible only by passing an endorsement. This field is disabled if the cover is set as Basic Cover because a basic cover is included from the start of the policy period and is not included midterm.

SI (Sum Insured) Type

The method for arriving at the sum insured for the cover at the time of premium computation is set in this field. The options are:

- ☐ Entered Value – Sum Insured to be entered by the user
- ☐ Derived from Risk
- ☐ Derived from Rating – The value is pre-defined in the Rating master
- ☐ Derived from Subject Matter Insured
- ☐ Data Element value*Factor*Subject Matter Insured Group total

SMI % of SI

If Sum Insured Type is set as Derived from Subject Matter Insured, set the percentage of sum insured to be derived from the subject matter insured for the cover.

☒ **Default Cover**

Select this checkbox if the cover is to be defaulted during underwriting.

☒ **Default on Renewal**

Select this checkbox for those covers to be defaulted and automatically calculated on renewal, based on the history of the policy such as claims experience.

For example, a new vehicle in auto policy is covered for the first time and not eligible for No Claim Bonus (NCB). However, if there is no claim under this policy during the policy period, the insured is eligible for NCB cover at the time of renewing the policy.

Escalation Field

Set the field to which the escalation logic is to be applied from the LOV, if SI Type chosen is Data Element value*Factor*SMI Group total. These values are applicable only for certain insurance products.

Escalation Factor

Enter the rate or factor to be applied on the escalation cover.

☒ **Built-in Cover**

The built-in cover concept in the application has been added to take care of covers that require multiple rating logics for calculation. Separate built-in covers are created for each required logic and attached to the parent cover. Built-in covers are set at all levels and serials in the various sections. This is unlike the basic cover that is set only at Level 1 and Serial 1. Sum insured and Premium for this cover is not displayed in the Premium Computation Sheet and is not used for RI allocation.

☒ **Display Built-in Cover**

Select this checkbox if the built-in cover is to be displayed in the Premium Computation Sheet.



SMI Group Code

Grouping is a facility provided in PREMIA, where if 'Sum Insured Type' is set as 'Derived from SMI', only those covers that lie under the SMI group code specified in this field are taken into consideration while arriving at the sum insured.



All SMIs that need to be grouped to derive one SI for a cover are to be pre-defined in the SMI Group master.

☒ **Add to SI**

Select this check box if the sum insured of the cover is to be added to the sum insured of the basic cover.

☒ **Add RI SI**

Select this check box if the sum insured of the cover is to be added to the sum insured for the purpose of reinsurance. The sum insured for cover RI is defaulted in the Peril class mapping of covers.

Rate Per

Set the rate per/denominator for calculating the cover premium. This value is the denominator for the rate set for the applicable cover.

Round To

Set the round off method for the cover premium from the option available in the LOV.

☒ IDV YN

Select this checkbox if the applicable cover represents Insured Declared Value (IDV).

Mutual Exclusion Group ID

Define a unique group Id to identify the applicable covers as mutually exclusive covers. For example, these three cover codes come under mutually exclusive cover.

- ☐ ICC - A (All Risk)
- ☐ ICC- B (Wider Cover)
- ☐ ICC- C (Basic Cover)

During policy transaction when user selects more than one cover from the same mutually exclusive group, then system displays an alert message – ‘Only one cover can be selected from the group of covers ICC ‘A’, ICC ‘B’ and ICC ‘C’, and does not allow the user to complete the transaction unless the user selects a different cover.

☒ Refund Applicable

Select this checkbox if the cover is to be considered for refund in the case of cancellation of the policy.

☒ Modify Rate Allowed

Select this checkbox if, during underwriting, users are to be allowed to modify the rate.

Sum Insured (SI) Value Type

Set whether the cover sum insured is to be validated against the current claim or claims during the policy period. This is validated during claims registration. Select the required type from the options provided:

- ☐ For the Claim – The cover sum insured is validated against the current claim amount and the total sum insured
- ☐ For the Policy period – The cover sum insured is validated against the total amount of multiple claims during the policy period and the total sum insured
- ☐ Not Applicable – No validation is required during registration

☒ Sum Insured (SI) Validation required during Claim

Select this checkbox if the sum insured of the cover is to be validated at the time of claim settlement.

☒ Broker Commission Applicable

Select this checkbox if broker commission is applicable on the selected cover.

Renewal Inclusion/Exclusion

The applicable cover defined here are included or excluded on renewal or the policy is excluded from renewal. Select the required option from the following:

- ☐ Exclude Cover for Renewal
- ☐ Include Cover or Excluded
- ☐ Exclude Policy for Renewal

☒ Apportion Discount/Apportion Loading

Select the respective check boxes to include the applicable cover premium for discount or loading calculation.

Effective From and To Dates

Set the validity period if the cover is to apply only for a certain period during New Policy, Renewal and Endorsement. Enter or select the From and To dates from the calendar accessed using the LOV.

	During copy of the policy transaction the covers which are not applicable for the effective period is not copied to the transaction. But when a cover is defined effective from a specific period and set as default or mandatory, then it will be available when a transaction is copied.
---	--

Bilingual Details

Enter the applicable bilingual description fields.

PREMIA provides the user with the facility of setting applicable 'Conditions' and 'Deductibles' for a cover. If set here, these conditions and deductibles are defaulted during 'Underwriting' once the cover is selected.

The screens in these blocks are the same as those explained earlier at the header level.


	☐ PREMIA also provides the facility to attach Conditions, Discounts, Loadings, and Deductibles at the block level. ☐ The screens are the same as those explained earlier for the header block.
---	---

Field Value Based Defaulting

PREMIA provides the option of defaulting covers, conditions, discounts, loadings, and deductibles based on values entered in certain fields. This is called Field Value Based defaulting.

Once all fields are defined in Field Definition, click the Field Value button available inside any of the Cover, Condition, Discount, Loading and Deductible screens of the Block section to set the value range for fields.

The system displays the screen as shown below:



Block Name	Field Name	Field Value From	Field Value To
PGIT_POL_RISK_ADDL_INFO_01	Seating	2	20

Fig. 50 – Field Value

Block Name

Select the block name from which the field is to be selected to set the field value.

Field Name

All the fields applicable to the block are available in the LOV. Select the field name for which the value is to be set.

Field Value From and To

Enter the value range in this field, for which specific conditions, deductibles, covers, discounts, and loadings are to be defaulted. For example, in a Y/N field if the choice is Y then a specific condition is set by entering 1 in both the Field Value From and To fields. This defaulting condition is defined by entering it in the Conditions screen under 'Block Definition'. Similarly, if the choice is N, another condition is set by entering 0.

Similarly user is allowed to set:

- ☐ Applicable conditions and corresponding field values
- ☐ Applicable deductibles and field values and conditions

☐ Applicable discounts and field values, conditions, and deductibles

☐ Applicable loadings and field values, conditions, and deductibles


Coverage (Section Level)

All covers that are applicable at the Section level are to be defined in this block. This screen is the same as that explained for the Coverage under Block Definition.

SMI (Section Level)

For an insurance contract to be valid, the insured/policy-holder has an insurable interest in the subject matter of insurance. The insurable interest is the pecuniary interest whereby the policyholder is benefited by the existence of the subject matter and is prejudiced by the death or damage of the subject matter. The subject matter is property and goods in property insurance and, liability and adventure in general insurance.

PREMIA provides the facility to enter applicable subject matter to be insured for the combination of section, policy type, and product at the section level. This is useful in certain geographies where a list of items requires one type of cover. While another group of items require another type of cover. The sum insured for the cover depends on the sum insured of the group of items.



The screenshot displays the 'Product Setup' and 'Applicable SMI' sections of the PREMIA software interface.

Product Setup:

- Product Code*:** 3003, Marine cargo-Open cover-Import/Export
- Class Code*:** 30, Marine
- Refund Type:** INCLUDE EFF. FROM D...
- Min. Premium (LC 1):** [Empty field]
- Effective From:** 01/01/2000 To [Empty field]
- Tariff Applicable:** ☐
- Short Desc.:** Marine cargo-Open cover-Import/Export
- Annual Prod Y/N:** ☒
- Inw Comm:** Inward Commission not ...
- Max. Discount Perc:** [Empty field]
- Prod. Dur Type:** Previous Day Mid Night
- IBNR Process Applicable Y/N:** ☐
- Min. Max. SI:** [Empty field]
- Min. Max. Premium:** [Empty field]
- Min. Max. Charge:** [Empty field]

Bi-Lingual Details:

- Description:** Marine cargo-Open cover-Import/Export
- Short Desc.:** Marine cargo-Open cover-Import/Export

Applicable SMI:

SMI Code*	Description	Max Applicable Value	IDV YN	Add to SI	Default SMI	Declaration Y/N ?
23001	Personal Effects	1,000,000,000.00	☐	☒	☐	☐
23002	Hazardous Goods	1,000,000,000.00	☐	☒	☐	☐
23003	Non Hazardous Goods	1,000,000,000.00	☐	☒	☐	☐
23004	Breakable Items	1,000,000,000.00	☐	☒	☐	☐
23005	Light Machinery	1,000,000,000.00	☐	☒	☐	☐

Fig. 51 – Applicable SMI

SMI Code

Set the requisite SMI code from the LOV. Once the code is selected, the description is automatically displayed. All applicable SMIs are pre-defined in the SMI master.

Max Applicable Value

Enter the maximum value applicable for the SMI.

☒ IDV YN

Select this checkbox if the applicable cover represents Insured Declared Value (IDV).

☒ Add to SI

Select this checkbox if the sum insured of the SMI is to be added to the sum insured of the policy for calculation of premium.

☒ Default SMI

Select this checkbox if the SMI is to be defaulted for the section during underwriting.

☒ Declaration Y/N?

Select this checkbox if the declaration facility is to be allowed for the particular SMI.

	User also has the option to enter specific 'Conditions', 'Covers', 'Discount', 'Loading' and 'Deductibles' relevant to the SMI. Screens displayed in these blocks are the same as those explained earlier at the header level.
---	--

Flexi Setup (Section Level)

PREMIA provides the user with the additional flexibility to define extra fields required while doing any setup. Depending on the table where this is required, a minimum of 10 fields and a maximum of 20 fields are provided.

In the Product Setup master, user is provided a Flexi Setup tab with 20 fields to capture additional information required at the Coverage and SMI levels during underwriting.




Fig. 52 – Flexi Setup

Flexi Type

Two pre-defined flexi types are Cover and SMI. These are selected from the LOV.

Select the required type for which extra fields are to be defined.

For example, on selecting 'C' from the LOV it implies that selected fields are reflected at the Cover level in the underwriting screen.

Caption 1 To 20

Enter the caption for the required field. This caption is displayed during underwriting, based on the selected Flexi Type, either in the Cover block or the SMI block. The Navigation of fields is based on the order of the caption numbers.

	PREMIA also provides the facility to attach conditions, discounts, loadings, and deductibles at the Section level. The Screens are the same as those explained earlier for the header block.
---	---

TAB Cum Bonus (Cummulative Bonus)

	This tab will be enabled only when the 'Cummulative Bonus Applicable' check box is selected in the 'Others' block in the Product Setup.
---	--

The system displays the screen as shown below:

Section Cum. Bonus IBNR				
Renewal Year	Bonus Percentage	Deduction Percentage	Effective From	Effective To
1	2.00	1.00	01/01/2013	01/02/2014

Fig. 53 – Cumulative Bonus

Depending on the maximum limit set in the cumulative bonus percentage field in the header block, enter the actual percentage in this screen. The value entered here is validated during transactions. User is allowed to define two types of percentages:

- ☐ Bonus Percentage – This refers to the discount to be given on renewal, in case no claims are registered or experienced by the insured
- ☐ Deduction Percentage – This refers to the loading incurred during renewal, in case claims are registered or experienced by the insured



The total cumulative bonus (Bonus/Deduction) is not allowed to exceed the value entered in the Maximum Cumulative Bonus Applicable field.

Renewal Year

Set the renewal year for which the cumulative bonus (Bonus/Deduction) is to be applied. For example, if user enters 5 in this field, it implies that the bonus/deduction percentage entered in the subsequent field is applicable only for the fifth year. User has the option of setting differing percentages for various renewal periods.

Bonus Percentage

Enter the bonus percentage if no claim experience exists. The total percentage cannot exceed the limit set in the Maximum Cumulative Bonus Percentage field.

Effective From and To Dates

If percentages are to apply only for a certain period, set the validity period in this field. Enter or select the From and To dates from the calendar that is accessed through the LOV.

TAB IBNR

The rates for IBNR and URR are defined used during the URR and IBNR processes. The screen as shown below:

Section	Cum. Bonus	IBNR																		
		<table border="1"> <thead> <tr> <th>Effective From</th> <th>Effective To</th> <th>IBNR Rate</th> </tr> </thead> <tbody> <tr> <td>01/01/2010</td> <td></td> <td>10</td> </tr> <tr> <td></td> <td></td> <td></td> </tr> <tr> <td></td> <td></td> <td></td> </tr> <tr> <td></td> <td></td> <td></td> </tr> <tr> <td></td> <td></td> <td></td> </tr> </tbody> </table>	Effective From	Effective To	IBNR Rate	01/01/2010		10												
Effective From	Effective To	IBNR Rate																		
01/01/2010		10																		

Fig. 54 – IBNR

Effective From/To

Enter or select the From and To dates from the calendar icon.

IBNR Rate

Enter the rate for IBNR.

VEHICLE QUERY MAPPING (SETTING UP VEHICLE OR SHIPMENT QUERY)

This setup allows users to perform following types of queries:

- ☐ Vehicle Query allows users to search for policies specific to vehicle number, registration number
- ☐ Shipment query allows users to search for policies specific to marine using vehicle name, conveyance type and so on

In order to setup query screens, follow the steps given below:

- ☐ Create a dynamic table and columns using Risk Summary Form
- ☐ Map the fields of the dynamic risk information block with the fields of the newly created table using Dynamic Mapping screen
- ☐ Create a form for Shipment and Vehicle query
- ☐ Create prompts for the mapped fields using Instance screen

Risk Summary Detail

This screen is used to create a risk summary table and the corresponding columns for the vehicle or shipment query.

Risk Summary Detail

Table Name: PDYN_SHIPMENT

Remarks: SHIPMENT

Table Boiler Plate: SHP

Column Name	Column Boiler Plate	Data Type	Precision	Remarks	Add/Drop
SHP_CODE_06	Shp Code 06	VARCHAR2	12	Shp Code 06	☐
SHP_CODE_07	Shp Code 07	VARCHAR2	12	Shp Code 07	☐
SHP_CODE_08	Shp Code 08	VARCHAR2	12	Shp Code 08	☐
SHP_CODE_10	Shp Code 10	VARCHAR2	12	Shp Code 10	☐
SHP_CODE_05	Shp Code 05	VARCHAR2	12	Shp Code 05	☐

Buttons: Create Table, Add Column, Drop Column

Fig. 55 – Risk Summary Detail



Table Name

Enter the name of the table to be created for shipment/vehicle query. Table names are to be prefixed with key word 'PDYN_'. Actually a back end table is created with this name for example PDYN_Shipment.



Remarks

Enter the remarks related to shipment/vehicle query table.



Table Boiler Plate

Enter the text to provide a name for the created table.



Add/Drop

Select this checkbox, if any of columns need to be added or deleted from the table.



Create Table

Click this button to create the table. On clicking, the screen defaults 14 mandatory columns which are created along with the table.

The Detail table allows the user to create new columns and also displays the created columns of the table which are allowed to be added or dropped respectively, as required, except for the mandatory columns:

- ☐ Column Name– enter the name of the column
- ☐ Column Boiler Plate – enter the prompt of the column
- ☐ Data Type – allows users to specify if the details entered has to be numeric or character
- ☐ Precision – allows users to specify the width of the column for character fields; it is mandatory to specify the details
- ☐ Remarks – enter the remark



Add Column


Click this button to add columns for the table. User is allowed to add the column only by clicking this button.

Drop Column

Click this button to delete the columns of the table. User is allowed to delete the column only by clicking this button.

VEHICLE QUERY COLUMN MAPPING (DYNAMIC MAPPING – RISK SUMMARY)

This screen allows the user to map the newly created table with the Risk table columns.



Sr.No	Summary Column Name*	Risk Field Name*
1	Veh Data 01	Chassis No.
2	Veh Data 02	Engine No.
3	Veh Data 03	Reg. No.
4	Veh Data 04	
5	Veh Code 08	
6	Veh Code 09	
7	Veh Code 10	
8	Veh Code 14	
9	Veh Code 15	
10	Veh Code 01	

Fig. 56 – Dynamic Mapping – Risk Summary

Product

Select from the LOV, the product for which users need to map the created table.

Section

Select from the LOV, the section related to product.

Risk Block

Select from the LOV, the risk block related to product

Summary Table

Select from the LOV, the summary table for which users need to map the fields. Once the summary table is selected, 'Summary Column Name' displays all the existing mapped/unmapped columns.

Remarks given against each table, during the table creation are listed this field.

The following are the details displayed:

- ☐ Sr.No – displays the serial number
- ☐ Summary Column Name – displays the column boiler plate
- ☐ Risk Field Name – select from the LOV, the name of fields to be mapped with the summary column

Unmapped Col

This button will be enabled only if any of columns are not mapped. If all the columns are mapped then this button will not be enabled.

	☐ It is possible to map multiple products in one table sharing the similar information. Eg Commercial vehicle Product/Non-commercial vehicles product is allowed to be mapped in the same table wherein the Risk elements are similar. ☐ Advantage of mapping multiple products to one summary table is, say when querying a vehicle detail across products, it will possible for the query to retrieve the same. Query screen discussed in the query manual.
---	--

CUSTOMER

A customer is any entity with whom the company conducts business and who is external to the company. These external entities include individual or corporate customers, agents, surveyors and brokers.

To incorporate information regarding all the external entities, the application provides a common 'Customer Category Master'. Once this process is completed, individual details for all these categories are entered in the respective masters provided.

The 'Custom' master comprises of the following sub-menus:

Masters		Underwriting	
o	System Parameter		
+	Codes Master		
+	Product Master		
-	Customer		
o	Customer Category		
o	Customer Code Creation		
o	Insured Code Creation		

Fig. 57 – Customer Menu

CUSTOMER CATEGORY

The 'Customer Category' screen is used to map various Customer Categories to a pre-defined set of Customer Types. These categories are user-defined.

The system displays the screen as shown below:

Fig. 58 – Customer Category

Category

Enter a unique customer category code. This enables identification of every user-defined customer category during recording of transactions.

Category Description/Short Description

Enter a description of the Category entered in the previous field. The application defaults the Category Description. The user is allowed to modify the Short Description.

Customer Type

Enter or select from the LOV the appropriate Customer Type to map with the new Category being created. The corresponding description is defaulted in the adjacent field.

The values available in the LOV belong to a system defined value set and are not available for modification.

Control Account

Enter or select from the LOV the appropriate code of the control account that needs to reflect the effect of any financial transactions carried out with the specified customer category.

Effective From/To Date

Enter or select the 'From' and 'To' dates from the Calendar help. Click the LOV icon to view the calendar help. These dates specify the validity period of the defined customer category.

☒ Customer Auto Code Generation

Select this checkbox to enable the auto generated serial number (created in the document setup menu) to be the default customer code.



For more information on the Document Setup menu, check the Document Setup user manual.

☒ Prefix Applicable

Select this check box to attach a prefix to the auto generated document number. The prefix enables the user to identify documents generated for different customers.

Prefix

Enter the prefix that needs to be attached to the auto generated document number.

☒ Prefix Validation Required

Select this check box to enable the application to validate the prefix created in the 'Prefix' field.

TAB Control Account Details

This block enables users to define new control accounts and map applicable control accounts for the customer category. For example

☐ 2203006 (Control Acct) – CLAIMS PAYABLE – AGENTS (Description)

☐ 2203503 – COMMISSION PAYABLE - AGENTS

Control Account

Select the control account for the customer category from the LOV. The description is automatically displayed in the adjacent field.

TAB Default Tax

Click this tab to enter the tax category applicable for the customer category. The system displays the screen as shown below:

Tax Category*	Default Tax Y/N
BIT	☐
VAT	☐
WHT	☐
	☐

Fig. 59 – Default Tax

Tax Category

The system displays the list of tax categories.

☒ Default Tax YN

Select the check box to default the respective tax category during customer code creation for that customer category.

CUSTOMER CODE CREATION

Once the customer category is set, individual customers for that category are to be defined using this master. Accounting entries are passed only on the Customer and not on the insured. Details pertaining to the customer such as mailing addresses, currency code to be set, etc are to be captured using this master. The screen is as displayed below:

Fig. 60 – Customer Setup

The header block field entries for all the sub menus within Customer Setup (except for Customer Category menu) are the same. Only the field names change based on the menu.

Category Code

Use this field to select and set the category to which the customer belongs. Enter or select the category code from the list of values. The customer could be a public/private company, a Government organization, co-operative society.

Customer Code

Enter a unique customer code in this field. This field uniquely identifies every customer in the application.

Customer Title

Select the title for the customer as one of the following - Mr., Mrs. Miss and so on from the drop-down list.

Group Code

Use this field to specify the group code to which the customer belongs. This group code is used to identify a particular group of companies that belong to a corporate group (Example: Tata & Sons). The individual companies are to be entered as separate customers and can be attached to the group company based on this code. The group code creates the relationship between various customers belonging to a particular group.

If the customer does not belong to any group, this field may be left blank. Enter or select the group code from the list of values. Once the code is entered, the description pertaining to it is automatically displayed in the adjacent field.


First Name

Enter the name of the customer in this field.

Middle Name

Enter the middle name of the customer.

Last Name

Enter the last name of the customer

Reporting To

Select from the LOV, the reporting manager for the customer.

DOB

Enter in this field, the date of birth of the customer.

☒ **Default Assured YN**

Select the check box to specify whether this customer is to be the default insured for the customer entered for all transactions. If this is checked here, during underwriting transactions, this insured is defaulted automatically on selection of the customer code.

☒ **All Currencies Appl YN**

Select the check box to specify whether all currencies are applicable for this customer.

☒ **Cust Tax YN**

This check box will be automatically selected if 'Default YN' field it is already checked in the Customer Category screen. User is allowed to modify by de-selecting the check box if the customer is exempted from tax for any reason.

Else, select this check box, if Value Added Tax (VAT) / Withholding Tax (WHT) or Business Income Tax (BIT) needs to be captured in the 'Tax' tab and Tax needs to be calculated for this customer at transaction level.


Customer Name

Enter the name of the customer in this field.

Short Name

This field will automatically default the name from the 'Customer Name' field. User may alter it if necessary.

Passport No

Enter the passport number of the customer.

Marital Status

Select the marital status of the customer from drop-down list.

☒ **Local Customer YN**

Select the check box to specify if the customer is a local customer.

☒ **Commercial Customer Y/N**

Check this field, if the defined customer is a commercial customer.



Only if this field is checked, the Commercial Details block is enabled to enter all details pertaining to the commercial customer.

Contact Type

Select the type of customer contact from the drop-down list as –Home/ E-Mail / Phone and so on.

Mailing Address

Use this field to specify the mailing address. All correspondence with the insured will be made depending upon the selection made in this field. This address will appear in the 'Address' block

of the underwriting screen on selection of the insured code. Select the mailing address from the drop down menu. The options available are:

☐ Residential Address

☐ Office Address



Default Broker Code

Use this field to specify the default broker, if applicable, to be linked to the customer. Enter or select the default broker code from the list of values. On entering the code, the description pertaining to it is automatically displayed in the adjacent field.

☒ Credit check required

Select the check box to specify whether credit check is required for this customer.

Credit Limit

This field is enterable only if the 'Credit Check Required' field is checked. Enter the credit limit of the customer in this field.

Credit Days

Enter credit limit in number of days.

Passport No

Enter the passport number of the customer

Effective From and To Date

Enter or select the 'From' and 'To' dates from the Application Calendar, which can be accessed using the list of valid values key. These dates specify the validity period of the insured in the system.

Marketer Code

Select from the LOV, the marketer code



Social Security ID

Enter the unique ID such as the Passport number of the customer.



Reference Number

Enter any reference number from broker or from insurance company in case of FAC in policy. This field is used to post finance details of the policy.



Applicable Branches/Divisions

Click on the 'Appl. Divn' button to set the applicable offices/divisions for the customer. The customer code is displayed automatically on entering this screen. The screen is as displayed below.

Office From*	Description	Office To*	Description	Include?	Marketer Code*	Marketer Desc
100	Head Office	100	Head Office	☒		
				☐		
				☐		
				☐		
				☐		

Fig. 61 – Applicable Divisions

Office From and To

Enter or select 'Office From' and 'Office To' from the list of values. These fields signify the applicable offices for the customer. For example, if this customer is to be available across all the

divisions, enter “0” in the ‘Office From’ field and “zzzzzz” in the ‘Office To’ field. On entering the codes, the description pertaining to them is automatically displayed in the adjacent fields.

Include/Exclude

Check this field to include the customer for the specified division.

TAB Residential Address

Enter in this block, all the details pertaining to the residential address of the customer.

This screen is as displayed below.

Fig. 62 – Residential Address

Address

Enter the residential address of the customer in this field. User is provided with 3 rows for the same.

Country/State/City/PIN Code

Enter or select the Country/State/City/PIN code pertaining to the address entered in the previous field, from the list of values. Once the code is entered, the description pertaining to the code is automatically displayed in the adjacent field.

	☐ The LOV for city displays only those cities belonging to the chosen state
	☐ The LOV for PIN Code displays only those codes falling under the selected city

Phone/Fax

Enter in this field, the phone number and the fax number of the customer.

Contact 1/Contact 2

Enter details of the contact person of the customer for communication purposes. Two fields have been provided for the same.

TAB Office Address

Enter details pertaining to the official address of the customer. The system displays the screen as shown below:

Fig. 63 – Office Address

Office/Flat No / Build No/ Road No /Area Block No

Enter the official address of the customer in this field. User is provided with 4 rows for the same.

City/PIN Code

Enter or select the City/PIN code pertaining to the address entered in the previous field, from the list of values. Once the code is entered, the description pertaining to the code is automatically displayed in the adjacent field.

Country

Enter or select the country from the LOV.

	☐ The LOV for city displays only those cities belonging to the chosen state
	☐ The LOV for PIN Code displays only those codes falling under the selected city

Phone/Fax

Enter in this field, the phone number and the fax number of the customer.

Contact No

Enter details of the contact person of the customer for communication purposes. Two fields have been provided for the same.

Mobile Number

Enter in this field, the mobile number of the customer.

Email 1

Enter the E-mail Id of the customer. User is provided with two fields for the same.

Web Site

Enter in this field, the website URL of the customer.

Click 'Save' to save the setup details. On saving, the system prompts the user to enter the VAT Registration number (if the Cust Tax YN check box is selected).




Fig. 64 – Prompt Message for VAT Registration Number

TAB Commercial Details

This tab is enabled only if the customer is defined as a commercial customer. Use this block to enter all the applicable commercial details of the customer. The screen is as displayed below:

Res Address	Off Address	Commcl Dtls	Currency	Agent	Broker	Dev Officer	Surveyor	Advocate	TDS Party	Stop List	Credit Dtl
Paidup Share Capital		456677.000	Type of Business		Fisheres						
Financial Start Period		01/01/1980	Financial End Period		30/06/2013						
No. of Employees		50	No. of Branches		6						
CMM Level*			Credit agency rating*								
Contact Person 1-Designation		Manager	Phone No.		97897897						
Mobile No.		9079789	Contact Person 2-Designation		Asst. Manager						
Phone No.		9089080	Mobile No.		908908						
Commercial Type*			Date of Registration								

Fig. 65 – Commercial Details

Paid Share Capital

Enter in this field, the paid up share capital of the company

Type of Business

Enter in this field, the type of business being done in the company.

Financial Start/End Period

Enter or select the financial accounting period of the customer. The period is set from the application calendar accessed using the list of valid values.

Number of Employees

Enter in this field, the number of employees in the company.

Number of Branches

Enter in this field, the number of branches the company has.



CMM Level

Use this field to specify the Capability Maturity Model (CMM) level of the company, if applicable.

Credit Agency Rating

Use this field to specify the credit rating of the company, as listed by any recognized credit rating agency. Enter or select the rating code form the list of values. On entering the code, the description pertaining to it is automatically displayed in the adjacent field.

Contact Person-1/Contact Person-2 Designation

Enter in this field, the designation of the contact person. User is provided with two fields for the same.

Phone/Mobile Number

Enter in this field, the phone number and mobile number of the contact persons. These fields have been provided for both the contacts.



Commercial type

Select the type of commercial company from the LOV. The customer may belong to a Private/Public sector, maybe a Government organization or a co-operative society.

Date of Registration

Enter in this field, the date of registration of the company.

TAB Currency

Use this block to set the applicable currency codes to be used for all transactions purposes for the customer. The screen is as displayed below:

Res Address	Off Address	Currency	Agent	Broker	Surveyor	Advocate	Credit Dtl
		Currency Code*	Currency Description	Effective From	Effective To		
		001	US DOLLAR				
		002	INDIAN RUPEE				
		003	JAPANESE YEN				
		004	STERLING POUND				
		005	KUWAIT DINAR				

Fig. 66 – Currency

Currency Code

Use this field to specify the applicable currency code/s for the customer. Enter or select the currency code from the list of values. On entering the code, the description pertaining to it is automatically displayed in the 'Description' field, which is a display only field.

Effective From and To Date

Enter or select the 'From' and 'To' dates from the Application Calendar, which can be accessed using the list of valid values key. These dates specify the validity period of the currency code for the customer.

TAB Agent

Use this block to set the agent related information to be used for all transactions purposes. This screen is as displayed below:

Res Address	Off Address	Currency	Agent	Broker	Surveyor	Advocate	Credit Dtl
			License Number	54/LIN/TN01			
			License Expiry Date	01/01/2015			
			PAN	BBBOK987878			
			Gender	Male			
			Qualification*				

Fig. 67 – Agent

License Number

Enter the license number in this field.

License Expiry Date

Enter or select the license expiry date from the Application Calendar, which can be accessed using the LOV key. These dates specify the validity period of the license of the agent.

Civil ID

Enter the unique identification number for the customer.

Gender

Select the gender of the agent from the drop down menu. The options available are:

- ☐ Male
- ☐ Female

Qualification

Enter or select the qualification of the agent from the LOV. On entering the code, the description pertaining to it is automatically displayed in the adjacent field.

TAB Broker

Use this block to set the broker related information to be used for all transactions purposes. This screen is as displayed below:

Res Address	Off Address	Currency	Agent	Broker	Surveyor	Advocate	Credit Dtl	Stop List	Tax
License Number	License From Date	License Expiry Date	Name of Organization	Name of CEO	Field of Specialization*				
pol9090	01/01/2000	31/12/2030	3i infotech	MB					

Fig. 68 – Broker

License Number

Enter the license number in this field.



License From Date

Enter or select the license From date from the Application Calendar, which can be accessed using the LOV key.

License Expiry Date

Enter or select the license expiry date from the Application Calendar, which can be accessed using the LOV key. These dates specify the validity period of the license of the broker.

Name of the Organisation

Enter the broker's organisation name in this field.

Name of the CEO

Enter the name of the Chief Executive Officer of the brokerage firm in this field.

Field of Specialisation

Each broker firm might specialize in certain class of insurance (Example: Rural). Enter the field of specialization for the selected brokerage firm in this field.

TAB Surveyor

Use this block to set the Surveyor related information to be used for all transactions purposes. The system displays the screen as shown below:

Res Address	Off Address	Currency	Agent	Broker	Surveyor	Advocate	Credit Dtl	Stop List	Tax
License Number	JAGD123								
License Expiry Date	08/05/2014								
Qualification*									
Class of Business*	Category Code*	Description	Effective From Date	Effective To Date					
10	SRV-01	CATEGORY-A	01/01/2000	31/12/2099					
20	SRV-02	CATEGORY-B	01/01/2010						
30	SRV-03	CATEGORY-C	01/01/2010						
40	SRV-01	CATEGORY-A	01/01/2010						
90	SRV-01	CATEGORY-A	01/01/2010	31/12/2099					

Fig. 69 – Surveyor

License Number

Enter the license number in this field.

License Expiry Date

Enter or select the license expiry date from the Application Calendar, which can be accessed

using the LOV key. These dates specify the validity period of the license of the broker.

Qualification

Enter or select the qualification of the surveyor from the LOV. On entering the code, the description pertaining to it is automatically displayed in the adjacent field.



Class of Business

Surveyors, based on their experience and expertise, would be allowed to handle selected classes of businesses. Select the class of business of the surveyor from the LOV.



Category Code

Surveyors, based on their experience and expertise, are categorized as A, B and C. Select the category code of the surveyor from the LOV. The description pertaining to it is automatically displayed in the adjacent field.

Effective From and To Date

Enter or select the 'From' and 'To' dates from the Application Calendar, which can be accessed using the list of valid values key. These dates specify the validity period of the surveyor in the system.

TAB Advocate

Use this block to set the advocate related information to be used for all transaction purposes. This screen is as displayed below:

Fig. 70 – Advocate

Bar Membership Number

Enter the bar membership number of the advocate in this field.

Bar Name

Enter the name of the bar (where the advocate holds the membership) in this field.

TAB Credit Details

Use this block to set the credited related information to be used for all transactions purposes.

This screen is displayed below:

Code*	Description	Credit Limit	Credit Days
10	Motor	400000	
20	Fire	400000	
30	Marine	700000	

Fig. 71 – Credit Details



Code

Select the code from the LOV. The description pertaining to it is automatically displayed in the adjacent field.

Credit Limit

Enter the credit limit in this field.

Credit Days

Enter the credit days in this field.

TAB EFT (Electronic Funds Transfer)

This block enables the user to capture the bank details of the customer/insured for handling the mode of payment as EFT or Auto debit for a customer. User is able to set whether EFT/Direct Debit/Direct credit is applicable for the customer/assured or not.

The system displays the screen as shown below:

Fig. 72 – EFT

A/C No

Enter the bank account number of the customer.

A/C Holder Name

Enter the account holder name.

Bank Code

Enter the bank code (system generated code).

Bank Name

Enter the name of the bank where the customer account is available.

Bank Id

Enter the Bank IFSC code.

Bank Branch

Enter the branch name.

Eff From Date / To Date

Enter the validity period of this bank account in the respective fields.

☒ EFT Appl YN

Select this check box if electronic fund transfer is applicable for the customer with this bank account number.

☒ Dflt YN

Select this check box if this bank account number is to be set as a default account number during EFT manual processing. Although this account number will be defaulted in the EFT manual processing screen, user will be allowed to select the appropriate bank account number.

A/C Type

Specify the account type as Current or Savings account for each bank account available with the customer.

EFT Trans Type

Specify the fund transfer type. Select the required option to set the customer /insured account number for one of the following:

- ☐ Payment – to debit the premium from the selected Bank account
- ☐ Receipt – to receive commission or credit the Insured account directly in case of refunds or settlement of claims
- ☐ Both – both, payment and receipt

Remarks

Enter remarks if any towards EFT.

TAB **Stop List**

This block enables users to restrict specific transactions for a customer based on the customer stop list (Claims Payment, Claims Recovery, Extension of period, Renewal) type selection.) (The blacklisting processes for the customer up to a specified date).

On selection of this block from the Customer Master main screen, the following screen is displayed.

Res Address	Off Address	Currency	Agent	Broker	Surveyor	Advocate	Credit Dtl	Stop List																																				
<table border="1"> <thead> <tr> <th>Process Id*</th> <th>Process Description</th> <th>Block</th> <th>Block Date</th> <th>Release</th> <th>Release Date</th> </tr> </thead> <tbody> <tr> <td>01</td> <td>Stop List Claims payment</td> <td>☒</td> <td>17/10/2013 11:52</td> <td>☒</td> <td>17/10/2013 11:52</td> </tr> <tr> <td></td> <td></td> <td>☐</td> <td></td> <td>☐</td> <td></td> </tr> <tr> <td></td> <td></td> <td>☐</td> <td></td> <td>☐</td> <td></td> </tr> <tr> <td></td> <td></td> <td>☐</td> <td></td> <td>☐</td> <td></td> </tr> <tr> <td></td> <td></td> <td>☐</td> <td></td> <td>☐</td> <td></td> </tr> </tbody> </table>									Process Id*	Process Description	Block	Block Date	Release	Release Date	01	Stop List Claims payment	☒	17/10/2013 11:52	☒	17/10/2013 11:52			☐		☐				☐		☐				☐		☐				☐		☐	
Process Id*	Process Description	Block	Block Date	Release	Release Date																																							
01	Stop List Claims payment	☒	17/10/2013 11:52	☒	17/10/2013 11:52																																							
		☐		☐																																								
		☐		☐																																								
		☐		☐																																								
		☐		☐																																								

Fig. 73 – Stop List

The steps for restricting and later releasing the customer's transactions are:

Step 1: Select the Process ID. Process Ids are unique values that define the type of transaction to be restricted. Currently the application displays the following Ids:

- ☐ Stop List Claims Payment
- ☐ Stop List Claims Recovery
- ☐ Stop List Extension of Period Endorsement
- ☐ Stop List Renewal

On selection of the process id, its description is displayed in the Process Description field.

Step 2: Select the Block checkbox. The date of blocking is displayed in the Block Date field.

Step 3: To release the blocking, select the Release checkbox. The date of release is displayed in the Release Date field. On releasing the customer is allowed to carry out the restricted transactions.

TAB Tax



If the value for Customer Tax Y/N option is selected as 'Y', then this tab is enabled to capture the VAT and other Tax details.

System also validates that at least one of Tax fields is entered with the registration number. Generally, either VAT and WHT or VAT and BIT could be applicable for the customers/surveyors/loss assessors/Insurance Brokers/Reinsurance participants.

Click this tab to capture the Tax details of the customer. The system displays the screen as shown below:




Fig. 74 – Tax

☒ VAT YN (Value Added Tax)

Select the check box if VAT is applicable for the customer category, for example, Agent, Broker, Policy Surveyors, Claim Surveyors and so on.

VAT Reg No

Enter the corresponding VAT registration number.

☒ WHT YN (With Holding Tax)

Select the check box if WHT is applicable for the customer category, for example, Agent, Broker, Policy Surveyors, Claim Surveyors and so on.

WHT Reg No

Enter the corresponding withholding tax registration number.

☒ BIT YN (Business Income Tax)



Either VAT and WHT or VAT and BIT are only applicable for the customers/surveyors/ loss assessors/ Insurance Brokers/ Reinsurance participants, and so on.

Select the check box if BIT is applicable with VAT for the customer category, for example, Agent, Broker, Policy Surveyors, Claim Surveyors and so on.

BIT Reg No

Enter the corresponding Business Income Tax registration number.

INSURED CODE CREATION

Insured is the party to an insurance agreement whom the insurance company agrees to indemnify for losses, provide benefits for, or render services to. An insured is an individual or a company nominated by the customer to benefit from the policy. No Accounting entries are passed based on the insured.

In some cases, the insured may be the same as the customer. In this case, any claim settlement will be done in favour of the customer itself. Alternatively, there can be many insured's for a customer. In this case the option of setting the default insured for a customer. Details pertaining to the Insured such as mailing addresses, credit card details, etc are to be defined using this master.

Click on the Insured from the Customer Setup menu list, to open the Insured screen. The option of creating a new insured can also be accessed through the new quotation/proposal screen in the Underwriting menu. The procedure of accessing the creation of a new insured screen has been detailed out in the generation of a quotation/proposal process under all the products in the respective manual.



Most of the tab entries in this master and the masters explained hereafter is the same as those explained for the 'Customer' master.

Refer to the Customer Master Sub-menu section for information on the Header and common tabs field entry.




Fig. 75 – Insured Master Details



Additional tabs available in this section are the Credit card Details and the Additional Details Tabs. Field level explanations for these tabs are provided below.

Insured Code

Enter in this field a unique code for the Insured. This code uniquely identifies every Insured in PREMIA.

☒ Default Y/N

Check this field, if this insured is to be the default insured for the customer entered in the previous field, for all transactions. If this is checked here, during underwriting transactions, this insured is defaulted automatically on selection of the customer code.

☒ Commercial Y/N

Check this field, if the insured is a commercial customer.



On checking this field, the Commercial Details tab is enabled in the Details block to enter all commercial details pertaining to the insured.

Customer Code

Specify in this field, the customer code to which this insured is to be linked. Enter or select the customer code from the list of values. The LOV displays all the customer codes set in the Customer Master. Once the user enters the code, the description pertaining to it is automatically displayed in the adjacent field.

Category Code

Use this field to select and set the category to which the customer belongs. Enter or select the category code from the list of values. The customer could be a public/private company, a Government organization, co-operative society.

Insured Name

Enter in this field, the actual name of the insured.

Short Name

This field will automatically default the name from the 'Insured Name' field. The user may alter it if necessary.

Remarks

Enter any additional information about the Insured in this field, if any.

Mailing Address

Use this field to specify the mailing address. All correspondence with the insured will be made depending upon the selection made in this field. This address will appear in the 'Address' block of the underwriting screen on selection of the insured code. Select the mailing address from the drop-down list. The options available are:

☐ Residential Address

☐ Office Address

Date of Birth

Enter in this field, the date of birth of the insured.

Assured Business Sector

Select from the LOV, to identify the business type of the new insured like Individual, Corporate or Government and so on.


Effective From and To Date

Enter or select the 'From' and 'To' dates from the Application Calendar, which can be accessed using the list of valid values key. These dates specify the validity period of the insured in the system.

TAB Residential Address

Enter in this tab, all the details pertaining to the residential address of the customer.

The screen is as displayed below:



	Res. Add	Office Add	Emp Dtl	Cr.Card Dtls	Comm. Dtls
Address	Flat 1 2nd Floor				
Area/Block No.	1				
City*	068 Abdullah-as-Salam				
State*	001 al-'Asamah				
Country*	4001 AFRICA				
Phone	789789				
Fax	907987987				
Contact 1	Contact				

Fig. 76 – Residential Address

Address / Area /Block No

Enter the residential address of the customer in this field. Four rows are provided for the same.

City/State/Country

Enter or select the City/State/Country code pertaining to the address entered in the previous field, from the list of values. Once the code is entered, the description pertaining to the code is automatically displayed in the adjacent field.

	☐ The LOV for city displays only those cities belonging to the chosen state ☐ The LOV for PIN Code displays only those codes falling under the selected city
---	---

Phone/Fax

Enter in this field, the phone number and the fax number of the customer.

Contact 1

Enter details of the contact person of the customer for communication purposes. Two fields have been provided for the same.

TAB Office Address

Enter in this tab, all the details pertaining to the official address of the customer. This screen is as displayed below:

Fig. 77 – Office Address

Office/Flat No / Building No /Road No

Enter the official address details of the customer in the respective fields provided.

City/State/Country

Enter or select the City/State/Country pertaining to the address entered in the previous field, from the list of values. Once the code is entered, the description pertaining to the code is automatically displayed in the adjacent field.

	☐ The LOV for city displays only those cities belonging to the chosen state
	☐ The LOV for PIN Code displays only those codes falling under the selected city

Phone No/Fax

Enter in this field, the phone number and the fax number of the customer.

Contact No

Enter details of the contact person of the customer for communication purposes. Two fields have been provided for the same.

Mobile Number

Enter the mobile number of the customer

Email 1/2

Enter the E-mail Id of the customer. Two fields are provided for the same.



Check Dup

Click this button to check for duplicate insured names, if any as shown below:

Fig. 78 – Duplicate Insured Names

TAB Emp Details

If the assured is an employee, then click this tab to capture the employee details.

Fig. 79 – Employee Details

Enter the field details such as:



Assured Code

Enter the assured code.



Employee Name

Enter the employee name.



Address /1/2

Enter the address details in the respective fields.

- ☐ Zip Code
- ☐ City Name
- ☐ Country Name and
- ☐ State



Occupation

Enter the occupation of the employee.



Yrs in Current Occupation

Enter the total number of years in current profile.



Yrs with Current Employer

Enter the total number of years with the current employer.



Yrs with Previous Employer

Enter the total number of years with the previous employer.

TAB Cr. (Credit) Card Details

Click this tab to enter credit card details of the insured, if any.

Res. Add	Office Add	Emp Dtl	Cr.Card Dtls.	Comm. Dtls
Credit Card Details				
Card No.	Bank	Expiry Date		
44343432	Bank of Alzeera	01/02/2020		

Fig. 80 – Credit Card Details



Card Number

Enter the credit card number if the insured in this field.



Bank

Enter the name of the bank that has issued the credit card to the insured, in this field.



Expiry Date

Enter or select the 'Expiry Date' from the Application Calendar that can be accessed using the list of values. This date specifies the validity period of the credit card.

TAB Commercial Details



This block is enabled when the 'Commercial' check box is selected in the header block.

If the assured is a Commercial customer, then click this tab to enter the commercial details pertaining to the insured.

Res. Add	Office Add	Emp Dtl	Cr.Card Dtls.	Comm. Dtls
Commercial Details				
Date of Registration	01/07/1980	Type of Business	Industrialist	
Financial Start Period		Financial End Period		
No. of Employees	50	No. of Branches	2	
CMM Level*		Crysil Rating*		
Contact Person 1-Designation		Phone No.		
Mobile No.	6666	Contact Person 2-Designation		
Phone No.	6666	Mobile No.		
Commercial Type*		Paid Share Capital		

Fig. 81 – Commercial Details

Enter the commission details like:

- ☐ Date of Registration
- ☐ Type of Business and CMM Level detail
- ☐ Financial Start /End period
- ☐ Address Details

- ☐ Crsyal Rating
- ☐ Commercial Type
- ☐ Paid Share Capital

RATING

Introduction

PREMIA combines a powerful rating engine that can be used to configure the premium rating for different products. In the current business environment, where there have been frequent changes to the rating by insurance regulators, the flexible rating engine allows easy handling of this fluid situation. The premium computation logic has been derived for most of the products and is modifiable for a specific installation, without having to change the core of the application.

The Rating Master is used to set the logic based on which premium calculation happens for covers, discounts and loading for all the products defined. This menu comprises of the following sub-menus:




Fig. 82 – Rating Setup

The functionalities of various sub-menus are described in detail.

Features of Rating Setup Masters

- ☐ Provides the methods to derive a rating for a product
- ☐ Describes the components to derive the rating
- ☐ Provides the order by discounts/loadings applied for a every product
- ☐ Defines the rating calculation for short period policies

Rating Setup consists of the following five Setups

- ☐ **Section Parameter** – In this master we create the parameters based on which the rates vary. For example, in a health policy, the rate varies based on the age of a person. As the age increases the rate (i.e. premium) also increases. So, age has to be created as a rating parameter
- ☐ **Cover Parameter** – The system provides 57 calculation logics which are used based on the requirement of the client. Each logic works in a certain way. For example, if we use the logic 007-Data Element * Rate, it means that sum insured is going to be entered in a data element (risk block). This sum insured will be multiplied with the tariff rate
 - o System also facilitates the user to define own premium calculation logic under Prem Calc Login Code '058'.
- ☐ **Short Period Rate Setup** – Set applicable rates for various durations, if short period is applicable for the product

- ☐ Charges Setup – Set all applicable charges for the product
- ☐ Premium Computation Sheet Setup – Set the order of calculation sequence and display for all the premium elements at the cover/policy/charges level, for the product

SECTION PARAMETER

Use this master to setup the rating elements for the product. Set the parameters required for arriving at the rate for calculating the premium. All applicable parameters are defined here.

Parameters set as 'Data Element and Rating' type in the 'Product Setup' Master is defaulted in this screen. For parameters set as 'Data Element' and 'Rating' type and 'Range' in the 'Field Definition Block' of the 'Product Setup' master, two records for the parameter is defaulted in this screen. Select the required product code and click in the multi-record block for the defaulting to happen.

If the parameter is not set as 'Rating Range' in the Product Setup, the same is defined here and associated with the right value.



- ☐ New parameters can be created for any field which has tariff type as 'Data Element' in the Product Setup field definition.
- ☐ Once a parameter is mapped to a cover in the 'Rating Cover Parameter Setup' master, the same parameter cannot be deleted from this master. Delete the record in the 'Rating Cover Parameter Setup' master, before deleting the same in the 'Section Parameter' master.

Click Section Parameter menu to view the following screen:




Fig. 83 – Section Parameter

Product Code

Select the product code for which the rating parameter is to be defined, from the LOV. If the selected product has any parameters set as 'rating type' and also set as 'range' in the 'Product Setup' master, they are defaulted in the multi-record block below this field.

Parameter Name

Enter the required parameters to be set for arriving at the rate for this product.

Section Code

Select the section code to which this parameter belongs from the LOV. The description of the section is defaulted in the corresponding field below the multi-record block.

Tariff Type

This field displays the Tariff type of the parameter.

Rating Type

This is a display only field. The fields defined as 'Data Element & Rate' in the field definition block of the Product Setup Master are defaulted to the same type in this field. All other fields are defaulted to type 'Rate'.

Indicator

Select the rating indicator for the parameter from the drop-down list provided. The options available are:

- ☐ Constant Value
- ☐ None
- ☐ Non-Slab
- ☐ Slab From
- ☐ Slab To



If there is no Slab From and Slab To then the indicator is selected to be none or non-slab for a rating element.

Associated Type

Select the associated type to which the parameter is to be linked, from the drop-down list provided. The options available are:

- ☐ Cover Field Names
- ☐ Link Cover Field Names
- ☐ Claims Ratio
- ☐ Cover Group– rate would depend on the on the sum insured of all the covers in the Cover group
- ☐ Data Element– rate would depend on the risk element
- ☐ Long Term Years
- ☐ No Claim Bonus
- ☐ Number of risks
- ☐ Number of sections
- ☐ SMI Group – rate would depend on the sum insured of all the SMIs in the SMI group
- ☐ SMI – rate would depend on the sum insured of the SMI



Since no specific values are indicated for the above types, these types have to be linked to the actual associated value from where the data is to be taken.

For example: Associated Type – SMI; Associated Value – SMI Code.

- ☐ Long term years
- ☐ Claim Count
- ☐ Renewal Count
- ☐ Policy Type
- ☐ Cover Field Names

☐ Link Cover Field Names

☐ SMI Flexis



For the above associated types there are no associated values. The values for these types are picked up from pre-defined values set in the system.

The associated type is a pointer or a value itself for arriving at the rate to be calculated. If used as a pointer, an associated value is to be set for the type.

Associated Value

Select the associated value for the associated type, if the type is of 'Data element', 'SMI', 'SMI Group' and 'Cover Group', from the LOV. The LOV displays only those values that pertain to the set associated type (from the four types) selected from the field definition block of the Product Setup Master.

Block Name

This is a display only field. If the rating type is 'Data element and Rating', the block name to which the parameter belongs, set in the 'Product Setup' master, and is defaulted in this field.

Section Description

This is a display only field. The corresponding description of the Section Code is defaulted in the field.

Associated Block Name

This is a display only field. The corresponding description of the value set in the 'Associated Value' field is defaulted in this field.

COVER PARAMETER

Use this master to set the rating parameters required to arrive at the premium calculation logic and the rate for the covers. The parameters set here are those created for the product in the 'Rating Section Parameter' master.

Click 'Cover Parameter' to view the following screen:

Key	Variable Code*	Variable Code Desc	Variable Value
3	005	Coverage Group Premium	1001 OD - TP premium Cover Group
1	008	Cover SI	
2	010	Cover Rate	

Fig. 84 – Rating Cover Parameter Setup



Product Code

Select the required Product Code for which the cover rating parameters are to be set. The description of the product is defaulted in the adjacent field. The various covers set for the particular product in the Product Setup master is defaulted in the LOV of the Cover code field.

Code

All covers attached to the selected product are displayed in this field, once the product code is selected. Select the required cover code for which the rating parameters and the premium calculation logic are to be set, either by clicking the down arrow in the keypad or from the LOV. The description of the cover is defaulted in the adjacent field.

	The fields such as 'Type'(Cover/Discount/Loading), 'Level', 'Section Code', 'SMI Code' 'Basic cover Y/N', 'Summary cover Y/N', 'Level number' and the 'Serial number' fields are all display only fields. The values in these fields are defaulted once the 'Code' is selected. The values have been defined in the 'Product Setup' master for the combination of the Code and product code.
---	--

Premium Calculation Logic

Select the required Premium calculation logic to be set for the cover, from the LOV. Various calculation logics have been pre-defined in the system. The logic set here is used during the actual transaction.

	☐ PREMIA provides the user with 59 predefined premium calculation logics. ☐ User can define their own calculation logic under the Prem Calc Logic code - 058 is User Defined Logic.
---	---

Once the logic is selected, the variables pre-defined for this logic is defaulted in the 'Premium Logic' block. For example if the logic used is 007-Data Element * Rate then in the premium logic block in the 'Variable Code' field, defaults 'Data Element' for which the user needs to specify the variable value. In this case, user is allowed to select the desired data element from the LOV for the variable value.

Rate Per

This field defaults the value 100. User is allowed to modify it. Enter the applicable rate per for the rate. This field is the denominator for the rate field. The rate per is also set through the 'Product Setup' master.

Rating Level

Use this field to specify the level at which the defined rate is to be applied. Select the rating level from the drop-down list. The options available are:

- ☐ Cover – the defined rate is applied at the cover level
- ☐ SMI – the defined rate is applied at the SMI level. This is mainly used in the case of marine policies.

☒ Rate Editable Y/N

Select the check box, if the user is to be allowed to modify the pre-defined rate during transaction.

Short Rate Id

If a short period is applicable for the product, enter the short rate ID (set in the 'Short Period rate' master) to be used for this cover. During transaction, the cover premium is calculated based on the rate set in the short rate ID set in this master.

Rate rounding decimals

Enter the decimal rounding off value, if the rate is in decimals.

TAB Tariff/Rating Parameter

Use this block to enter details pertaining to the rating parameter. The system displays the screen as shown below:

Sort Order	Parameter	Mapping Column
1	Occupational Parameter	PTD_VALUE_SET1

Fig. 85 – Tariff/Rating Parameter



Sort order

This is used to set the calculation sequence. Set the sort order of the parameters by which the premium is to be calculated for rating computation. Computation happens only in the order specified in this field.

Parameter

Select the required rating parameter for the cover, from the LOV. The LOV displays all the parameters defined in the 'Section Parameter' for the product.



Mapping column

Use this field to specify the column name where the data is to be stored for the parameter in the system. Enter or select the mapping column name from the LOV. There are 20 columns -10 columns to store numeric parameters and 10 for codified parameters.

TAB Premium Logic

Use this block to set the actual variable values for the variable codes that are defaulted here. The variable codes are defaulted based on the calculation logic set in the cover section. Various variable codes have been pre-defined in the system. They are:

- ☐ 001 – SMI Group
- ☐ 002 – Cover Group
- ☐ 003 – Data element
- ☐ 004 – Constant
- ☐ 005 – Rate logic
- ☐ 006 – Premium logic

Depending on the calculation required to arrive at the premium for the product, these variable code/s are to be used.

Click 'Premium Logic' to view the following screen:

Variable Code	Variable Code Desc	Variable Value
001	Sum Insured Group(SMI Group)	

Fig. 86 – Premium Logic

Variable Code

The Variable Code and its description, used to arrive at the calculation logic for the cover, are defaulted in this block.

Variable value

Select the variable value from the LOV. The values available in the LOV are filtered based on the variable code selected. These values are fetched from the respective masters for the defined product and section.

TAB Formula

Click this tab to define the Formula to calculate the premium logic. The system displays the screen as shown below:

Rating Cover Parameter Setup

Product Code* 1001 Motor Commercial
 Code 3101 Own Damage
 Level F Applicable covers at Field Level
 Section Code* 100101 Motor Commercial
 SMI Code
 Cover Code
 Basic Cover YN ☐ Built in Cover YN ☐ Summary Cover YN ☐ Level Number 1
 Prem Calc Logic* 058 User defined Logic
 Parent Code*
 Rate Key
 Rate Per 100
 Short Rate ID* M1

Type Cover
 Serial Number 1
 Rate Editable YN ☒

Rating Level Cover
 User Ent. Formula Greatest((#1*#2#),#3#)-(#3#)
 Rate Rounding Decimals

Key	Variable Code*	Variable Code Desc	Variable Value
3	005	Coverage Group Premium	1001 OD - TP premium Cover Group
1	008	Cover SI	
2	010	Cover Rate	

Key

Enter the place order to be used in the formula.

Variable Code

Select the Variable Code from the LOV. The description is displayed in the adjacent field. This code is used to arrive at the calculation logic for the cover.

Variable value

Select the variable value from the LOV. The values available in the LOV are filtered based on the Variable Code selected. These values are fetched from the respective masters for the defined product and section.

Tariff Data



This button is enabled based on the Tariff Parameter.

Use this screen to set the rates for the parameters set in the 'Rating Parameter' block of this master. Depending on the parameter selected, the value entered here could be for a single value or for a range. The parameters are available as the headings in this multi-record block. Based on the number of parameters defined, use the horizontal scroll bar to enter the values.

Click 'Tariff Data' button to view the screen as shown below:




Fig. 87 – Tariff Data



The data entered here is based on the parameters set in the 'Rating Parameter' block

Effective 'From' and 'To' Date

Enter or select the 'From' and 'To' dates from the Calendar help. These dates specify the validity period for the rate defined for the product.

Rate

Enter the rate for the combination of parameter values.



If 'Rating level' has been set as 'SMI' in the header section of this master, the 'SMI Code' is visible as a separate column in this block. The rate is then defined for the SMI code.

If 'Rating level' is 'Cover', then the rate defined here is applicable for the selected cover.

Rate Effect

In some cases, covers act as a 'Discount' or 'Loading'. If it is a discount, the amount is to be reduced from the gross premium. If loading, the amount is to be added to the gross premium. Select the required option from the drop-down list provided. The options are:

- ☐ Less from gross premium
- ☐ Add to gross premium

Minimum/Maximum Premium and SI

Set the minimum / maximum SI and premium on which the rate is to be applied, in the base currency. During transactions, the application accepts premium and SI based on the values defined in these fields (For example, within the set range from both the 'Minimum' and 'Maximum' values if both the fields are defined or else based on any one field parameter). Else, an error message is raised.

SI currency code / Default SI FC

Set the currency code for the sum insured as also the default sum insured in local/foreign

currency. The values set here are defaulted during transaction, if in the 'Product Setup', for the selected cover, 'SI to be derived from Tariff' has been set.

CHARGES SETUP

Use this master to set all the applicable charges for the product. Charges are to be based on a fixed rate for a product or depend on the cover premium. This calculation logic and the rate are defined in this master.

Click 'Charges Setup' menu to view the screen shown below:

Fig. 88 – Taxes and Charges Setup Master



Product Code

Select the product code from the LOV for which the applicable taxes and charges is to be set. The description of the code is defaulted in the adjacent field.

Section

Select the section code from the LOV to set the applicable taxes and charges (if available for the specified product). The description of the section is defaulted in the 'Section Description' field.



If user selects the Section code, then the taxes/charges is applied at the Section level also otherwise, the taxes/charges are applicable for the product level only.



Type

Select the required charge type from the LOV. Charge types have been pre-defined in the system. The description of the charge type is defaulted in the 'Type Description' field.



Tax/Charge Code

Select the required Tax/Charge code from the LOV. This field is linked with the 'Type' field. The LOV displays only those Codes that are set under the selected type in the 'Type' code field. This is set in the 'Taxes and Charges' master.

The description pertaining to the code is defaulted in the 'Tax/Charge Desc' field. If required, user may modify the description.

Customer Share %

If the Customer is to bear the charges, then enter the percentage of share that the customer has to pay.



Calculation Logic

Select the calculation logic for the charge, from the LOV. Three calculation logics have been provided in the LOV. They are:

- ☐ 001 – Rate on Coverage group – Select this option, if charges are to be calculated based on the cover premium
- ☐ 002 – Rate on Constant – Select this option, if charges are fixed for the product
- ☐ 003 – Rate on SI – Select this option, if the charges are to be calculated on the basis of the sum insured (Gross SI or Net SI basis)

The corresponding description of the calculation logic option selected is defaulted in the 'Calc Logic Desc' field.



Cover Group

If the Calculation Logic is set to '001' or '003', then select the applicable Cover Group from the LOV.



Sort Order

Enter a defined order in which the calculation sequence is to be set. Based on this order, the Taxes and charges are calculated.



Rate Per

Enter the applicable rate per for the annual rate. This value is the denominator for the rate.

Annual Rate

Enter the annual rate for the charge.

Short Rate

Enter the Short-Rate in this field. This rate is applicable only for short-term policies.



Rounding Method

Select the rounding off method (number of decimal places) to which the taxes and charges amount is to be rounded off, from the LOV. The description of the method is defaulted in the 'Rounding Desc' field.

☒ Risk Y/N

Select the check box, if this charge is to be applied at the risk level.

☒ Mandatory Y/N

Select the check box, if this charge is to be made mandatory for the product. Once the charge is made as mandatory, then it cannot be deleted during transaction.

☒ Modify Y/N

Select the check box, if the rate is to be modified during transaction.

☒ Refund Y/N

Select the check box, if Refund to the customer is applicable on the tax/charge during endorsements.

Default

Specify the block to default the charges from the LOV. The available values are:

- ☐ Charges block
- ☐ Coinsurance block
- ☐ Both

Minimum – Maximum Tax Charge in LC_1

Define the minimum and maximum tax charges for a particular tax/charge code selected in the fields.



Effective 'From' and 'To' Date

Enter or select the validity period of the tax/charges in 'From' and 'To' dates using the Calendar help.

PREMIUM COMPUTATION SHEET SETUP

This setup is used to specify how the cover premiums, discounts & loadings, taxes and charges, etc., is displayed on the premium computation sheet. Set the display order and sort order for the various covers and charges. The premium for a product, after calculation, is displayed based on the setup done through the 'Premium Computation Sheet' setup.

Premium Computation Sheet Setup

Product Code* 5017 Hotel Comprehensive

Cover Policy Taxes and Charge

Cover Level

Cover Code	Section Code	Section Description	Cover type	Cover level	Display Order	Sort Order	Display
3201	200201	Fire Material Damage	Cover	F	1	1	☒
3209	200201	Fire Material Damage	Cover	F	8	8	☒
4001	200201	Fire Material Damage	Discounts	F	102	102	☒
4002	200201	Fire Material Damage	Discounts	F	103	103	☒
4012	200201	Fire Material Damage	Discounts	F			☐

Rate Key

Cover Description Fire & Lightning

Cover Level Description Applicable covers at Field Level

Fig. 89 – Premium Computation Sheet Setup

The display is set at three levels:

- ☐ Cover level
- ☐ Policy level
- ☐ Taxes and Charges level



Product code

Select the product code for which the applicable taxes and charges is to be set, from the LOV. The description of the code is automatically displayed in the adjacent field.

TAB Cover level

Once the Product code is selected, all the covers/discounts/loading, the section to which they belong, the cover type and cover level are defaulted on clicking inside this multi-record block. Set the display and sort order of these covers. Click Premium Computation Sheet Setup to view the following screen:

Cover Code	Section Code	Section Description	Cover type	Cover level	Display Order	Sort Order	Display
3201	200201	Fire Material Damage	Cover	F	1	1	☒
3209	200201	Fire Material Damage	Cover	F	8	8	☒
3225	200201	Fire Material Damage	Cover	F	17	17	☒
3239	200201	Fire Material Damage	Cover	F	40	40	☒
3240	200201	Fire Material Damage	Cover	F	41	41	☒

Rate Key:

Cover Description:

Cover Level Description:

Fig. 90 – Premium Computation Sheet Setup – Cover



Display order

Set the order in which the cover is to be displayed in the Premium Computation Sheet.

Sort order

This is used to set the calculation sequence. The premiums are calculated in the order specified in this field.

☒ Display

Select the check box, if the cover is to be displayed in the Premium Computation Sheet.

TAB Policy level

Once the cover level premium computation setup is completed, click the Policy Level tab to map the Product Code at Policy level.

Premium Breakup Code	Breakup Description	Cover Group*	Display Order	Sort Order
STP001	SUB TOTAL	CGP001	2	2
BRK001	BROKER SUMMARY	BRK001	4	4
SUR001	SURVEYOR FEE	SUR001	5	5
STP001	SUB TOTAL	CGP001	2	2
BRK001	BROKER SUMMARY	BRK001	4	4

Cover Group Description:

Fig. 91 – Premium Computation Sheet Setup – Product



Premium Break up Code

Select the Premium Break up Code from the LOV. The description is defaulted in the adjacent field.



Cover Group

Select the cover group code from the LOV. The description is defaulted in the respective description field.

Display order

Set the order in which the policies are to be displayed in the Premium Computation Sheet.

Sort order

This is used to set the calculation sequence. The premiums are calculated in the order specified in this field.

TAB Taxes and Charges level

Set the display order and sort order for the applicable charges for the product. The system displays the screen as shown below:

Tax^@ Charge Code	Tax^@ Charge Description	Tax Charge Type	Display Order	Sort Order	Display
1001	Policy Fees	Charges	10		☐
2001	Service Levy	Levies	20		☐
					☐
					☐

Fig. 92 – Premium Computation Sheet Setup – Taxes and Charges

Tax Charge Code

Enter the tax charge code. The tax charge description is displayed in the adjacent field.

Display order

Set the order in which the charges are to be displayed in the Premium Computation Sheet.

Sort order

This is used to set the calculation sequence. The charge amount is calculated in the order specified in this field.

SHORT PERIOD RATE SETUP MASTER

Use this master to set the percentage of the annual rate to be applied for a short period policy. Click Short Period Rate Setup Master to view the screen as shown below:

Short Rate Id	Duration Ind	Duration	Duration Type	Rate	Rate Per
M1	Exceeding	0	Days	12.5	100
M1	Exceeding	8	Days	25	100
M1	Exceeding	31	Days	37.5	100
M1	Exceeding	61	Days	50	100
M1	Exceeding	91	Days	62.5	100
M1	Exceeding	121	Days	75	100
M1	Exceeding	181	Days	87.5	100
M1	Exceeding	241	Days	100	100

Fig. 93 – Short Period Rate Setup Master

Product code

Select the product code for which the short period rate is to be set, from the LOV. The description of the code is automatically displayed in the adjacent field.



Short Rate Id

Select the applicable short rate for the product form the LOV provided. These ID's are pre-defined in the system.



Duration Indicator

Select the duration indicator from the list box provided. The short rate will be applied, based on the indicator set here and the actual duration set in the next field. The indicator options are:

- ☐ Exceeding
- ☐ Not exceeding



Duration

Enter the actual duration for which this rate is valid.



Duration Type

For the duration entered in the previous field, select the duration type from the drop-down list provided. The options are:

- ☐ Days
- ☐ Weeks
- ☐ Months



The short period rate work based on the duration, indicator and type set in this master.



Rate

Enter the short period rate in this field.



Rate per

Enter the applicable rate per for the short period rate. This value is the denominator for the rate.

VAT/TAX MASTER

Use this master to set the VAT/Tax parameters required to arrive at the rate for the respective tax. The parameters set here are those that have been created for the product in the 'Rating Section Parameter' master.

Click 'VAT/Tax Master' to view the screen as shown below:

Tax Master

Tax Code*: VAT01 Tax Category: Value Added Tax

Tax Description: Value Added Tax Inward

Tax Desc(Bilingual): F_Value Added Tax Inward

Tax Short Desc: Value Added Tax Inward

Tax Short Desc(Bilingual): F_Value Added Tax Inward

Refundable Y/N: ☒ Effective Fm Date: 01/01/1990 Effective To Date: 31/12/2020

Applicable at :

On Policy Commission ☒ On Surveyor Fees ☒ Insurance Premium ☐

On Fac/Treaty Commission ☒ On Inward/Outward Commission ☒ Reinsurance Premium ☐

Tax Rates

Product From*	Product to*	Cust. Type From*	Cust. Type To*	Effective Fm Date	Effective To Date	Tax(%)
7001	7001	AG	TP	01/01/1990	01/01/1999	12
1001	9001	AG	TP	01/01/2000	31/12/2020	10

Product Fm Description: Performance Bond Product To Description: Performance Bond

Cust Cat Fm Desc: Agents Cust Cat To Desc: Third Party

Fig. 94 – VAT/Tax Master



Tax code

Select the applicable tax code from the LOV. The available values are:

- ☐ BIT01 – Business Income Tax
- ☐ VAT01 – Value Added Tax
- ☐ WHT01 – Withholding Tax
- ☐ VAT02 – Value Added Tax Outward

Tax Category

Select the applicable tax category from the drop-down list. The available options are:

- ☐ Value Added Tax
- ☐ Withholding Tax
- ☐ Business Income Tax



Either WHT or BIT along with VAT can be given to the Customer Category.

Tax Description

On selecting the tax code, by default the tax description is displayed.

Enter tax desc (bilingual) and short description in the respective fields.

☒ Refundable YN

Select the check box to specify that the tax amount will be refunded while passing any refund endorsement like cancellation or decrease in SI.

**Effective From/To Date**

Enter the validity period for this tax in 'From' and 'To' date fields. If the date is not within the given range the Tax defined cannot be used.

Applicable At

Select the check box to specify at which level this tax is applicable. This will be the tax collected for the payment made to Broker/Agent/Surveyor/other Insurance Co. The available options are:

- ☐ On Policy Commission – Select this option to apply tax on policy commission
- ☐ On Surveyor Fees – Select this option to apply tax on the surveyor fees
- ☐ On Fac/Treaty Commission – Select this option to apply tax on Insurance company for FAC/treaty participant commission
- ☐ On Inward/Outward Commission – Select this option to apply tax on the Insurance company for Inward /Outward Policy
- ☐ Insurance Premium– Select this option to apply tax on the insurance premium to be paid by the customer
- ☐ Reinsurance Premium – Select this option to apply tax payable on the reinsurance premium

Tax Rates**Product From/To**

Select the range of products applicable for this tax. On selecting the product codes, the description gets defaulted in the respective Product Description fields.

Customer Type From/To

Select the range of customers applicable for this tax.

Effective From/to

Select the date range from when the defined tax will be applicable for that product.

Tax%

Enter the percentage of tax value that needs to be calculated.

Based on the setup defined, the applicable rate is picked up for the policies based on the policy issue date or the inception date. On policy approval, the accounting entries are generated (as it currently happens for the VAT on agent/broker commission).

DOCUMENT SETUP

Introduction

In PREMIA the Document setup defines the behavior specific to a Document type over and above the common functionality specified in the Product setup.

In the General Insurance business there are various document types that are necessitated, based on the requirement.

Click 'Document Setup' menu comprises of the following sub-menus:




Fig. 95 – Document Setup Menu

These documents are explained in brief below:

- ☐ Quotation Setup – used to quote premium value for the risk covered
- ☐ Policy Setup – contains all the decided/defined Risk Details, Covers, Conditions, Clauses, and other details
- ☐ Endorsement Setup – used to define the flow regarding any changes required after the issue of the policy. The changes could be of any type
- ☐ Claims Setup – used to register process and settle any claims

The flow and functionality of these documents is decided through the details set in this setup. Whenever a set up for the new product is done, all documents such as Policy, Endorsement, also needs to be setup for that product.

In Document Setup, the 'Policy Setup' has to be completed before setting the flow for the other document types.

QUOTATION

Click this menu to enter the details pertaining to the flow and setup of the quotation document for a product or set of products. The Document Setups are to be done once the policy document setup is completed.

The Quotation screen is displayed as shown below:

Fig. 96 – Quotation Setup

	☐ The flow of the Quotation Document Setup is the same as explained in the Policy Document Setup section of this manual. ☐ All the blocks – 'Header', 'Product', 'Condition', 'To Do List', 'Applicable Divisions', 'Charges', 'Section' and 'Print' are the same and are not explained separately in this section. ☐ Refer 'Policy' Document Setup (below section) of this manual.
--	--

Document Code

Enter the document code for the quotation / proposal document setup. This is the code that defines the flow of the quotation / proposal for the product/s attached to this code. Enter the code in this field along with its name or description in the adjacent field. This name will be used during reporting. Existing codes can be viewed in the query mode.

Short description

This field defaults the name or description from the 'Document Code' field. User may modify, if required.

	Based on the requirements, the description or the short description can be mapped and used while printing the document.
--	---

Policy Document

Use this field to link the required policy document with the quotation / proposal document setup. Enter or select the policy document setup code from the LOV. The LOV displays codes from the 'Policy Document Setup Master'. Once the code is entered, the description pertaining to the code is automatically displayed in the adjacent field.



The policy document setup is to be completed before setting up any other document setup.

Mode of Posting

Set the account processing mode for all the products attached to the quotation / proposal document setup. The mode selected here will be applied during transaction, on approval of the quotation / proposal.

Select the mode of posting from the LOV. The available options are:

- ☐ Batch
- ☐ Online



Policy Period unit

Set the required policy period unit from the list box. The option set here is applicable for all products attached to this quotation / proposal setup. The options available are:

- ☐ Hour
- ☐ Day
- ☐ Week
- ☐ Month
- ☐ Year

Policy Period From & To

For the period unit set in the previous field, enter the minimum and maximum range in the 'From' and 'To' fields.

Currency Rate type

By default the rate type is set as 'Buying Rate' on entering this screen. In case of transaction in foreign currency, set the rate type to be used. All currency transactions will depend on the rate type selected here. The actual rate for the selected type is defined in the Currency Master. The options available are:

- ☐ Buying Rate
- ☐ Selling Rate
- ☐ Quarterly Closing Rate
- ☐ Average of Buy/Sell Rates
- ☐ Book Keeping Rate
- ☐ Yearly Closing Rate
- ☐ Quarterly Average Rate

☒ Inward Commission required

Check this box if inward commission is applicable for any of the products set in this document setup.

Commission code

This field is enterable only if 'Inward Commission required' is checked. Select the commission setup code under which this commission amount is to be accounted for, during transaction. Once the 'Code' is entered, the description of the code is automatically displayed in the adjacent field.

Percentage tolerance

Percentage tolerance is applicable only for premium FC conversion alone. Enter the tolerance limit for percentages in this field.

Currency tolerance

While doing the currency conversion for any premium amount (FC to FC or FC to LC), if there is any difference between the calculated value and existing value (i.e., the difference within the currency tolerance) system will not update the existing value with the calculated value, if not then calculated value will update to the existing value. Enter the tolerance limit for currencies in this field.

☒ **Agent Commission required**

Check this box if agency commission is applicable for any of the products set in this document setup.

Code

This field is enterable only if 'Agent Commission required' is checked. Select the agency commission setup code under which this commission amount is to be accounted for, during transaction. Once the 'Code' is entered, the description of the code is automatically displayed in the adjacent field.

Policy Inception days

Enter the number of days from issue date, when the risk coverage is to become active. For example, if user enters 4 in this field and if the policy is generated on 02/12/2004, then risk coverage starts only from 06/12/2004.

Premium Currency Type

Select the premium currency type for all the products attached to this document setup, from the list box. The options available are:

- ☐ Premium in Premium Currency
- ☐ Premium in SI Currency

SI round to

Select from the given LOV the round off method to be set for the SI amount.

Agent A/C Document type

The option set in this field determines the processing type for posting the accounting entries for agents/brokers. Select the agent A/C document type from the list box. The options available are:

- ☐ Single Accounting
- ☐ Bulk Accounting
- ☐ No Accounting

Premium round to

Select from the given LOV the round off method to be set for the premium amount.

Customer A/C Document type

The option set in this field determines the processing type for posting the accounting entries for customers. Select the agent A/C document type from the list box. The options available are:

- ☐ Individual Accounting Document.
- ☐ Bulk Accounting Document.
- ☐ No Accounting Document

☒ **RI allocation required**

Check this box, if RI allocation is required for all the products attached to the document setup. If checked, on approval, RI related entries are passed before the premium collection is completed.

Commission round to

Select from the given LOV the round off method to be set for the commission amount.

☒ **Policy Period modifiable**

Check this box, if the policy period is modifiable at the transaction level. If checked, the 'Policy To Date' is not modifiable. If un-checked, the 'Policy To Date' is modifiable.

☒ **Policy From Date modifiable**

Check this field if the 'From' date of the policy is modifiable at the transaction level.

☒ Premium Collection Required

Check this field if collection of premium is to be completed before issue of the quotation / proposal. The policy number will be generated only after the premium is collected.

Risk SI Limit

Set the maximum limit for the sum insured for the risk. The total sum insured for the risk during transaction is checked against the limit set here. If the total sum insured is higher than the limit set here, an appropriate warning is issued in the system.

Effective From & To

Enter or select the validity period for the document setup using the 'From' and 'To' date fields. The dates can be selected from the Application Calendar accessed using the LOV. If no period is defined, then there is no end date for the validity period.

Policy Conversion Mode

By default, this field is set as '02 – Convert to Policy with Complete status'

POLICY

The Policy Setup screen is used to enter details pertaining to the flow and setup of the policy document for a product or set of products. This document setup is to be done once the product setup is completed.



Setup done for some of the features in the 'Product Setup' master may be over-ridden by setups done for the same features in the Document Setup.

The 'Policy' setup screen is displayed as shown below:

Fig. 97 – Policy Setup



Document Code

Enter the document code for the policy document setup. This is the code that defines the flow of the policy for the product/s attached to this code. Enter the code in this field along with its name or description in the adjacent field. This name is used during reporting. Existing codes are viewed in the query mode.

Short description

The Document Code description is defaulted in this field.



Based on the requirements, the description or the short description is mapped and used while printing the document

Currency Rate type

By default the rate type is set as 'Buying Rate' on entering this screen. In case of transaction in foreign currency, set the rate type to be used. All currency transactions depend on the rate type selected here. The actual rate for the selected type is defined in the Currency Master. The options available are:

☐ Buying Rate

☐ Selling Rate

Mode of Posting

Set the account-processing mode for all the products attached to the policy document setup. On approval of the policy, the mode selected here is applied during transaction.

Select the mode of posting from the drop-down list. The available options are:

☐ Batch

☐ Online

Effective 'From' and 'To'

Enter or select the validity period for the document setup using the 'From' and 'To' date fields. The dates are selected from the Calendar help.

If no period is defined, then there is no end date for the validity period.

Policy Number Generation Type

Select the appropriate option from this drop-down list to define the policy number generation type. The options available are:

☐ Custom – Select this option to enter the transaction reference number manually

☐ Setup – Select this option to define unique policy number setup through the 'Document Number' setup screen

Endorsement Number Generation Type

Select the appropriate option from this check box to define the endorsement number generation type. The options available are:

☐ Custom – Select this option to enter the endorsement number manually

☐ Setup – Select this option to define unique endorsement number setup through the 'Document Number' setup screen

Surveyor A/C Document type

The option set in this field determines the processing type for posting the accounting entries for surveyors. Select the surveyor A/C document type from the list box. The options available are:

☐ Single Accounting – Accounting entry is generated immediately

☐ Bulk Accounting – Accounting entry is generated only when the batch processing is done

☐ No Accounting – No entry is generated

Risk SI Limit

Enter the maximum limit for the sum insured for the risk. The total sum insured for the risk during transaction is checked against the limit set here. If the total sum insured is higher than the limit set here, an appropriate warning is displayed in the system.

☒ Inward Commission required

Select the check box if Inward Commission is applicable for any of the products set in this

document setup.

Commission code

This field is enterable only if 'Inward Commission required' is checked. Select the commission setup code under which this commission amount is to be accounted for, during transaction. Once the 'Code' is entered, the description of the code is defaulted in the adjacent field.



Policy Period Unit

Set the required policy period unit from the drop-down list. The option set here is applicable for all products attached to this policy setup. The options available are:

- ☐ Hour
- ☐ Day
- ☐ Week
- ☐ Month
- ☐ Year

☒ Agent Commission required

Select the check box if agency commission is applicable for any of the products set in this document setup.

Code

This field is enterable only if 'Agent Commission required' is checked. Select the agency commission setup code under which this commission amount is to be accounted for, during transaction. Once the 'Code' is entered, the description of the code is defaulted in the adjacent field.

Policy Inception days

Enter the number of days from Issue Date, when the risk coverage is to become active. For example, if the user enters 4 in this field and if the policy is generated on 12/02/2013(mm/dd/yyyy), then risk coverage starts 4 days later only i.e. from 12/06/2013.

☒ Policy From Date modifiable

Select the check box if the 'From' date of the policy is modifiable at the transaction level.

☒ Zero Premium Allowed YN

Select the check box if policy to be underwritten with zero premium else, system does not allow

Range From – To

If 'Policy From Date Modifiable' check box is selected, then enter the day's range within which the policy is modifiable in the respective fields.

Copy Condition from Parent

This option is used for child policies that are linked to a parent policy.

Select this option to copy the conditions that are applied at the parent policy level to the child policy.



Parent-Child policy relationship has to be pre-defined at the product setup level to select this check box.

Percentage tolerance

Percentage tolerance is applicable only for premium FC conversion alone.

Enter the tolerance limit for percentages in this field.

Currency tolerance

Enter the tolerance limit for currency.

While doing the currency conversion for any premium amount (FC to FC or FC to LC), if there is any difference between the calculated value and existing value (i.e., the difference within the currency tolerance) system is unable to update the existing value with the calculated value, if not

then calculated value is updated to the existing value.

☒ **Policy Period modifiable**

Select the check box if the policy period is modifiable at the transaction level. If checked, the 'Policy To Date' is not modifiable. If un-checked, the 'Policy To Date' is modifiable

☒ **Fleet YN**

This field is applicable only for Motor product.

Select this check box to default this field at the transaction level as Fleet Policy.

SI (Sum Insured) Round to

Select from the given LOV the round off method to be set for the SI amount.

☒ **Apply Short Rate YN**

Select this check box if short rate is applicable for the product. The short rate for the product must be defined in Short rate master.

☒ **Cover SMI Relation YN**

Select this check box if relationship is between cover and SMI is applicable.

☒ **SI No of Decimals**

Select this check box if sum insured needs to be in decimals.

☒ **Premium No of Decimals**

Select this check box if premium needs to be in decimals

☒ **Premium Collection Required**

Select the check box if collection of premium (cash before cover concept) is to be completed before issue of the policy. The policy number will be generated only after the premium is collected. The said premium is collected through Premium Collection screen.

Commission Round to

Select from the LOV the round off method to be set for the commission amount.

Premium Round to

Select from the LOV the round off method to be set for the premium amount.

☒ **RI Allocation Required**

Select the check box if RI allocation is required for all the products attached to the document setup. If checked, on approval of the policy, RI related entries are passed before the premium collection is completed.

Customer A/C Document type

The option set in this field determines the processing type for posting the accounting entries for customers. Select the agent A/C document type from the list box. The options available are:

- ☐ Single Accounting
- ☐ Bulk Accounting
- ☐ No Accounting

New policy on renewal/Renewal processing allowed. If both these boxes are checked, a new policy number is generated on renewal processing.

Premium Currency Type

Select the premium currency type for all the products attached to this document setup, from the list box. The options available are:

- ☐ Premium in Premium Currency - The currency applicable to the customer as premium currency and calculate accordingly
- ☐ Premium in SI Currency - This defaults the SI currency to the premium currency

Agent A/C Document type

The option set in this field determines the processing type for posting the accounting entries for Agents/Brokers. Select the Agent A/C document type from the list box. The options available

are:

- ☐ Single Accounting
- ☐ Bulk Accounting
- ☐ No Accounting

☒ Risk Acceptance required

If some of the mandatory risk details are not available while issuing the policy a System generated Cover note (SGN) is issued. Once these details are available from the customer, the SGN is converted to a policy by using the 'SGN convert to Policy' screen. If the check box is selected here, all SGN's belonging to the products attached in this document setup is available in the SGN LOV in the 'SGN convert to Policy' screen.

☒ Provisional Account Doc YN

Select the check box if user needs to generate accounting entries before policy approval.

☒ Discount Account Doc YN

Select the check box if user needs to generate accounting entries before discounts on policy.

☒ Renewal Processing Allowed

Select the check box if renewal processing is required for the documents attached for the product.

☒ New Policy on Renewal

Select the check box to generate new policy number on renewal.

☒ Generate Policy on Renewal

Select the check box to generate policy on renewal processing

☒ Use Same Policy No YN

Select the check box if user wants to use the same policy number on renewal.

☒ Renewal Time Stamp

Select the check box if the renewal policy 'From' date to appear as the time stamp defined as same time else the renewal policy 'From' date appears as the time stamp defined as incremental time of one minute.

☒ Round the Sum Insured

Select the check box if the sum insured amount is to be rounded off.

☒ Round the Premium

Select the check box if the premium is to be rounded off.

☒ Debit/Credit Gen YN

Select the check box if debit/credit accounting entries are to be generated.



Applicable Branches

Click 'Applicable branches' button to set the applicable divisions of the company where this particular product is applicable. The product code is displayed automatically on entering this screen.



If the user needs this product to be applicable across all the divisions, enter "0" in the 'Division From' field and "zzzzzz" in the 'Division To' field.

The 'Applicable Divisions' screen displayed as shown below:

Fig. 98 – Applicable Branches

Office 'From' and 'To'

Enter or select 'Office From' and 'Office To' from the list of values. The LOV displays codes set in the Office/Division Master. Once the codes are selected, the description is defaulted in the respective fields.

Include

If this field is checked, it signifies that the defined product is applicable to the specified division range. If left unchecked, the division range is excluded.



Product

Click 'Product' button to set the products that requires the same policy document flow, from the LOV. The system displays the screen as shown below:

Fig. 99 – Applicable Products



Product code

Select the product code to be linked to the particular document setup from the LOV. The LOV displays codes set in the Product Setup. The description of the code is defaulted in the adjacent field.

Hide section

If the product code selected has only one section defined and this is set as default for the product, this 'Section' tab is hidden in the policy screen by checking the box in this field. This enables the risk details tab to display instead of the section tab, in the policy transaction screen.



If the selected product has multiple sections defined then the system is not permitted to check this box



Charges

Click this button to define all applicable charges and taxes for the products at the document setup level. The charges set here are defaulted for the particular document during transaction.



If multiple products have been set in the 'Product Block', click on each Product Code and then Click 'Charges' button to set the corresponding Charge details.

The system displays the screen as shown below:




Fig. 100 – Default Charges

The product code and description for which the charges are defined is defaulted in this block.

Tax/Charge type

All applicable taxes and charges have been clubbed under various charge types. Enter or select the applicable tax/charge type to be set, from the LOV. These charge types are pre-defined in the system. The description of the type is defaulted in the adjacent field.

Code

This field is linked with 'Tax/Charge Type' field. Enter or select the required tax/charge code for the selected charge type, from the LOV. The codes that are in the LOV are filtered based on the charge type selected. During transaction, these Charges is added to the Premium to be collected from the Customer The LOV displays codes set in the 'Taxes and Charges' Master. The description of the code is defaulted in the adjacent field.

Section

Click this button to define sections, if the selected product has various sections and policy types. Also set various properties like 'default' and 'mandatory' for these sections.

The properties set here define the behavior of the document at the transaction level.



If multiple products have been set in the 'Product Block', click on each product code and then Click 'Section' button to set the applicable sections for each product.

The system displays the screen as shown below:




Fig. 101 – Applicable Section

The product code and description for which the charges are defined is defaulted in this block.

Section Code

Select the section code from the LOV. The LOV displays those section codes that have been set for the product in the Product Setup Master. The description of the code is defaulted in the adjacent field.

Policy Type

The Policy Type for the selected section code in the 'Product Setup' master is defaulted along with the description in the corresponding fields once the section code is entered.

☒ **Mandatory**

Select the check box if the section code is to be mandatory for the product at the transaction level for the document setup. If checked, then the corresponding section is automatically inserted during transaction and the user is not allowed to delete.

☒ **Default**

Select the check box if the selected section code is to be defaulted for the product at the transaction level. If checked, then the corresponding section is automatically inserted during transaction but the user is allowed to delete. In case of multiple sections, the section set as default here appears in the 'Sections' screen once the sections tab is clicked, during transactions.

☒ **Default to Risk**

Select the check box if the selected section code needs to be defaulted automatically for the product at the risk level.

This means that if a section does not have any risk details to be captured and only requires directly setting up the covers during transaction, checking this box here would mean that a dummy risk is created for the product during transaction to take care of the internal flow of the system



Print

Click this button to set the print options and properties for the 'Policy Schedule/Certificate' for all the defined products.



If multiple products have been set in the 'Product Block', click on each product code and then Click 'Print' button to set the print options/properties for each product.

The system displays the screen as shown below:

Sr. No.	Type*	Description	Section From*	Section To	Document Required	Print Before Approval	Reprint Allowed	No. of Prints	Report
1	1	Schedule	0	////	☒	☒	☒	10	PSCH0001
4	3	FACULTATIVE INSURANCE SLIP RISKWISE	0	////	☒	☒	☒	10	PSCH0053
2	7	Credit Note/Debit Note (Fac Out)	0	////	☒	☒	☒	10	PSCH0052
2	5	Debit Note/Receipt Voucher / Credit Note/Payment Vo	0	////	☒	☒	☒	10	PSCH0051

Short Description:

Description BL:

Short Description BL:

Effective From Date: Effective To Date:

Section From: Section To:

Main

Fig. 102 – Print Setup

The product code and description for which the charges are defined is defaulted in this block.

Print Type

Use this field to set the print type of the document. The various print types are; schedules/certificates. Enter or select the print type from the LOV. The LOV displays codes pre-defined in the system.



Description

Once the print type is entered, the description pertaining to it is defaulted in this field. The user may alter this if required.

Section 'From' and 'To'

Enter or select the 'Section From' and 'Section To' from the LOV. During transaction, printing is

confined to the section range specified here. The LOV displays those section codes defined in the section tab in this master. The description pertaining to the codes is defaulted in the respective fields.

☒ **Document required**

Select the check box if a printed document is to be generated.

☒ **Print before approval**

Select the check box, if the printing of the policy is to be allowed before the policy is approved.

☒ **Reprint allowed**

Select the check box, if reprints of the same policy are to be allowed.

Number of Prints

The number of prints required for the product is set here.

Reports

Use this field to enter the report ID for the product. This field is linked to the print type selected.

Short description

This field defaults from the 'Description' field. The user may alter this if required.



Based on the requirements, the description or the short description is mapped and used while printing the document

Effective 'From' and 'To' Date

Enter or select the validity period for the print setup using the 'From' and 'To' date fields. The dates are selected from the Calendar help. If no period is defined, then there is no end date for the validity period.



Condition

Click this button to define conditions applicable for the document setup.

The user can also enter the conditions that are required from the given list of values. The system displays the screen as shown below:

Code*	Description	Short Desc.	Long Desc.
7004060	GENERAL CONDITIONS	GENERAL CONDITIONS	GENERAL CONDITIONS

Description: GENERAL CONDITIONS
 Short Desc.: GENERAL CONDITIONS
 Long Desc.: GENERAL CONDITIONS

Fig. 103 – Policy Level Conditions




Code

Enter or select the conditions at the policy level from the list of values. Once the code is entered, its description is defaulted in the 'Description', 'Short Description', and 'Long Description' fields as defined in the 'Conditions Master'.



To Do List

Click this button to define the To Do list for the document code that needs to appear in the transaction as per the effective date.



The screenshot shows a 'To Do List' form with a table of checklist items. The table has columns for Serial No, To Do List Description, Effective From, Effective To, and Mandatory Y/N. There are five items listed, each with a checkbox for mandatory status. A 'Main' button is in the top right corner. Below the table is a 'Description BL' text field.

Serial No	To Do List Description	Effective From	Effective To	Mandatory Y/N ?
1	Is Proposal form and/or Underwriting information received	01/01/2000	31/12/2030	☐
2	Is rating done as per underwriting guideline	01/01/2000	31/12/2030	☐
3	Is rating done as per rates quoted approved by A.G.M(Tech)	01/01/2000	31/12/2030	☐
4	Is policy issued contained all the terms and clauses as mentioned in original quota	01/01/2000	31/12/2030	☐
5	Debit/ Credit notes and calculation sheet signed by in accordance with authority limi	01/01/2000	31/12/2030	☐

Description BL:

Fig. 104 – To Do List



Serial No

Enter the serial number for the list item.



To Do List Description

Enter the checklist items that are to be followed / collected from the customer during the policy creation process.

Effective 'From' and 'To' Date

Enter or select the validity period for the 'To Do List' using the 'From' and 'To' date fields. The dates are selected from the Calendar help. If no period is defined, then there is no end date for the validity period.

☒ Mandatory Y/N

Select the check box to set the mandatory checklist items from the available checklist values.

ENDORSEMENT

Select this setup to enter details pertaining to the flow and setup of the endorsement document for a product or set of products. Various endorsement types have been pre-defined in the system. For each of these endorsement types the user can setup various endorsement codes, set the flow and attach the same to the applicable product/s. This document setup is to be done once the policy document setup is completed. The screen is as displayed below.

The screenshot shows the 'INSURANCE CO LTD' Endorsement Setup screen. It includes fields for Document Code (ED002), Short Desc (Increase of Sum Insured), Effective From Date (01/01/2000), Policy No Gen Type (Setup), Mode of Posting (Online), Endt No Gen Type (Setup), Risk SI Limit, and various checkboxes for options like Hold Y/N, Reinstatement of Cancellation, Non-Renewal Y/N, Update Exchange Rate, Extn. Period Less than Policy Period Only, Restrict Cancellation when Claim's Open, Out of Sequence Y/N, FAC Adjustment Y/N, and Najmnet Applicable Y/N. There are also dropdown menus for Surveyor A/C Doc. Type, Endorsement Type, Customer A/C Doc Type, and Agent A/C Doc Type.

Fig. 105 – Endorsement



The buttons available in the screen are the same as explained under Policy Setup. Refer the '[Policy](#)' Document Setup section of the document for more information.



Document Code

The document code field is used to enter endorsement codes applicable for a product/s. Generic endorsement types have been provided in the system. These are further customized to suit the requirements of each product or products.

Enter the code in this field along with its name/description in the adjacent field. This name appears in the transaction screen while passing an endorsement. Existing codes are viewed in the query mode.

Short Description

This field defaults the name or description from the 'Document Code' field. The user may alter it if required.



Based on the requirements, the description or the short description can be mapped and used while printing the document

Mode of Posting

Set the account-processing mode for all the products attached to the endorsement document setup. The mode the user select here is applied during transaction, on passing/approving the endorsement. Select the mode of posting from the drop-down list

- ☐ Batch
- ☐ Online

Effective 'From' and 'To' Date

Enter or select the validity period for the document setup using the 'From' and 'To' date fields. The dates are selected from the Calendar help. If no period is defined, then there is no end date for the validity period.

☒ Policy Number Generation Type

Select the appropriate option from this check box to define the policy number generation type. The options available are:

- ☐ Custom – Allows user to enter the policy number manually.
- ☐ Setup – Allows users to define unique policy number setup through the 'Document Number' setup screen.

☒ Endorsement Number Generation Type

Select the appropriate option from this check box to define the endorsement number generation type. The options available are:

- ☐ Custom – Allows user to enter the endorsement number manually.
- ☐ Setup – Allows users to define unique endorsement number setup through the 'Document Number' setup screen.

Surveyor A/C Document type

The option set in this field determines the processing type for posting the accounting entries for surveyors. Select the surveyor A/C document type from the drop-down list. The options available are:

- ☐ Single Accounting
- ☐ Bulk Accounting
- ☐ No Accounting

Risk SI limit

Set the maximum limit for the sum insured for the risk while passing an endorsement. The total sum insured for the risk during endorsement is checked against the limit set here. If the total sum insured is higher than the limit set here an appropriate warning is issued in the system.



Endorsement Type

Various endorsement types have been pre-defined in the system. These are generic in nature and are to be used for all classes of business. For the endorsement document code defined in the previous field, attach the applicable endorsement type. Once the code is entered, the description pertaining to the code is defaulted in the adjacent field.

Endorsement print text

Enter the description of the actual endorsement to be done. The text the user enters here is defaulted in the endorsement screen while passing the endorsement. The user has the permission to modify it at the transaction level. This appears on the endorsement schedule also.

☒ Reinstatement of Cancellation

If this is checked, then the endorsement code specified acts as a 'Re-instatement of Cancelled Policy' endorsement.

The Endorsement button is enabled on the cancelled policies (within the products specified in the Product tab within the Endorsement Document Setup), and the Endorsement Type 'Reinstatement of Cancellation' is passed on the cancelled policy to reinstate the same.



- ☐ Only those policies that have been cancelled due to non-payment of premium as well on insured request are cancelled
- ☐ No reinstatement of policies is allowed, which have been cancelled for reasons of fraud/misrepresentation

Maximum Extension Period in Days

Enter the maximum period to be allowed for extension of the policy. The extension is possible by passing an extension type of endorsement. The value entered here is checked with the 'Policy period unit' set for the policy in the Policy setup.

Maximum Number of Extension

The maximum number of extensions to be allowed by using the cancellation endorsement is set here. By default '1' appears as soon as the screen is enabled.

Minimum Silent Period

Enter the minimum number of days; the product can be in silent mode.

☒ **Update Exchange Rate**

Select the check box, if the exchange rate is to be set as modifiable at the transaction level while passing the endorsement. If left un-checked, no modification is possible.

☒ **Extension Period Less than Policy Period Only**

If the check box is selected, any extension of the policy period should not be more than the original policy period. For example if the policy period is 2 years, then any extension is for 1 year and not for another 2 years. This is used widely in short-term policies.



The above validation works in conjunction with the values set for 'Maximum extension period' and 'Maximum number of extensions'.

Consecutive days

This field is applicable for 'Cancellation' type of endorsement and is used effectively for short-term policies. The functionality of this is explained through the following example:

☐ Policy period: 01/01/2007 to 30/06/2007

☐ Policy cancellation date: 20/03/2007

☐ Consecutive days: 30

In the above scenario, refund of premium is calculated for 3 months. Premium is retained for the first 3 months as the cancellation date falls in the middle of the 3rd month because the consecutive days are set as 30 days.



If the number of consecutive days is set for the product in the endorsement document setup screen, then refund of premium is based on this number.

☒ **Restrict Cancellation When Claim is Open**

Select the check box if a Cancellation Endorsement should not be passed when a claim is open on the Policy. This also impact any provisions to refund premium on cancelled policy with normal claims or with total loss claims based on setup defined (see previous field).

Leaving this check box unselected allows a user to cancel a policy with a normal claim or with a total loss claim where a different subject matter is covered under a single policy and to refund the premium on the claim affected risk.

Minimum Premium in LC for Refund

Enter in this field the minimum premium applicable towards the refund of a selected endorsement type. The application, during transactions, allows for refund only if it is above the minimum premium for refund defined in this field. Else, an error message is raised.

Minimum Premium in LC for Payment

Enter in this field the minimum premium on collection applicable for the selected endorsement type. The application, during transactions, accepts a premium collection value only if it is above the minimum premium for collection defined in this field. Else, an error message is raised.

Refund Even Claim

This is an additional provision that facilitates users to determine (at the policy or risk level) on whether to refund premium on cancelled policy with normal claims/ with total loss claims or not.

A user is able to select any one of the following options from the drop-down list:

- ☐ No refund if claim exists for the policy
- ☐ Refund even claim for policy/risk
- ☐ No refund if the claim exists for the risk
- ☐ Refund applicable if not total loss claim for the risk
- ☐ No refund if total loss claim for the policy

☒ FAC Msg YN

Select the check box if the FAC placement message needs to be displayed at transaction level.

☒ FAC Adjustment YN

Select the check box if FAC adjustment is required at transaction level.

CLAIMS

The Claims Setup screen allows the user to choose the accounting mode, exchange rate calculation, cover effective date validation, and estimate applicable currency, currency rate type, mode of posting and many more features.

Click Claim Setup to view the following screen:

The screenshot shows the 'INSURANCE CO LTD' Claims Setup screen. It features a top navigation bar with the Infotech logo and a toolbar with icons for navigation and actions. The main form area is divided into several sections:

- Document Code***: 30-CL-01-001, General Accident
- Short Desc**: (empty field)
- Effective From Date**: 01/01/2000
- Claim No Gen Type**: Setup
- Currency Rate Type**: Buying
- Mode of Posting**: Online
- Effective To Date**: 01/01/2020
- Account Estimation in Claim Req.**: (empty field)
- Accounting Mode**: Immediate
- Cover Eff. Date Validation**: Loss Date
- Estimate Applicable Currency**: Risk Currency
- Exchange Rate Calc. Type**: Estimate Date
- Dflt Recovery Estimate***: 3000001
- Dflt Recovery Estimate on Refund Premium***: (empty field)
- Dflt Rfnd Rec. Est. Req. YN**: (empty field)
- Loss Date Validation Required**: (checked)
- Rounded To***: 02
- NEAREST 5**: (selected)
- Assessment Dtls Val. Reqd**: No validation
- Loss Dt. Val. Prior Claim Req.**: (empty field)
- Loss Desc Modifiable YN**: (checked)
- Dflt Close Reason Code***: (empty field)
- Single Risk per Claim YN**: (checked)
- Single Policy per Claim YN**: (checked)
- Generate Coins A/C**: (checked)
- Generate Claim A/C**: (checked)
- Generate FAC A/C**: (checked)
- Auto Inc. of Estimation**: (empty field)
- MACT Claim**: (empty field)

Fig. 106 – Claims

Document Code

Select the document code from the LOV.

☒ Claim Number Generation Type

Select the appropriate option from this check box to define the claim number generation type. The options available are:

- ☐ Custom – Allows user to enter the claim number manually.
- ☐ Setup – Allows users to define unique claim number through the 'Document Number' setup screen. Based on the system parameter, the system generates the Claim number at any one of the following stages in the transaction level:
 - o On saving the transaction
 - o On clicking the 'Generate' button or
 - o On clicking the 'Claim Approval button

Currency Rate Type

Select the means of transaction, buying or selling.

☒ **Account Estimation in Claim Required**

Select the check box if account estimation is required for claim request.

Accounting Mode

Select the Accounting mode, immediate or batch.



Cover Effective Date Validation

Select the effective loss or intimation cover date for validation.

- ☐ Loss Date – On selecting this option, user is allowed to register the claim when the loss date is within the cover effective period
- ☐ Intimation date – On selecting this option, user is allowed to register the claim when the intimation date is within the cover effective period

Estimate Applicable Currency

Select the currency defined for risk or any currency.

- ☐ If set as Risk currency, estimate is done only in risk currency
- ☐ If set as any currency, estimate currency can be in any currency

Exchange Rate Calculation Type

Select the exchange rate on the basis of five dates for calculation.

- ☐ Policy
- ☐ Loss date
- ☐ Current date
- ☐ Estimate date
- ☐ Intimation Date

Default Recovery Estimate

Select the default recovery, default salvage or salvage receipt estimate from the LOV.

Default Refund Rec. Est. Required YN

If Default Refund Recovery Estimation Required field is enabled the corresponding field is also enabled and the user can enter the value or select from the LOV.

Default Recovery Estimate on Refund Premium

Select the default recovery, default salvage or salvage receipt estimate from the LOV.

☒ **Loss Date Validation Required**

Select this check box if the loss date validation is required for claim setup. When set to yes, system does not allow any loss date prior to previous claim loss date.

Rounded To

The user can enter the value to round off the sum to the specified value by default.

Assessment Default Validation Required

If the default validation is required for assessment then this field is checked. No warning/error/warning can be selected.

☒ **Loss Date Validation Prior Claim Required**

Select this check box if the loss date for validation is required for prior claim.

☒ **Loss Description Modifiable YN**

Select this check box if the loss description needs to be modified.

Default Close Reason Code

Enter the default close reason code.

☒ **Single Risk per Claim YN**

Select this check box if single risk is to be enabled for a claim. When this option is enabled the corresponding single policy per claim is disabled, if not it is enabled.

☒ **Single Policy per Claim YN**

This check box is selected by default depending on the risk per claim field, if not it is applied for any claim.

☒ **Generate Coins A/C**

Select the check box if the account for the Co insurance is to be generated

☒ **Generate Claim A/C**

Select the check box if the account for the Claim is to be generated

☒ **Generate FAC A/C**

Select the check box if the account for the Facultative of Re insurance is to be generated

☒ **MACT Claim**

Select the check box if the account for the Motor Accident Claims Tribunal is to be generated. If this option is selected only the claim for orphan is possible.



The Product and To Do list are similar to other document setups and hence not explained here.



Schedule

Click this button from the header block to view the screen shown below:

Sr. No.	Caption	Data Type	Width	Hint	Mandatory
		Text	240		☐
					☐
					☐
					☐

Bilingual Details

Caption:

Hint:

Fig. 107 – Schedule Setup

Caption

Enter the caption for the schedule.

Data Type

Select the Data Type of the caption, either Date/Number/Text/ {Yes/No} Option.

Width

Depending on the Data Type the width is displayed accordingly.

Hint

Enter the hint.

☒ **Mandatory**

Select the check box if the field has to be mandatory.



The field entries for First Notice Loss are similar to that of Claims Setup.

CLAIM INTIMATION

When a loss occurs, the customer informs the insurance company about the same. The Claim Intimation or First Notice Loss screen enables the user to enter these details.

The document setup for Claim Intimation as shown below:

Fig. 108 – Claim Intimation - First Notice Loss

The field entries technique for the Claim Intimation screen is similar to the [Claims Setup](#) screen. Please refer the above section for detailed information.

DOCUMENT NUMBER GENERATION

The Document Number Generation Setup screen defines the method of generation of the Quotation/Proposal/Policy/Endorsement/Claim number.

The user has the option of setting up the document number generation flow based on the following fields in the header block (highlighted in blue in the figure below):

- ☐ Document Type
- ☐ Document Code
- ☐ Company Code
- ☐ Division Code
- ☐ Department Code

The process of document number generation setup in PREMIA is as follows:

- ☐ Select the required combination in the header block for the number setup.
- ☐ Set the required parameter values for the generation of the quotation / proposal / policy / endorsement / claim number in the 'Level Details' block
- ☐ Set the values required to be included as part of the document number
- ☐ Set the values to be included to define the serial number range
- ☐ Set the running serial number details in the 'Range Setup' block for the parameter values set to be part of the document number in the 'Level Details' block

Click 'Document Number Generation' menu. The system displays the screen as shown below:

Document Number Setup

Document Type* 4 Claims

Document Code* 0 All Documents

Company Code* 001 INSURANCE CO LTD

Branch Code*

Department Code*

Field Separator /

Effective From 01/01/2000 To 26/11/2032

Level Details

Level Number	Serial No.	Static Value	Level Parameter Code*	Level Ref Column*	Include in Serial No. Range	BP Text	Part of Doc No
1		C					
2			066	CLM_DVN_CODE		Office code	
3			068	CLM_PROD_CODE		Product	
4			067	CLM_YEAR		Clm Year	
5							

Para Level Name

BP Text BL

Fig. 109 – Document Number Generation

The multiple combinations that are available for the setup based on the above-mentioned fields are as follows:

- ☐ Combination 1 – Select for a combination of a particular document type and a particular document code
- ☐ Combination 2 – Select for a combination of a particular document type and the 'All Documents' document code
- ☐ Combination 3 – Select for a combination of a particular document type, particular/all documents document code and the company code

The various fields in the above screen are explained below:

Document Type

Select the document type for which the number generation is to be setup, from the LOV. The LOV displays codes pre-defined in the system. Once the code is entered, the description pertaining to the code is defaulted in the adjacent field.

Document code

Select the required document code for which the number generation is to be setup, from the LOV. The LOV displays codes set in the various document setups. Once the code is entered, the description pertaining to the code is defaulted in the adjacent field.



The user has the option of setting the same document number generation method for all documents defined in the document setups, across all classes of business. To do this, click on the 'All Document' button adjacent to the document code field. The value '0' is populated in this field

Company Code

Select the Company code for which the number generation is to be setup from the LOV. The LOV displays codes set in the Financials. Once the code is entered, the description pertaining to the code is defaulted in the adjacent field.

Branch Code

Select the applicable branch code for which the number generation is to be setup, from the LOV.

The LOV displays codes set in the Financials and is filtered for the Company code selected in the previous field. Once the code is entered, the description pertaining to the code is defaulted in the adjacent field.



Department Code

Select the applicable department code for which the number generation is to be setup, from the LOV. The LOV displays codes set in the Financials and is filtered for the combination of the Company and division codes. Once the code is entered, the description pertaining to the code is defaulted in the adjacent field.

Field Separator

The field separator is used to separate the various parameter values selected for generating the document number in the 'Level Details' block. For example, if the user has selected the three parameter values of Company Code (001), Division Code (411200) and Department Code (31) in the 'Level Details' block for a 'policy' document type, and if "/" is specified as the field separator, then the generated number in the policy transaction screen will be: 001/411200/31/(serial number)

Effective 'From' and 'To' Date

Enter or select the validity period for the document number generation setup using the 'From' and 'To' date fields. The dates are selected from the Calendar help. If no period is defined, then there is no end date for the validity period.

Level Details

Use the level details block to enter static or parameter values to be used for number generation. The values set here is a part of the document number being generated. For example, if 'FIR' is one level, '11' is another level and so on, and then the generated number is 'FIR/11/001'. The user is able to set the sequence/order in which these values appear as part of the document number.

Level Number	Serial No.	Serial No. Pad	Serial No. Length	Static Value	Static Value	Level Parameter Code*	Level Ref Column*	Include in Serial No Range	BP Text	Part of Doc No
1	☐	☐		☒	C			☐		☒
2	☐	☐		☐		066	CLM_DVN_CODE	☒	Office code	☒
3	☐	☐		☐		068	CLM_PROD_CODE	☒	Product	☒
4	☐	☐		☐		067	CLM_YEAR	☒	Clin Year	☒
5	☒	☒	6	☐				☐		☒

Para Level Name BP Text BL

Fig. 110 – Level Details

Level Number

Enter the level number in this field. This number uniquely identifies each level/order/sequence in the document number. This field is defaulted with a running serial number starting with "1". The user may alter this order if necessary. The order in which the document number is displayed in the transaction screen depends upon the order in which the level number is specified.

Serial Number

Check this field if the document number is to have a running serial number. Once this field is checked, the 'Part of document number' field is automatically checked.



Serial number is set for only one level

Serial Number Pad

This field is enterable only if the 'Serial Number' field is checked.

Check this field if the serial number is to be padded. Padding is a process in which the serial number is prefixed with 'zeros'. Padding can be done based on the requirements and depends on the length of the serial number set in the 'Serial Number Length' field. For example, if the

user checks this field, set the serial number length to 4 and set the first number to 1 in range setup, then the running serial number For Example: 0001, 0002, 0003... 0015.

Serial Number Length

This field is enterable only if the 'Serial Number Pad' field is checked. Enter the length of the serial number in this field. For example, if the user enters 4 in this field the maximum length of the serial number during transaction cannot exceed four digits.

Static Value

Check this field, if a static value is required to be a part of the document number. The static value is placed in the document number based on the 'Level Number' set.

Static value description

If the 'Static Value' is checked, enter the static value description in this field. This static value features without any change in all the document numbers being generated for the document type. For example, if the user enters "POL" (policy) as the static value at level 1, then all the generated document numbers are of the form: "POL/0001, POL/0002"



Level Parameter Code

If any parameters like, 'Company code', 'Division code', 'Underwriting code', 'Product code', etc., are required in the document number, select the same from the LOV. The display of these values depends on the level number set for the values. The column name of the level parameter code is defaulted in the 'Level Reference Column' field, based on the code entered in the 'Level Parameter Code' field. The user may alter it if necessary. In the above field, the various parameters such as 'Office code', 'Class code' and 'Underwriting year' or 'Calendar year' have been set as the parameter codes to be included in the serial number range. The user is allowed to select the applicable values from the LOV's provided.

The Boilerplate text (parameter name) is defaulted with the parameter name, once the parameter code is selected. This is the text that is displayed for the code (if set to be included in the serial number range) in the 'Range Setup' block. The user is able to alter the text, if necessary.

The parameter level name pertaining to the code is defaulted in the 'Parameter Level Name' field.

Include in Serial Number Range

Check this box, if the parameter code is to be included as part of the serial number range. Based on the value set here, the running serial number is to be set/reset for a parameter code or a combination of parameter codes. This field is enabled only for 'Level Parameter code'. Once checked, the parameter code is displayed as a separate column in the Range Setup block.

Part of Document Number

Check this field, if the 'Serial number', 'Static value' or 'Level parameter code' is to be included as part of the document number generated.




If the 'Serial Number' field is checked, this field is also checked automatically. The user may uncheck it if necessary.

Important: Not including the serial number as a part of the document number may cause inconvenience in tracking the policy.

Range Setup

Click 'Range Setup' button to setup the serial number range of the document number. The parameter codes that are set to be included in the serial number range in the 'Level Details' block are displayed here.



Office code	Product	Clin Year	Current No	First No	Last No	Effective From Date	Effective To Date
02	1008	2012	0	1	999999	01/01/2013	31/12/2013
02	1008	2013	0	1	999999	01/01/2013	31/12/2013
02	1008	2013	0	1	999999	01/01/2013	31/12/2013
02	1008	2012	0	1	999999	01/01/2012	31/12/2012
100	1008	2013	0	1	999999	01/01/2013	31/12/2013

Fig. 111 – Range Setup

ACCOUNT SETUP

Accounts Setup enables the user to map all transactions that occur within PREMIA as account entries to the General Ledger available in the Accounts module.

For example:

Customer A pays a premium of \$1000 to the insurance company through a cheque, where a special charge of \$5 is applicable. The cheque is then presented to the insurance company's bank. In general ledger, the following ledger posting is entered:

Debit - The Insurance Company's Bank via cheque payment

Credit - Premium paid by the customer less the service tax deductible.

There are three lines of account entries- Debit, Credit and the service tax applicable.

For example:


☐ Dr. Bank \$1000

☐ Cr: Premium \$995

☐ Less \$5

To map these postings, use the three sub-menus (Customer, Premium and Miscellaneous Account Setups) available within the Accounts Setup sub menu of the Masters main menu.

Double click on  placed before the Accounts Setup sub menu. The 'Account Setup' menu comprises of the following sub-menus:



- **Account Setup**
 - o Premium Account Setup
 - o Transaction Account Setup
 - o Miscellaneous Account Set Up
 - o Customer Account Setup
 - o Claims Account Setup
 - o Claims OSLR/IBNR Account Setup
 - o UPR/IBNR/Surplus Account Setup

Fig. 112 – Account Setup Menu

PREMIUM ACCOUNT SETUP


Premium Account Setup menu enables users to map the premium collected for a product, cover by a range of branches (along with other parameters) to a main and sub account. The main account is the accounting head under which all the premium general ledger entries are placed.

For the sake of better understanding, Premium Account Setup screen is split into two. The first half of the Premium Account Setup screen (before the Force checkboxes) is the Premium collection detail area. In this area, the user is allowed to enter the Company, Office, and Department details and include information on the product, cover and the document type. This avoids further mapping on a particular range of data.

The next step is to enter account related details. This is carried out in the second half of the Premium Account Setup screen (after the Force checkboxes).

This ensures that the account type, with all its parameters complete, is entered into accounts.

Click 'Premium Account Setup' menu to view the following screen



The screenshot shows the 'Premium Account Setup' form. It is divided into two main sections. The top section contains fields for 'Company From', 'Office From', 'Department From', 'Business Type From', 'Business Source From', 'Product Code From', 'Section From', 'Cover From', 'Pas Cvr Indicator', 'Doc Type From', and 'Doc Code From'. Each field has a value and a corresponding 'Upto' field. The bottom section contains 'Force Company', 'Force Office', and 'Force Department' checkboxes, followed by 'Company', 'Office', 'Department', 'Main Account', 'Sub Account', 'Analysis Code1', 'Analysis Code2', 'Activity Code1', 'Activity Code2', 'Effective From Date', and 'Effective To Date'.

Fig. 113 – Premium Account Setup



Company From/Upto

Select the Company Code range from the LOV.

Office From/Upto

Select the Office Code range from the LOV. Office refers to the branch or division office

Department Code From/Upto

Select the Department Code range from the LOV. Department refers to the class of business.

Business From/Upto

Select the Business range from the LOV. Business refers to the type of business such as direct without co-insurance, direct with co-insurance, treaty.

Business Source From/Upto

Select the Business Source range from the LOV. Business Source refers to the source through which the business is generated and includes direct, agent or broker

Product Code From/Upto

Select the Product Code range from the LOV.

Section From/Upto

Select the Section Code range from the LOV.

Cover From/Upto

Select the Cover Code range from the LOV. There is a provision for cover level accounting.

Cover Indicator

Select the cover indicator code from the LOV. Cover Indicator refers to the type of cover offered. The available options in Cover are Own Damage, Third Party Cover or Others.



Document Type From/Upto

Select the Document type range from the LOV. Documents are of various types such as Quotation, Policy, Proposal, Claim, and Legal File.

Document Code From/Upto

Select the Document code range from the LOV. Document Code is a sub classification of the document type. For example, Claim is to be either third party claim or own damage.

☒ **Force Company/Office/Department**

Select any or a combination of these checkboxes to force the login Company/Office/Department details to be default values during accounts processing.

☒ **New/Renewal Business**

Select the required option from the drop-down list.

- ☐ Renewal Business – Select this option to set the premium account setup only for renewal business
- ☐ New Business – Select this option to set the premium account setup only for new business
- ☐ Both



Company Code

Select the Company Code from the LOV. Its description is defaulted in the adjacent display field.



Office

Select the Office Code from the LOV. Its description is defaulted in the adjacent display field.



Department

Select the Department Code from the LOV. Its description is defaulted in the adjacent display field.



Main Account Code

Select the Main Account Code from the LOV. Its description is defaulted in the adjacent display field.

Sub Account Code

Select the Sub Account Code from the LOV. Its description is defaulted in the adjacent display field.

Analysis Code 1 and 2

Analysis Code adds a level of filter so that the reports generated through the reports module has a broad set of uniform keywords. The user is able to add multiple filters by stating the classification, sub classification etc. The user is able to select the analysis code from the LOV or manually enter the same.

Activity Code 1 and 2

Analysis Code is similar to the remarks field. In this field, the user is able to add more information that is in line with the current field entry operations.

Effective From/To Date

Enter or select the 'From' and 'To' dates from the Calendar help. These dates specify the validity period.

Advance / Remittance

Some of the premiums collected might be an advance (premium collected beforehand) or remittances (premium collected for an old policy). In either case, the accounting procedure differs and hence advances and remittance is posted under exclusive advance and remittance main accounts respectively.

Enter the premium collection details in the first half of the screen (before the Force checkboxes), Click Advance button to view the following screen.




Fig. 114 – Advance Premium Details

Advance Force Company/Office/Department

Select any or a combination of these checkboxes to force the login Company/Office/Department details to be default values during accounts processing.

Advance Main Account Code

Select the Advance Main Account Code from the LOV. Its description can be viewed in the adjacent display box.



This advance main account is different from the Main Account code that the user has entered in the Premium Account Setup.

Advance Sub Account Code

Select the Advance Sub Account Code from the LOV. Its description can be viewed in the adjacent display box.

Advance Company Code

Select the Advance Company Code from the LOV. Its description can be viewed in the adjacent display box.

Advance Office Code

Select the Advance office Code from the LOV. Its description can be viewed in the adjacent display box.

Advance Department Code

Select the Advance Department Code from the LOV. Its description can be viewed in the adjacent display box.

Advance Analysis Code 1 and 2

Analysis Code adds a level of filter so that the reports generated through the reports module has a broad set of uniform keywords. The user can add multiple filters by stating the classification, sub classification etc. The user can select the analysis code from the LOV or manually enter the same.

Advance Activity Code 1 and 2

Analysis Code is similar to the remarks field. In this field, the user can add more information that is in line with the current field entry operations.

Effective From/To Date

Enter or select the 'From' and 'To' dates from the Application Calendar which is accessed using the LOV key. These dates specify the validity period.

On completing the Advance field entry, Click 'Main' button

On completing the field entries, click 'Save' button to save the details.



The field entries for Remittance are similar to Advance. For further reference to Remittance field entries please refer to Advance section in this module.

TRANSACTION ACCOUNT SETUP

All the transactions carried out in PREMIA is raised as a Debit, Credit notes, Receipt, Payment or a Journal Voucher during accounts processing. To facilitate this process, all the transaction types (based on the company, office and department) are mapped to their respective notes/voucher in the Transaction Code Setup.

Click 'Transaction Code Setup' menu to view the following screen.

Transaction Account Setup

INSURANCE CO LTD

Transaction Code setup

Transaction Type From*	19	Policy Surveyor Fee	Upto*	19	Policy Surveyor Fee
Company From*	001	INSURANCE CO LTD	Upto*	001	INSURANCE CO LTD
Office From*	110		Upto*	110	
Department From*	0		Upto*	zzzzz	
Debit Note TXN Code*	DN110	Debit Note Operations Branch Office			
Credit Note TXN Code*	CN110	Credit Note Operations Branch Office			
Receipt TXN Code*	RVC110	Receipt voucher Cash Branch Office			
Payment TXN Code*	PVC110	Payment voucher Cash Branch Office			
JV TXN Code*	JV	Journal Voucher			
Effective From Date	01/01/2000		Effective To Date	31/12/2099	

Fig. 115 – Transaction Code Setup

Transaction Type From/Upto

Select the type range from the LOV. Transaction Type indicates the Transaction Code type.

Company From/Upto

Select the Company Code range from the LOV.

Office From/Upto

Select the Office Code range from the LOV. Office refers to the branch or division office.

Department Code From/Upto

Select the Department Code range from the LOV. Department refers to the class of business



Debit Note Transaction Code

Select the Debit Note Transaction Code from the LOV. Its description is defaulted in the adjacent display field.



Credit Note Transaction Code

Select the Credit Account Transaction Code from the LOV. Its description is defaulted in the adjacent display field.



Receipt Transaction Code

Select the Receipt Transaction Code from the LOV. Its description is defaulted in the adjacent display field.

display field.



Payment Transaction Code

Select the Payment Transaction Code from the LOV. Its description is defaulted in the adjacent display field.



Journal Voucher Transaction Code

Select the Journal Voucher Transaction Code from the LOV. Its description is defaulted in the adjacent display field.

Effective From and To Date

Enter or select the 'From' and 'To' dates from the Calendar help. These dates specify the validity period.


MISCELLANEOUS ACCOUNT SETUP

Miscellaneous Account Setup helps users to map the various taxes and additional expenses that occurs while generating a policy to a main and sub account based on the range of parameters selected (For example: Office, Department etc). The main account is the accounting head under which all the miscellaneous general ledger entries would be placed.

For the sake of better understanding, Premium Account Setup screen is split into two. The first half of the Premium Account Setup screen (before the Force checkboxes) is the Miscellaneous Account setup. In this area, the user is able to select the miscellaneous type and enter the Company, Office, and Department details and include information on the cover and the account type. This would avoid further mapping on a particular range of data.

The next step is to enter account related details. This is carried out in the second half of the Premium Account Setup screen (after the Force checkboxes). This would ensure that the account type, with all its parameters complete, is entered into accounts.

Click 'Miscellaneous Account Setup' menu to view the following screen.



The screenshot shows the 'Miscellaneous Account Setup' form. It is divided into two main sections. The left section contains various input fields for account details, including Type (014 Inward Outward Charge), Cover Indicator (OTH Others), Business From (1 Direct without coinsurance), Business Source From (0), Ds Type From (2 Policy), Ds Code From (0), Product From (9001 Oil & gas), Section Code From (0), Code From (0), Acnt Source From (0), Company From (0), Office From (0), and Department From (0). Below these are checkboxes for Force Company, Force Office, and Force Department, all of which are checked. The right section contains a list of 'Upto' values (2, 3, 9001) with corresponding descriptions (Direct with coinsurance, Endorsement, Oil & gas). At the bottom, there are fields for Main Account (3602001 COINSURANCE ADMIN CHARGE DIRECT), Sub Account (3602009 COINSURANCE ADMIN CHARGE DIRECT), Company (001 INSURANCE CO LTD), Office (100 Head Office), Department (90 Oil and Gas), Analysis Code 1, Activity Code 1, Analysis Code 2, Activity Code 2, Effective From Date (01/01/2000), and Effective To Date (31/12/2009).

Fig. 116 – Miscellaneous Account Setup



Type

Select the type from the LOV. Type indicates the miscellaneous type.

Cover Indicator

Select the cover indicator from the LOV. Cover Indicator refers to the type of cover offered. The option in Covers is Own Damage, Third Party Cover or Others.

Business From/Upto

Select the Business range from the LOV. Business refers to the source of business such as direct without co-insurance, direct with co-insurance and treaty.

Business Source From/Upto

Select the Business Source range from the LOV. Business Source refers to the source through which the business is generated and includes direct, agent or broker.

Document Type From/Upto

Documents are of various types such as Quotation, Policy, Proposal, Claim, and Legal File. Select the Document type range from the LOV.

Document Code From/Upto

Select the Document code range from the LOV Document Code is a sub classification of the document type. For example, the options available in Claim are third party claim or own damage.

Product From/Upto

Select the Product from the LOV.

Section Code From/Upto

Select or enter the section code from the LOV.

Code From/Upto

Select the Code from the LOV. Some of the Miscellaneous Type has a sub-classification. (For Example: If Service Tax is the miscellaneous type, state service tax might be the sub-classification).

Account Source From/Upto

Select the Account Source Code range from the LOV. Account source is either company or the customer.

Company From/Upto

Select the Company Code range from the LOV.

Office From/Upto

Select the Office Code range from the LOV. Office refers to the branch or division office.

Department Code From/Upto

Select the Department Code range from the LOV. Department refers to the class of business.

Force Company/Office/Department

Select any or a combination of these checkboxes to force the login Company/Office/Department details to be default values during accounts processing.



Main Account Code

Select the Main Account Code from the LOV. Its description is defaulted in the adjacent display field.

Sub Account Code

Select the Sub Account Code from the LOV. Its description is defaulted in the adjacent display field.



Company

Select the Company Code from the LOV. Its description is defaulted in the adjacent display field.



Office

Select the Division Code from the LOV. Its description is defaulted in the adjacent display field.



Department Code

Select the Department Code from the LOV. Its description is defaulted in the adjacent display field.

Analysis Code 1 and 2

Analysis Code adds a level of filter so that the reports generated through the reports module has a broad set of uniform keywords. The user is able to add multiple filters by stating the classification, sub classification. The user is able to select the analysis code from the LOV or manually enter the same.

Activity Code 1 and 2

Analysis Code is similar to the remarks field. In this field, the user is able to add more information that is in line with the current field entry operations.

Effective From/To Date

Enter or select the 'From' and 'To' dates from the Calendar help. These dates specify the validity period.

CUSTOMER ACCOUNT SETUP


Customer Account Setup helps users to map a range of customers along with various parameters to a main and sub account. The main account is the accounting head under which all the customer general ledger entries are placed.

For the sake of better understanding, Customer Account Setup screen is split into two. The first half of the Customer Account Setup screen (before the Force checkboxes) is the Customer area. In this area, the user enters the Customer category range (Example: General Customer, Credit Customer etc.) and then enters the ranges for various parameters (Example: Company, Office, Department etc). This would help in establishing the customer type operation.

The next step is to enter account related details. This is carried out in the second half of the Customer Account Setup screen (after the Force checkboxes).

This, along with the premium and miscellaneous field entries, ensures that the accounts are processed effectively within the accounts module.

Click 'Customer Account Setup' menu to view the following screen.



The screenshot shows the 'Customer Account Setup' window. It is divided into two main sections. The left section contains fields for 'Customer catg from' (RL), 'Company From' (001), 'Office From' (100), 'Department From' (0), 'Business From' (1), 'Instrument Type From' (00), 'A/C Doc Type From' (001), and checkboxes for 'Force Company', 'Force Office', and 'Force Department'. The right section contains 'Upto' fields for the same categories: 'RL' (Reinsurance Co - Local), '001' (INSURANCE CO LTD), '100', '5' (Inward - Fac Foreign), 'RFD' (Refund Adjustments), and '001' (Premium Account). Below these are 'Main Account' (1206008), 'Sub Account' (R10000001), 'Company' (001), 'Office' (100), and 'Department' (10). At the bottom, there are fields for 'Analysis code1', 'Analysis code2', 'Activity code1', 'Activity code2', 'Effective From Date' (01/01/2012), and 'Effective To Date' (31/12/2099).

Fig. 117 – Customer Account Setup

Customer Category From/Upto

Customers are categorized such as General, Private Companies, Firms, and Individual. Select the customer category code range from the LOV.

Company From/Upto

Select the Company Code range from the LOV.

Office From/Upto

Select the Office Code range from the LOV. Office refers to the branch or division office.

Department Code From/Upto

Select the Department Code range from the LOV. Department refers to the class of business.



Business From/Upto

Select the Business range from the LOV. Business refers to the source of business such as direct without co-insurance, direct with co-insurance, treaty



Instrument Type From/Upto

Select the instrument type range from the LOV. Instrument type refers to financial instruments such as demand draft, bank guarantee.



For Cash Customers, select the instrument type as 'OTHERS' from the LOV while defining this setup and for Credit Customers select the instrument type as '00'.



Account Type From/Upto

Select the Account Type range from the LOV There are different account types such as premium account, incentive account based on the transaction.

Force Company/Division/Department

Select any or a combination of these checkboxes to force the login Company/Office/Department details to be default values during accounts processing.



Main Account Code

Select the Main Account Code from the LOV. Its description is defaulted in the adjacent display field.

Sub Account Code

Select the Sub Account Code from the LOV. Its description is defaulted in the adjacent display field.



User needs to enter the sub account code. But during transaction entry, the actual sub account entered is used in the accounting entry.



Company Code

Select the Company Code from the LOV. Its description is defaulted in the adjacent display field.



Office

Select the Office Code from the LOV. Its description is defaulted in the adjacent display field.



Department Code

Select the Department Code from the LOV. Its description is defaulted in the adjacent display field.

Analysis Code 1 and 2

Analysis Code adds a level of filter so that the reports generated through the reports module has a broad set of uniform keywords. The user is able to add multiple filters such as stating the classification, sub classification, and is able to select the analysis code from the LOV or manually enter the same.

Activity Code 1 and 2

Analysis Code is similar to the remarks field. In this field, the user is able to add more information that is in line with the current field entry operations.

Effective 'From' and 'To' Date

Enter or select the 'From' and 'To' dates from the Calendar help. These dates specify the validity period.

On completing the field entries, click 'Save' button to save the details.

CLAIMS ACCOUNT SETUP


Claims Account Setup helps users to map the claim types that occur while processing a claim to a main and sub account based on the range of parameters selected (Example: Office, Department etc). The main account is the accounting head under which all the claims general ledger entries would be placed.

For the sake of better understanding, Claims Account Setup screen is split into two. The first half of the Claims Account Setup screen (before the Force checkboxes) is the claims detail area. In this area, the user has to select the claim type; product and the provision code and enter the Company, Office, and Department details. This would help avoid further mapping on a particular range of data.

The next step is to enter account related details. This is carried out in the second half of the Claim Account Setup screen (after the Force checkboxes).

This ensures that the account type, with all its parameters complete, is entered into accounts.

Click 'Claims Account Setup' menu to view the following screen.



Claims Account Setup Master

Account Type

Company Code From To Branch Code From To

Department Code From To Business Source From To

Claim Type From To Document Code From To

Product Code From To Section Code From To

Cover Code From To Provision Code From To

Provision Ind From To Source Type From To

Force Company ☒ Force Division ☒ Force Department ☒

Main Account Code

Sub Account Code

Company Code

Branch Code

Department Code

Analysis Code 1

Analysis Code 2

Activity Code 1

Activity Code 2

Effective From Date Effective To Date

Fig. 118 – Claims Account Setup



Account Type

Select the account type from the LOV.



Company Code From/To

Select the Company Code range from the LOV.

Branch Code From/To

Select the Branch Code range from the LOV.

Department Code From/To

Select the Department Code range from the LOV. Department refers to the class of business.

Business Source From/To

Select the Business Source range from the LOV. The available options are Source of business such as direct without co-insurance, direct with co-insurance and treaty.

Claim Type

Select the Claim Type from the drop down list. The available options in Claim Type are Own Damage, Third Party/Motor Accident Claims Tribunal and Others.

Document Code From/To

Select the Document code range from the LOV .Document Code is a sub classification of the document type. For example, Claim is either third party claim or own damage.

Product Code From/To

Select the Product Code from the LOV.

Cover Code From/To

Select the Cover Code range from the LOV.

Provision Code From/To

Select the Provision Code range from the LOV.A provision is any amount held in balance to meet the cost of a particular liability or loss, which is likely or certain to be incurred, but it is uncertain as to the exact amount and/or date on which it will arise. An example is a provision for bad debt.

Provision Indicator From/To

Select provision indicator range from the LOV. Provision Indicator is a Loss Estimation or Expense Estimation.

Source Type From/To

Select the Source Type range from the LOV. Source Type refers to the source through which the business is generated and includes direct, agent or broker.

Force Company/Division/Department

Select any or a combination of these checkboxes to force the login Company/Office/Department details to be default values during accounts processing.



Main Account Code

Select the Main Account Code from the LOV. Its description is defaulted in the adjacent display field.

Sub Account Code

Select the Sub Account Code from the LOV. Its description is defaulted in the adjacent display field.

Company

Select the Company Code from the LOV. Its description is defaulted in the adjacent display field.

Division Code

Select the Division Code from the LOV. Its description is defaulted in the adjacent display field.

Department Code

Select the Department Code from the LOV. Its description is defaulted in the adjacent display field.

Analysis Code 1 and 2

Analysis Code adds a level of filter so that the reports generated through the reports module has a broad set of uniform keywords. The user is able to add multiple filters by stating the classification, sub classification. The user is able to select the analysis code from the LOV or manually enter the same.

Activity Code 1 and 2

Analysis Code is similar to the remarks field. In this field, the user is able to add more information that is in line with the current field entry operations.

Effective 'From' and 'To' Date

Enter or select the 'From' and 'To' dates from the Calendar help. These dates specify the validity period.

On completing the field entries, click 'Save' button to save the details.

RI ACCOUNT SETUP

RI Premium Accounts Setup

Reinsurance Premium Accounts Set up helps to map the premium collection details for a product, covered by a range of branches (along with other parameters) to a main and sub account. Click 'RI Premium Accounts Setup' from the menu.

The system displays the screen as shown below.

INSURANCE CO LTD

RI Premium Account Setup

Company From*	001	INSURANCE CO LTD	To*	001	INSURANCE CO LTD
Division From*	0		To*	////	
Department From*	0		To*	////	
Business Type From*	13	FAC Out Local	To*	13	FAC Out Local
Product Code From*	1001	Motor Commercial	To*	1013	Comesa Card
Peril Class From*	0		To*	////	
Document Type From*	0		To*	////	

Force Company ☒ Force Office ☒ Force Department ☒

Company Code*	001	INSURANCE CO LTD
Division Code*	100	Head Office
Department Code*	10	Motor
Main Account*	3201001	PREMIUM CEDED FAC OUT
Sub Account*	3201001	PREMIUM CEDED FAC OUT - MOTOR
Analysis Code1*		
Analysis Code2*		
Activity Code1*		
Activity Code2*		

Effective From Date: 01/01/2000 Effective To Date: 31/12/2099

Fig. 119 – RI Premium Account Setup

Company From / To

Enter or select the company's 'From and To' code range from the respective LOV. The description of the company code is automatically displayed in the adjacent fields. The company codes displayed in the LOV are set up in the common codes master-company master. The premium account set up is done for the company range selected here.



The Company From and Company To values must be same.

Division From / To

Enter or select the divisions from and to code range from the respective LOV. The description of the division code is automatically displayed in the adjacent fields. The division codes displayed in the LOV are set up in common codes master-division master, which is fetched depending on the division selected. The premium account set up is done for the division code range selected here.



To division code value has to be greater than 'From Division Code' value.

Department From / To

Enter or select the department's 'From and To' code range from the respective LOV. The description of the department code is automatically displayed in the adjacent fields. The department codes displayed in the LOV are set up in common codes master-department master which is fetched depending on the company and division selected. The premium account set up is done for the department code range selected here.



To department code value has to be greater than From department code value.

Business Type From / To

Enter or select the business type From and To codes range from the respective LOV. The values displayed in LOV are parameterized. The description of the business type code is automatically displayed in the adjacent fields.



To business type code value has to be greater than from business type code value.

Product Code From / To

Enter or select the product code From and To range from the respective LOV. The respective descriptions of the product codes are automatically displayed in the adjacent fields. The product codes displayed in the LOV are set up in product master.



To product code value has to be greater than from product code value.

Peril Class From / To

Enter or select the peril class From and To code range from the respective LOV. The description of the peril class code is automatically displayed in the adjacent fields. The peril class codes in the LOV are set up in peril class master and is fetched depending upon the product codes selected.



To peril class code value has to be greater than from peril class code value.

Document Type From/To

Enter or select the document From and To code range from the respective LOV. The description of the document type code is automatically displayed in the adjacent fields. The values displayed in LOV are parameterized.

Force Company

Check this flag if the reinsurance facultative premium accounting has to be done against a transaction company code. If this option is not checked, the reinsurance premium accounting is done against the company code specified in this master.

Force Office

Check this flag if the reinsurance facultative premium accounting has to be done against transaction office code. If this option is not checked, the reinsurance premium accounting is done against the office code specified in this master.

Force Department

Check this flag if the reinsurance facultative premium accounting has to be done against transaction department code. If this option is not checked, the reinsurance premium accounting is done against the department code specified in this master.

Company Code

Enter or select the company code from the LOV. The description for the code selected is automatically displayed in the adjacent field. The values displayed in the LOV are set up in common codes master – company master.



This field becomes mandatory if the Force Company option is not checked.

Division Code

Enter or select the division code from the LOV. The description of the code selected is automatically displayed in the adjacent field. The values displayed in the LOV are set up in common codes master-division master.



This field becomes mandatory if the Force Division option is not checked.

Department Code

Enter or select the department code from the LOV. The description of the department code is automatically displayed in the adjacent field. The values displayed in the LOV are set up in common codes master-department master.



This field becomes mandatory if the Force Department option is not checked.



Main Account

Enter or select the main account code from the LOV. The description of the code selected is automatically displayed in the adjacent field. The values displayed in LOV are set in Main account master set up.

Sub Account

Enter or select the sub account code from the LOV. The description of the code selected is automatically displayed in the adjacent field. The sub accounts displayed in the LOV depends on the Main account selected. This account is referred while posting accounting entries. The values displayed in LOV are set in Sub account master set up.

Analysis Code 1 / Analysis Code 2

Enter or select the analysis codes from the respective LOV. The description of the codes selected is automatically displayed in the respective adjacent fields. The values displayed in LOV are set in analysis master set up. These details are captured for the purpose of reporting.

Activity Code 1 / Activity Code 2

Enter or select the activity codes from the respective LOV. The description of the codes selected is automatically displayed in the respective adjacent fields. The values displayed in LOV are set in activity master set up. These details are captured for the purpose of reporting.



Effective From / To Date

Enter or select the effective from and to dates using calendar template in the respective fields. This premium set up is valid only for the period specified here.

RI Miscellaneous Account Setup

Miscellaneous Account Set up helps to map various taxes, charges and commissions that occur during proportional treaty allocation.

Facultative allocation to main and sub account is done on the range of parameter selected (miscellaneous type, range of business type, product code, DS type, miscellaneous code, company, division, department etc.) in this set up.

Click the 'RI Miscellaneous Account Setup' from the menu. The system displays the screen as shown below.

RI Miscellaneous Account Setup

Type*	018	FAC Commission	To*	////	
Business Type*	0		To*	////	
Document Type From*	0		To*	1013	
Product From*	1001		To*	////	
Code From*	0		To*	////	
Company From*	0		To*	////	
Division From*	0		To*	////	
Department From*	0		To*	////	
PC Code From*	0		To*	////	

Force Company ☒ Force Division ☒ Force Department ☒

Company Code*	001	INSURANCE CO LTD
Division Code*	100	Head Office
Department Code*	10	Motor
Main Account Code*	4202001	FAC INWARDS COMMISSION
Sub Account Code*	4202001	FAC INWARDS COMMISSION - MOTOR
Analysis Code 1*		
Analysis Code 2*		
Activity Code 1*		
Activity Code 2*		
Effective From Date	01/01/2000	Effective To Date 31/12/2099

Fig. 120 – RI Miscellaneous Account Setup



Type

Enter or select the miscellaneous type from the LOV. The description of the miscellaneous type code is automatically displayed in the adjacent field. The values displayed in LOV are parameterized.

Business Type From/To

Enter or select the business type from and to code range the respective LOV. The description of the business type code is automatically displayed in the adjacent field. The values displayed in LOV are parameterized.



To business type code value has to be greater than from business type code value.

Document Type From/To

Enter or select the document setup type from the LOV. The description of the DS code is automatically displayed in the adjacent field. The values displayed in LOV are parameterized.

Product From/To

Enter or select the product code from and to range from the respective LOV. The respective descriptions of the product codes are automatically displayed in the adjacent fields. The product codes displayed in the LOV are set up in the product master.



To product code value has to be greater than from the product code value.

Code From/To

Enter or select the code from and to range from the respective LOV, the description of the codes is displayed in the adjacent fields. The code values in the LOV depend on the miscellaneous type selected. The values displayed in LOV are codified.



To code value has to be greater than from the code value.

Company From/To

Enter or select the company from and to code range from the respective LOV. The description of

the company code is automatically displayed in the adjacent fields. The company codes displayed in the LOV are set up in the common codes master-company master. The premium account set up is done for the company range selected here.



'To' company code value and 'From' the company code values have to be same.

Division From/To

Enter or select the division from and to code range from the respective LOV. The description of the division code is automatically displayed in the adjacent fields. The division codes displayed in the LOV are set up in common codes master-division master, which is fetched depending on the division selected. The premium account set up is done for the division code range selected here.



'To' division code value has to be greater than 'From' the division code value.

Department From/To

Enter or select the department from and to code range from the respective LOV. The description of the department code is automatically displayed in the adjacent fields. The department codes displayed in the LOV are set up in common codes master-department master that is fetched depending on the company and division selected. The premium account set up is done for the department code range selected here.



'To' department code value has to be greater than 'From' department code value.

PC Code From

Enter or select from the LOV, the peril class code. The description of the peril class codes selected is automatically displayed in the adjacent field.

Force Company

Check this flag if the reinsurance facultative premium accounting has to be done against transaction company code. If this option is not checked, the reinsurance premium accounting is done against the company code specified in this master.

Force Division

Check this flag if the reinsurance facultative premium accounting has to be done against transaction division code. If this option is not checked, the reinsurance premium accounting is done against the office code specified in this master.

Force Department

Check this flag if the reinsurance facultative premium accounting has to be done against transaction department code. If this option is not checked, the reinsurance premium accounting is done against the department code specified in this master.

Company Code

Enter or select the company code from the LOV. The description of the code selected is automatically displayed in the adjacent field. The values displayed in the LOV are set up in common codes master – company master.



This field becomes mandatory if the Force Company option is not checked.

Division Code

Enter or select the division code from the LOV. The description of the code selected is automatically displayed in the adjacent field. The values displayed in the LOV are set up in common codes master-division master.



This field becomes mandatory if the Force Division option is not checked.

Department Code

Enter or select the department code from the LOV. The description of the code selected is automatically displayed in the adjacent field. The values displayed in the LOV are set up in common codes master-department master.



This field becomes mandatory if the Force Department option is not checked.



Main Account Code

Enter or select the main account code from the LOV. The description of the code selected is automatically displayed in the adjacent field. The values displayed in LOV are set in Main account master set up.

Sub Account Code

Enter or select the sub account code from the LOV. The description of the code selected is automatically displayed in the adjacent field. The sub accounts displayed in the LOV depends on the Main account selected. This account is referred while posting accounting entries. The values displayed in LOV are set in Sub account master set up.

Analysis Code 1 / Analysis Code 2

Enter or select the analysis codes from the respective LOV. The description of the codes selected is automatically displayed in the respective adjacent fields. The values displayed in LOV are set in analysis master set up. These details are captured for the purpose of reporting.

Activity Code 1 / Activity Code 2

Enter or select the activity codes from the respective LOV. The description of the codes selected is automatically displayed in the respective adjacent fields. The values displayed in LOV are set in activity master set up. These details are captured for the purpose of reporting.

Effective From / To Date

Enter or select the effective from and to dates using calendar template in the respective fields. This premium set up is valid only for the period specified here.

On completing the field entries, click 'save' icon to save the details.

RI Claims Account Setup

Reinsurance Claims Account Setup helps the user to pick the main account and sub account by mapping the transaction company, division, department, business type, account type, product and peril class for generating the accounting entries.

Click 'RI Claims Account Setup' from the menu. The system displays the screen as shown below:

RI-Claims Account Setup		
Business Type From*	7	FAC Out Foreign
Document Type From*	4	Claims
Company From*	0	
Division From*	0	
Department From*	0	
Product Code From*	1001	Motor Commercial
Peril Class From*	0	
Revenue Type	Foreign	
Force Company ☒ Force Division ☒ Force Department ☒		
Company Code*	001	INSURANCE CO LTD
Division Code*	100	Head Office
Department Code*	10	Motor
Main Account Code*	4102001	CLAIMS RECOVERY- FAC OUTWARD
Sub Account Code*	4102001	CLAIMS RECOVERY- FAC OUTWARD - MOTOR
Analysis Code1*		
Analysis Code2*		
Activity Code1*		
Activity Code2*		
Effective From	01/01/2000	Effective To 31/12/2099

Fig. 121 – RI Claims Account Setup

Business Type From/To

Enter or select the business type from and to codes range from the respective LOV. The values displayed in LOV are parameterized. The description of the business type code is automatically displayed in the adjacent fields.



To business type code value has to be greater than from business type code value.

Document Type From

Enter or select the document set up type from the LOV. The description of the document type code is automatically displayed in the adjacent fields. The values displayed in LOV are parameterized.

Account Type

Enter or select the account type from the LOV.

Company From/To

Enter or select the company from and to code range from the respective LOV. The description of the company code is automatically displayed in the adjacent fields. The company codes displayed in the LOV are set up in the common codes master-company master. The premium account set up is done for the company range selected here.



'To company code value' and 'From company code' value has to be same.

Division From/To

Enter or select the division from and to code range from the respective LOV. The description of the division code is automatically displayed in the adjacent fields. The division codes displayed in the LOV are set up in common codes master-division master, which is fetched depending on the division selected. The premium account set up is done for the division code range selected here.



'To division code' value has to be greater than 'From division code' value.

Department From/To

Enter or select the department from and to code range from the respective LOV. The description of the department code is automatically displayed in the adjacent fields. The department codes displayed in the LOV are set up in common codes master-department master which is fetched depending on the company and division selected. The premium account set up is done for the

department code range selected here.



'To department code' value has to be greater than 'From department code value'.

Product Code From/To

Enter or select the product code from and to range from the respective LOV. The respective description of the product codes is automatically displayed in the adjacent fields. The product codes displayed in the LOV are set up in product master.



TO product code value has to be greater than from product code value.

Peril Class From/To

Enter or select the peril class from and to code range from the respective LOV. The description of the peril class code is automatically displayed in the adjacent fields. The peril class codes in the LOV are set up in peril class master and is fetched depending upon the product codes selected.



TO peril class code value has to be greater than from peril class code value.

Revenue Type

Select the revenue type from the drop down menu, the options available are:

- ☐ Local
- ☐ Foreign

Force Company

Check this flag if the reinsurance facultative premium accounting has to be done against transaction company code. If this option is not checked, the reinsurance premium accounting is done against the company code specified in this master.

Force Division

Check this flag if the reinsurance facultative premium accounting has to be done against transaction division code. If this option is not checked, the reinsurance premium accounting is done against the office code specified in this master.

Force Department

Check this flag if the reinsurance facultative premium accounting has to be done against transaction department code. If this option is not checked, the reinsurance premium accounting is done against the department code specified in this master.

Company Code

Enter or select the company code from the LOV. The description of the code selected is automatically displayed in the adjacent field. The values displayed in the LOV are set up in common codes master – company master.



This field becomes mandatory if the Force Company option is not checked.

Branch Code

Enter or select the branch code from the LOV. The description of the code selected is automatically displayed in the adjacent field. The values displayed in the LOV are set up in common codes master-division master.



This field becomes mandatory if the Force Division option is not checked.

Department Code

Enter or select the department code from the LOV. The description of the code selected is automatically displayed in the adjacent field. The values displayed in the LOV are set up in

common codes master-department master.



This field becomes mandatory if the Force Department option is not checked.



Main Account Code

Enter or select the main account code from the LOV. The description of the code selected is automatically displayed in the adjacent field. The values displayed in LOV are set in Main account master set up.

Sub Account Code

Enter or select the sub account code from the LOV. The description of the code selected is automatically displayed in the adjacent field. The sub accounts displayed in the LOV depends on the Main account selected. This account is referred while posting accounting entries. The values displayed in LOV are set in Sub account master set up.

Analysis Code 1 / Analysis Code 2

Enter or select the analysis codes from the respective LOV. The description of the codes selected is automatically displayed in the respective adjacent fields. The values displayed in LOV are set in analysis master set up. These details are captured for the purpose of reporting.

Activity Code 1 / Activity Code 2

Enter or select the activity codes from the respective LOV. The description of the codes selected is automatically displayed in the respective adjacent fields. The values displayed in LOV are set in activity master set up. These details are captured for the purpose of reporting.

Effective From/To Date

Enter or select the effective from and to dates using calendar template in the respective fields. This premium set up is valid only for the period specified here.

On completing the field entries, click 'save' icon to save the details.

Treaty Account Set Up

Treaty Account Set Up is used to define the account codes that have to be used for various accounts involved in a treaty like premium ceded, claims paid, commission etc for a combination of treaty transaction type, company, division, department, treaty code, treaty type, and peril class and so on

RI Treaty Account Setup

Click 'Treaty Account Set-up' from the menu. The system displays the screen as shown below.

RI - Treaty Account Setup			
Treaty Transaction Type	Outward Treaty Accounting		
Company From*	001	INSURANCE CO LTD	
Division From*	0		
Department From*	0		
Treaty Code From*	FIRE/2012	Fire Treaty For 2012	
Treaty Bus Type From*	0		
Treaty Type From*	0		
Treaty Type Code From*	0		
Peril Class From*	0		
Ceding Basis	On Gross Rate (Total Premium)		
Commission From*	0		
Account Type*	01	Premium Ceded	
To*	001	INSURANCE CO LTD	
To*	////////		
To*	////////		
To*	FIRE/2012	Fire Treaty For 2012	
To*	////////		
To*	////////		
To*	////////		
To*	////////		
Revenue Type	Local		
To*	////////		
Force Company	☒	Force Division	☒
Force Department	☒		
Company Code*	001	INSURANCE CO LTD	
Division Code*	100	Head Office	
Department Code*	15		
Main Account Code*	03011004		
Sub Account Code*	1000		
Analysis Code1*			
Analysis Code2*			
Activity Code1*			
Activity Code2*			
Effective From	01/01/2000	Effective To	31/12/2099

Fig. 122 – RI Treaty Account Setup



Treaty Transaction Type

Enter or select the treaty transaction code from the drop down. The options available are:

- ☐ Outward Treaty Accounting
- ☐ Inward Treaty Accounting
- ☐ Outward Non-Proportional Treaty Accounting
- ☐ FAC Accounting
- ☐ FAC XOL Accounting



Account Type

Enter or select the account type from the LOV.



Company From / To

Enter or select the company From and To code range from the respective LOV. The description of the company code is automatically displayed in the adjacent fields. The company codes displayed in the LOV are set up in the common codes master-company master. The premium account set up is done for the company range selected here.



'To company code' value and 'From company code' value has to be same.



Division From/To

Enter or select the division From and To code range from the respective LOV. The description of the division code is automatically displayed in the adjacent fields. The division codes displayed in the LOV are set up in common codes master-division master, which is fetched depending on the division selected. The premium account set up is done for the division code range selected here.



To division code value has to be greater than From division code value.



Department From/To

Enter or select the department From and To code range from the respective LOV. The description of the department code is automatically displayed in the adjacent fields. The department codes displayed in the LOV are set up in common codes master-department master which is fetched depending on the company and division selected. The premium account set up is done for the department code range selected here.



To department code value has to be greater than the From Department code value.



Treaty Code From/To

Enter or select the treaty code From and To range from the respective LOV. The respective description of the treaty codes is automatically displayed in the adjacent fields.



To treaty code value has to be greater than the From Treaty code value.



Treaty Business Type From/To

Enter or select the treaty business type From and To code range from the respective LOV. The respective description of the treaty business types is automatically displayed in the adjacent fields. The values displayed in LOV are set in Treaty type master.



To treaty business type value has to be greater than the From treaty type value.



Treaty Type From/To

Enter or select the treaty type From and To code range from the respective LOV. The respective description of the treaty types is automatically displayed in the adjacent fields. The values displayed in LOV are set in Treaty type master.



To treaty type value has to be greater than the From Treaty type value.



Treaty Type Code From / To

Enter or select the treaty type code From and To range from the respective LOV. The respective description of the treaty type codes is automatically displayed in the adjacent fields. The values displayed in LOV are set in Treaty type code master.



To treaty type code value has to be greater than the From Treaty type code value.



Peril Class From/To

Enter or select the peril class From and To code range from the respective LOV. The description of the peril class of the peril class code is automatically displayed in the adjacent fields. The peril class codes in the LOV are set in peril class master.



Ceding Basis

Select the ceding basis from the drop down menu, the options available are:

- ☐ On Gross Rate (Total Premium)
- ☐ On Net Rate (Total Premium – Agency Commission)



Revenue Type

Select the revenue type from the drop down menu, the options available are:

- ☐ Local
- ☐ Foreign



Commission From/To

Enter or select the commission from and to code range from the respective LOV. The respective description of the commission codes is automatically displayed in the adjacent fields. The values displayed in LOV are codified.



Force Company

Check this flag if the reinsurance facultative premium accounting has to be done against transaction company code. If this option is not checked, the reinsurance premium accounting is done against the company code specified in this master.



Force Division

Check this flag if the reinsurance facultative premium accounting has to be done against transaction division code. If this option is not checked, the reinsurance premium accounting is done against the office code specified in this master.



Force Department

Check this flag if the reinsurance facultative premium accounting has to be done against transaction department code. If this option is not checked, the reinsurance premium accounting is done against the department code specified in this master.

Company Code

Enter or select the company code from the LOV. The description of the code selected is automatically displayed in the adjacent field. The values displayed in the LOV are set up in common codes master – company master.



This field becomes mandatory if the Force Company option is not checked.

Division Code

Enter or select the division code from the LOV. The description of the code selected is automatically displayed in the adjacent field. The values displayed in the LOV are set up in common codes master-division master.



This field becomes mandatory if the Force Division option is not checked.

Department Code

Enter or select the department code from the LOV. The description of the code selected is automatically displayed in the adjacent field. The values displayed in the LOV are set up in common codes master-department master.



This field becomes mandatory if the Force Department option is not checked.

PC Code From

Enter or select from the LOV, the peril class code. The description of the peril class codes selected is automatically displayed in the adjacent field.



Main Account Code

Enter or select the main account code from the LOV. The description of the code selected is automatically displayed in the adjacent field. The values displayed in LOV are set in Main account master set up.

Sub Account Code

Enter or select the sub account code from the LOV. The description of the code selected is automatically displayed in the adjacent field. The sub accounts displayed in the LOV depends on the Main account selected. This account is referred while posting accounting entries. The values displayed in LOV are set in Sub account master set up.

Analysis Code 1 / Analysis Code 2

Enter or select the analysis codes from the respective LOV. The description of the codes selected is automatically displayed in the respective adjacent fields. The values displayed in LOV are set in analysis master set up. These details are captured for the purpose of reporting.

Activity Code 1 / Activity Code 2

Enter or select the activity codes from the respective LOV. The description of the codes selected is automatically displayed in the respective adjacent fields. The values displayed in LOV are set in activity master set up. These details are captured for the purpose of reporting.

Effective From/To Date

Enter or select the effective from and to dates using calendar template in the respective fields. This premium set up is valid only for the period specified here.

On completing the field entries, click 'save' icon to save the details.

CLAIMS OSLR ACCOUNT SETUP

OSLR (Outstanding Loss reserve) account setup is used to create accounting entries on approval of OSLR process. OSLR process enables the calculation of OSLR reserve amount and to generate accounting entries for the same. The OSLR Account Setup Screen is displayed as follows:

Sample Screen as shown below:

Claims OSLR / IBNR Account Setup

Account Setup For: IBNR OSLR/IBNR Type: XOL

Company From: 001 INSURANCE CO LTD

Division From: 10 Division 10

Department From: 0

Class Code From: 0

Business Type From: 0

Document Code From: 0

Product Code From: 0

Section Code From: 0

Peril Class Code From: 0

Cover Code From: 0

Source Type From: 0

Force Company YN: ☒ Force Division YN: ☒ Force Department YN: ☒

Debit

Main A/C Code: 1600

Sub A/C Code:

Company Code: 001 INSURANCE CO LTD

Division Code: 10 Division 10

Department Code: 10 Motor

Analysis Code 1:

Analysis Code 2:

Activity Code 1:

Activity Code 2:

Credit

Main Account: 1500

Sub Account:

Company Code: 001 INSURANCE CO LTD

Division Code: 10 Division 10

Department Code: 10 Motor

Analysis Code 1:

Analysis Code 2:

Activity Code 1:

Activity Code 2:

Effective From: 01/01/2000 Effective To: 01/01/2020

Fig. 123 – Claims OSLR/IBNR Account Setup

Enter the field values as indicated below.



Account Setup For

Select from the drop-down list, the option for which account setup needs to be defined. The options available are:

- ☐ IBNR
- ☐ OSLR



IBNR Type

Select the relevant option from the drop-down list, if the 'Account Setup For' is selected as IBNR. The following are the options available:

- ☐ Claims
- ☐ FAC
- ☐ Treaty
- ☐ XOL



Company From/To

Select the Company Code range from the LOV.

Division From/To

Select the Division Code range from the LOV.



Department Code From/To

Department refers to the class of business. Select the Department Code range from the LOV.



Class Code From/To

The class of business corresponds to the category of the product, for example, Fire, Engineering, and Motor and so on. Select the Business Source range from the LOV.



Business Type From/To

The business type can be direct without co-insurance, treaty and so on. Select the Business Type range from the LOV.



Product Code From/To

Select the Product Code range from the LOV. The description of the products codes selected is automatically displayed.



Section Code From / To

Select the section code range from the LOV. The description of the section codes selected is automatically displayed.



Peril Class Code From/To

Select the peril class code range from the LOV. The description of the peril class code selected is automatically displayed.



Cover Code From/To

Select the cover code range from the LOV.



Source Type From/To

Enter the Source Type range from the LOV.



Main Account Code

Select the Main Account Code from the LOV. Its description can be viewed in the adjacent display box.

Sub Account Code

Select the Sub Account Code from the LOV. Its description can be viewed in the adjacent display box.

Company Code

Select the Company Code from the LOV. Its description can be viewed in the adjacent display box.

Division Code

Select the Division Code from the LOV. Its description can be viewed in the adjacent display box.

Department Code

Select the Department Code from the LOV. Its description can be viewed in the adjacent display box.

Analysis Code 1 and 2

Analysis Code adds a level of filter so that the reports generated through the reports module has a broad set of uniform keywords. User is able to add multiple filters by stating the classification, sub classification etc. User is able to select the analysis code from the LOV or manually enter the same.

Example: User can enter 'Engineering' in Analysis Code 1 and 'Workmen Compensation' in Analysis Code 2.

Activity Code 1 and 2

Analysis Code is similar to the remarks field. In this field, add more information that is in line with the current field entry operations.



Effective From and To Date

Enter or select the From and To dates from the Application Calendar which can be accessed using the LOV key. These dates specify the validity period.

UPR/IBNR ACCOUNT SETUP

Use this setup to define following types of account setup:

☐ Unearned Premium Reserve

☐ IBNR

UNEARNED PREMIUM RESERVE (UPR)

The Unearned Premium Reserve (UPR) Account Setup helps users to set up the various codes for the UPR Account. The main account is the accounting head under which all the UPR general ledger entries would be placed.

Unearned premium reserve is for the portion of the premium that has not been earned, since the customer may pay the premium over a period of time. In such cases, when a policy is taken and the premium is booked, the entire premium is not earned at the same time because the policy spans for an entire year or may be across many years. The Premium for the completed span period is calculated as the earned premium. The remaining premium is said to be Unearned, as the policy coverage is not over for that period. The unearned premium is calculated based on the methods namely 1/365 and 1/24 methods which are fixed.

INCURRED BUT NOT REPORTED (IBNR).

IBNR reflects the total amount owed by the insurer to all valid claimants who have had a covered loss but have not yet reported it. Since the insurer knows neither how many of these losses (the frequency) have occurred, nor the severity of each loss, IBNR is necessarily an estimate. The quality of this estimation is often used as a tool in assessing the financial accounting skills of a given insurer. Insurers track IBNR by policy periods (when the policy inception), along with other categorizations

Select 'UPR/IBNR Account Setup' menu to view the following screen:

UPR / IBNR / Surplus Account Setup			
Account Setup For		UPR	
Company From*	001	INSURANCE CO LTD	To*
Branch From*	100	Head Office	To*
Department From*	15		To*
Business Class From*	20	Fire	To*
Product From*	2002	Fire & Allied Perils with LOP	To*
Business Type From*	1	Direct without coinsurance	To*
UPR/IBNR Type From*	UCH	Underwriting Charges	To*
Force Company Y/N	☐	Force Division Y/N	☐
Force Department Y/N	☐		
Debit		Credit	
Main A/C Code*	2011016	Main Account*	2011016
Sub A/C Code*		Sub Account*	
Company Code*	001	INSURANCE CO LTD	Company Code*
Branch Code*	100	Head Office	Branch Code*
Department Code*	15		Department Code*
Analysis Code 1			Analysis Code 1
Analysis Code 2			Analysis Code 2
Activity Code 1			Activity Code 1
Activity Code 2			Activity Code 2

Fig. 124 – UPR/IBNR Account Setup

Enter the field values as indicated below.

Account Setup For

Select 'Surplus Distribution' from the drop-down list.



Company Code From/To

Select the Company Code range from the LOV. The description of the selected company is automatically displayed.



Branch From/To

Select or enter from the LOV, branch 'From and To' codes of the location. The description of the location is automatically displayed.



Department Code From/To

Department refers to the class of business. Select the Department Code range from the LOV.



Business Class From/To

The class of business corresponds to the category of the product, for example, Fire, Engineering, and Motor and so on. Select the Business Source range from the LOV.



Product Code From/To

Select the Product Code from the LOV. The description of the product code is automatically displayed.



Business Type From/To

The business type can be direct without co-insurance, treaty and so on. Select the Business Type range from the LOV.

Force Company/Division/Department

Select any or a combination of these checkboxes to force the login Company/Office/Department details to be default values during accounts processing.



Main Account Code

Select the Main Account Code from the LOV. Its description can be viewed in the adjacent display box.

Sub Account Code

Select the Sub Account Code from the LOV. Its description can be viewed in the adjacent display box.



Company Code

Select the Company Code from the LOV. Its description can be viewed in the adjacent display box.



Branch Code

Select the Branch Code from the LOV. Its description can be viewed in the adjacent display box.



Department Code

Select the Department Code from the LOV. Its description can be viewed in the adjacent display box.

Analysis Code 1 and 2

Analysis Code adds a level of filter so that the reports generated through the reports module has a broad set of uniform keywords. User can add multiple filters by stating the classification, sub classification etc. User can select the analysis code from the LOV or manually enter the same.

Example: User can enter 'Engineering' in Analysis Code 1 and 'Workmen Compensation' in Analysis Code 2.

Activity Code 1 and 2

Analysis Code is similar to the remarks field. In this field, user can add more information that is in line with the current field entry operations.



Effective From and To Date

Enter or select the From and To dates from the Application Calendar which can be accessed using the LOV key. These dates specify the validity period.

ACCOUNT DOCUMENT FLEXI FIELD SETUP

This Setup enables the user to provide additional flex fields which is utilized for customer specific requirement. The generated accounting entries such as Policy number, claim number, product code are stored in a table. Majority of the transaction reference data are mapped to these static fields in the table.

The Account Document Flexi Field Setup contains the following sub menus:

- ☐ Config
- ☐ Mapping

Config

This screen enables the user to create map-able fields using the interface provided called as Account Entry Flex config. Only the implementer configures the flex fields. The map-able fields created in this configuration screen appears in the Account Entry Flex field mapping interface which enables the user to choose the corresponding data for that flex field.

The system displays the screen as shown below:

The screenshot shows a web-based configuration interface. The 'Header' section contains three input fields: 'Code' with the value '1', 'Description' with the value 'Policy No', and 'Bilingual Desc' with the value 'F_Policy No'. The 'Detail' section is a table with three columns: 'Module Code*', 'Description', and 'Select Statement'. It contains five rows of data.

Module Code*	Description	Select Statement
01	Premium	SELECT POL_NO FROM PGIT_POLICY WHERE POL_SYS_ID = #P_POL_SYS_ID# AND POL_END_NO
02	Commission	SELECT POL_NO FROM PGIT_POLICY WHERE POL_SYS_ID = #P_POL_SYS_ID# AND POL_END_NO
03	Surveyor	SELECT POL_NO FROM PGIT_POLICY WHERE POL_SYS_ID = #P_POL_SYS_ID# AND POL_END_NO
04	TPA	SELECT POL_NO FROM PGIT_POLICY WHERE POL_SYS_ID = #P_POL_SYS_ID# AND POL_END_NO
05	Estimate	SELECT CLM_POL_NO FROM PGIT_CLAIM WHERE CLM_SYS_ID = #P_CLM_SYS_ID#

Fig. 125 – Config Screen

Header

The block enables the user to enter the header details.

Code

The item code gets displayed automatically on saving the record.



Description

Enter the description about the configuration of the flex field.

Bilingual Desc

Enter the bilingual description about the configuration of the flex field.

Detail

This block enables the user to enter the statement details.



Module code

Enter or select from the LOV the code of the module that has to be mapped. The accounting entries originate from the module code.

Description

The Description gets displayed automatically on entering selecting the module code.

Select Statement

Enter the query statement for configuring the flex fields.

Mapping

This screen enables the user to select the map-able fields for that corresponding flex fields. The map-able fields created in the configuration screen are displayed in this screen.

The Flex Field Mapping Screen is displayed as follows:

Flex Field Mapping			
Flex Field	Code*	Description	
AD_FLEX_01	1	Branch	
AD_FLEX_02	2	Business Type	
AD_FLEX_03	3	Claim No	
AD_FLEX_04	4	Claim Payee Name(at Settlement time)	
AD_FLEX_05	5	Class of Business	
AD_FLEX_06	6	Customer code	
AD_FLEX_07	7	Customer Name	
AD_FLEX_08	8	Customer Type	
AD_FLEX_09	34	Policy Premium	
AD_FLEX_10	10	Endorsement Type	
AD_FLEX_11	11	Endorsement No	
AD_FLEX_12	12	Insured Code	
AD_FLEX_13	13	Assured Name	
AD_FLEX_14	14	Open Policy Number	
AD_FLEX_15	15	Policy Number	
AD_FLEX_16	16	Product code	
AD_FLEX_17	17	Product Name	
AD_FLEX_18	24	Peril Class Code	
AD_FLEX_19	20	Treaty Type Code	
AD_FLEX_20	25	RI Customer Name	

Fig. 126 – Flex Field Mapping

Flex Field

This field displays the flex field code.

Code

This field displays the code from the configuration screen.

Description

The description gets displayed on selecting the code.

MOTOR CERTIFICATE

CERTIFICATE BOOK MASTER

When a policy is issued with the parameters defined in the Motor Certificate Book Master, on selecting the certificate mode as automatic, the user needs to select the appropriate certificate type and then the relevant book ID from the corresponding LOV.

On approval of the policy, the certificate pertaining to the selected book and next one available for assignment will be assigned to the policy automatically and saved.

This policy number is also updated in the Certificate Book Master against the certificate number for reference.

The system displays the screen as shown below:

Motor Certificate Book Master

Branch Code: 100 Head Office
 User Id: ADMIN PREMIA Administrator
 Broker Code*: AG0000001 Agent 001
 Certificate Type: 001 WAX 1/6
 Book Id: 100 Issue Dt: 12/06/2013 Prefix: MOTCERT-
 Start No: 0 End No: 50 Next No: 0
 Lead Zero ? Yes No Of Digit: 3
 Motor Certificate Book Start No. MOTCERT-000 End No. MOTCERT-050

Process

Certificate Details **Product Details**

Certificate	Policy No	Pol End No	Regis. No	Engine No	Chassis No	Issue Dt	Status

Fig. 127 – Motor Certificate Book Master

Branch Code

Select from LOV, the Branch Code from the LOV.

User Id

By default, the system displays the login user id.



Broker Code

Select from LOV, the broker code.



Certificate Type

Select from LOV, the certificate type.



Book Id

Enter a unique book ID to identify the certificate booklet.



Issue Date

By default, the system date is displayed. User is allowed to modify.



Prefix

Enter the prefix (alphabet) required to prefix the certificate number. For example 'MOTCERT-'.



Start No/End No

Enter the Starting number (for example '0') and ending number (for example '50') for the certificate.

Next No

Enter the number from which the certificate number is to be generated, while issuing policies. This number can be modified at a later stage.

Lead Zero?

If zeroes are to be added to be beginning of the number, then select 'Yes' from the drop down list, otherwise select 'No'.

No of Digit

This field is enabled if 'Yes' is selected in the 'Leading Zeroes Y/N' field .By default the value is displayed as 0. User is allowed to modify the same.

Tab out.

The Motor Certificate Book Start No and End no is displayed in the respective fields.

Click 'Process'.

TAB

Certificate Details

Click this tab to view the policies associated with the certificate.

Certificate Details		Product Details					
Certificate	Policy No	Pol End No	Regis. No	Engine No	Chassis No	Issue Dt	Status
MOTCERT-000	P/100/1001/2013/00348				TY8989	13/06/2013	Printed
MOTCERT-001	P/100/1001/2013/00359			PO214	PO123	14/06/2013	Printed
MOTCERT-002							None
MOTCERT-003							None
MOTCERT-004							None

Fig. 128 – Certificate Details

Certificate Number

This field shows the certificate number already generated and attached to a motor Policy. This is a display field.

Policy No

This field shows the Policy number to which the certificate number is attached with. This is a display field.

Policy End No

This field shows the Endorsement number to which the certificate number is attached with. This is a display field.

Registration No

This field shows the Motor vehicle registration number to which the certificate number is generated and attached with. This is a display field.

Engine No

This field shows the Motor Engine number of the vehicle to which the certificate number is generated and attached with. This is a display field.

Chassis No

This field shows the Motor vehicle Chassis number to which the certificate number is generated and attached with. This is a display field.

Issue Date

This field shows the issue date of motor certificate number. This is a display field

Status

Select the status of the certificate from the drop down list. The options available are:

- ☐ None
- ☐ Printed
- ☐ Regen and Printed
- ☐ Reprinted

TAB Product Details

Click this tab to view the products associated with the Certificate details.

Certificate Details Product Details	
Product Code*	Description
1001	Motor Commercial
1002	Motor Private
1003	Motor Fleet
1004	Motor - Special types
1005	Motor Cycle

Fig. 129 – Certificate – Product Details

MARKETING

INTRODUCTION

The Marketing Setup deals with set ups related to agents, brokers and cover notes.

The 'Marketing Setup' menu comprises of the following sub-menus:

-	Marketing
+	Agency Commission Set Up
+	Cover Note

Fig. 130 – Marketing menu

The usability of these menu items and their field level validations are explained in the respective sections.

AGENCY COMMISSION SETUP

Most companies have contracts with various agencies that carry out promotional activities as well as sales on behalf of the company. These agencies work on a commission basis. The Agency Commission Setup enables user to define the commission payable to the various agencies working for the company.

The 'Agency Commission Setup' menu comprises of the following sub-menus:

-	Agency Commission Set Up
o	Agency Commission Variant
o	Agency Commission Rate

Fig. 131 – Agency Commission Set Up

Agency Commission Variant

Variant is a factor on which the agency commission rate is based on (for example, Commercial Y/N, Renewal/New Policy). Based on the variance combination commission rate is defined.

The 'Agency Commission Variant' screen as shown below:

Policy / Section	Policy Level	
Class Code*	Policy Level	Engineering
Product Code*	Section Level	Contractors All Risk
Section Code		
Eff. From Date		Eff To Date
Variant 1*	SRC_CODE	Agent / Broker Code
Variant 2*		
Variant 3*		
Variant 4*		
Variant 5*		
Variant 6*		
Variant 7*		
Variant 8*		
Variant 9*		
Variant 10*		
Variant 11*		
Variant 12*		
Variant 13*		
Variant 14*		
Variant 15*		

Fig. 132 – Agency Commission Variant



Policy/Section

Select from the drop-down list the policy level. The options in the list are:

- ☐ Policy Level
- ☐ Section Level
- ☐ Risk Level (specific to Motor LOB)

Class Code

Enter or select from the LOV the code corresponding to the Class of business for which the variant has to be defined.

Product Code

Enter or select from the LOV the Product Code for which the variant needs to be defined. This field is mandatory if the user selects the Policy Level option in the 'Policy/Section' field.

Section Code

Enter or select from the LOV the Section Code for which the variant needs to be defined. This field is mandatory if the user selects the Section Level option in the 'Policy/Section' field.

Effective From/To Date

Enter or use the calendar help to specify the start and end dates of the validity period for the variants defined.

Variant

The application allows the user to define up to 15 variants.

Agency Commission Rate

This screen enables user to define the commission or allowance to be given to an agency working on marketing of the organization's products.

The commission or allowance is defined at both Policy and Section levels. The Agency Commission Rate screenshot as shown below:

Fig. 133 – Agency Commission Rate



Policy/Section

Select from the dropdown list the level at which the user needs to define the agency commission rate. The options in the list are:

- ☐ Policy Level
- ☐ Section Level

Class Code

Enter the Class Code for the Policy/Section for which the commission has to be defined. The application does not allow user to define the commission rates without selecting an appropriate Class Code.

Product Code

If the user has selected Policy as the commission level, the Product Code field is enabled. Select the appropriate Product Code from the LOV, if applicable.

Section Code

If the user has selected Section as the commission level, the Section Code field is enabled. Select the appropriate Section Code from the LOV, if applicable.



Set Rates

Click the 'Set Rates' button to enable the detailed Commission definition block available in the lower section of the screen.

Commission Code

Select from the LOV one of the following options:

- ☐ Agency Commission
- ☐ Agent Allowance

The corresponding description is automatically displayed in the adjacent field.

Default Commission %

Enter a percentage in the 'Dflt Comm. %' field to denote the default commission payable to the agent. If the user does not specify a commission during the transaction, the application defaults the value specified in this field. The application calculates the commission amount as:

$\text{Premium} * \text{Dflt Comm} / 100$

Minimum Commission %

Enter a percentage to denote the minimum commission payable to the agent. The application does not allow the user to enter an agent commission value lower than that defined in this field for the Policy/Section-Class Code combination.

Maximum Commission %

Enter a percentage to denote the maximum commission payable to the agent. The application does not allow the user to enter an agent commission value higher than that defined in this field for the Policy/Section-Class Code combination.

Effective From / To Date

Use the calendar help to specify the start and end dates for the time period for which the commission percentage defined are applicable.

☒ Editable Y/N

Select this check box to denote that the user is allowed to edit the default commission during transaction.



Back

Click the 'Back' button to reset the screen. The application deletes the values entered by the user and allows redefinition of the commission/allowance rates.

COVER NOTE

Cover Note Entry

Insurance companies, through their Underwriting Officers, issue a note first, which confirms that the asset has been insured. The policy normally takes few days, as it has to be processed by the company. This note, which is issued before the actual policy is made, is called Cover Note. Cover notes are mostly used in the rural insurance scenario where the insurance company does not have a direct presence and hence needs to issue a note that is similar to a policy to bring the insured and insurer to an agreement and confirmation.

This is also issued when all the mandatory details required for issuing a policy have not been provided by the customer or Insured while taking the policy.

Click 'Cover Note Entry' menu to view the following screen:

Manual Cover Note - Opening Entry

Dept No* Starting Cover Note No No of Books

Ref No Cover Note Prefix No of Pages for Book **PROCESS**

Department*	Cover Note Prefix	Start Serial No	End Serial No	Book No.	Ref No	Receipt Date	Status
10	CN	10056	10060	962	889	19/08/2013	1
10	CN	10056	10060	962	889	19/08/2013	3
10	CN	10051	10055	961	888	19/08/2013	4
10	CN	10011	10020	949	1235	19/08/2013	4
10	CN	10001	10010	948	1234	19/08/2013	4

Dept Desc:

Cover Book:

Status:

Remarks:

Issue to Office Code*

101
101

Fig. 134 – Cover Note Entry

Class From/To

Select the Class Code From/To from the LOV.

Reference Number

Enter the reference number of the cover note book in this field.

Starting Cover Note Number

Enter the reference number of the cover note book in this field.

Cover Note Prefix

Enter the cover note prefix number in this field.

Number of Books

Enter the number of books in this field.

Number of Pages for Book

Enter the number of pages for book in this field.

Click 'Process' to view a list of cover note books that is available in that specific category are displayed below.

Class Code From/To

Class refers to the class of business. Cover Notes are different for each class of business, as the sections would vary from one to the other. Select a class code from/to from the LOV. The corresponding description of class code from/to is displayed in the respective fields.

Cover Note Prefix

This prefix would appear along with each cover note serial number. It is possible to enter individual prefix such as FI-indicating the cover note is for Fire class of business or CN indicating it is cover note.

Start Serial Number

Enter the start serial number of the cover note. For example, if cover note starts with 200001 and ends at 200100, the start serial number is 200001.

End Serial Number

Enter the end serial number of the cover note. For example, if cover note starts with 200001 and ends at 200100, the end serial number is 200100.

Book Number

Enter the relevant book number.

Issue to Office Code

Select an office code from the LOV. This field is for entering information about the office of the

cover notes that would be delivered.

Reference Number

Enter the reference date in this field. It represents the reference number of the cover note.

Receipt Date

Enter the date manually or select the date from the calendar help. This refers to the receipt date of cover note.

Status

Status refers to the current position of the cover notes. The available statuses are:

- ☐ Issued
- ☐ Transfer
- ☐ Return
- ☐ Stolen
- ☐ Damage
- ☐ Closed
- ☐ Cancelled

Cover Book Status

The corresponding status description is displayed in this field.

Remarks

Enter remarks if any for future reference.

On completing the field entries, click 'Save'.

Cover Note Transaction

The receipt that the branch offices send to the head office serves as a point of reference for the RO (Regional office) or Head Office to estimate the number of cover notes issued. Based on this, the RO or Head Office is able to track all the transaction details for a particular transaction date, Underwriting Officer wise using Cover Note-Transaction.

All the details regarding the current status of cover notes such as conversion of cover notes to policies are viewed in this field.

Click 'Cover Note-Transaction' menu to view the following screen:

Cover Note Transaction - Source of Business Wise

Source* AG0000005 M/S.KARVY INSURANCE CONSULTANTS

Transaction Type* 1 Issued

Department* 10 Motor

Book ID* 948 User Id

Start Number 10001 End Number 10010

Remarks

Date of Transaction 19/08/2013

Approve

Cover Note No	Date	Status*	Issue Date	Policy No	Insured
CN0000010001	19/08/2013	6 Closed	16/08/2013 00:00	P/100/1001/2013/00622	Ms. SERENA ROBERT WILLIAMS
CN0000010002	19/08/2013	6 Closed	19/08/2013 00:00	P/100/1001/2013/00626	Agent 123
CN0000010003	19/08/2013	6 Closed	16/08/2013 00:00	P/100/1001/2013/00627	Ms. SERENA ROBERT WILLIAMS
CN0000010004	19/08/2013	7 Cancelled			
CN0000010005	19/08/2013	6 Closed	09/08/2013 00:00	P/100/1001/2013/00800	Ms. SERENA ROBERT WILLIAMS

Remarks

Fig. 135 – Cover Note Transaction



Source

Select the Underwriting Officer's code from the LOV.

Transaction Type

Transaction Type refers to the current position of the cover notes. Select the transaction type code from the LOV. The available transaction types are:

- ☐ Issued
- ☐ Transfer
- ☐ Return
- ☐ Stolen
- ☐ Damage
- ☐ Closed
- ☐ Cancelled

By default the status is set as 'Issued'.

Department

Select from the LOV, the department code, the cover note transaction is carried out.

Book ID (Identification)

A set of cover notes is called a book.

Enter the book number.

User Id (Identification)

Enter the user identification number of the user.

Start (Serial) Number

Enter the start serial number of the cover note. For example: If cover note starts with 200001 and ends at 200100, the start serial number is 200001.

End (Serial) Number

Enter the end serial number of the cover note. For example: If cover note starts with 200001 and ends at 200100, the end serial number is 200100.

Remarks

Enter remarks if any for future reference.

Date of Transaction

Enter the date for which the transaction details are to be viewed.



Approve

On completing the field entries, click 'Approve'. On clicking, the system fetches the information from the transaction table and displays the following details.

Cover Note Number

The Start and the End Serial numbers entered in the screen is displayed cover note wise in these columns.

Date

This is the same date as entered in the date of transaction. Essentially indicates that the records for the particular date within the serial number range entered are showcased.

Status

Status refers to the current position of the cover notes. The available statuses are:

- ☐ Issued
- ☐ Transfer
- ☐ Return

- ☐ Stolen
- ☐ Damage
- ☐ Closed
- ☐ Cancelled

The corresponding status description is displayed in the adjacent field.

Issue Date

The date of issuance of the cover note is displayed in this field.

Policy Number

If the status is closed, then the policy number would be displayed in this field.

Insured

Based on the policy number, the name of the Insured is displayed in the adjacent field.

Remarks


Enter remarks if any for future reference.

On completing the field entries, click 'Save'.

Cover Note Issue to Office

After creating a receipt for the cover note at the regional office, the next step is to issue them to office through which they would be issued to the concerned Underwriting Officers.

Click 'Cover Note-Issue to Office' menu to view the following screen:



Department *	Cover Note Prefix	Start Serial No	End Serial No	Book No.	Issue to Office Code*	Issue Date	Receipt Date
10	CN	10056	10060	962			
10	CN	5021	5025	981			
10	100	1001	1010	1061			22/10/2013
10	CN	941	950	936			23/04/2013
10	CN	931	940	935			23/04/2013

Dept Desc:

Cover Book:

Status:

Remarks:

Issue Office Desc:

Fig. 136 – Manual Cover Note – Issue/Return



Department

Department refers to the class of business. Cover Notes are different for each class of business, as the sections would vary from one to the other.

Select a department from the LOV. The corresponding description of department code is displayed in the respective field.



Cover Note Prefix

This prefix would appear along with each cover note serial number. It is possible to enter individual prefix like FI-indicating the cover note is for Fire class of business or CN indicating it is cover note.



Start Serial Number

Enter the start serial number of the cover note. For example, if cover note starts with 200001 and ends at 200100, the start serial number is 200001.



End Serial Number

Enter the end serial number of the cover note. For example, if cover note starts with 200001 and ends at 200100, the end serial number is 200100.

Book Number

Enter the relevant book number.



Issue to Office Code/Description

Select an office code from the LOV. This field is for entering information about the office of the cover notes that is to be delivered. The corresponding description of issue to office code is displayed in this field.

Issue Date

Enter the issue date of cover note.

Receipt Date

Enter the date manually or select the date from the calendar help that is accessed by using LOV. This refers to the receipt date of cover note.

Cover Book Status

The corresponding status description is displayed in this field.

Remarks

Enter remarks if any for future reference.

On completing the field entries, click 'Save'.

Cover Note Receiving

This screen enables branch/division offices to acknowledge that they have received the cover notes.

Click 'Cover Note Receiving' to view the screen as shown below

Manual Cover Note - Receipt

Department *	Cover Note Prefix	Start Serial No	End Serial No	Book No.	Recd. from Office	Receipt Date	Return RO Y/N
20	F100	1	99			22/10/2013	

Dept Desc: Fire

Cover Book:

Status:

Remarks:

Issue Office Desc:

Fig. 137 – Manual Cover Note – Receipt



Department

Select a department code from the LOV. The corresponding description of department code is displayed in the respective fields.



Cover Note Prefix

This prefix would appear along with each cover note serial number. It is possible to enter individual prefix like FI-indicating the cover note is for Fire class of business or CN indicating it is cover note.



Start Serial Number

Enter the start serial number of the cover note. For example, if cover note starts with 200001 and ends at 200100, the start serial number is 200001.



End Serial Number

Enter the end serial number of the cover note. For example, if cover note starts with 200001 and ends at 200100, the end serial number is 200100.

Book Number

Enter the relevant book number.

Received from Office

Refers to the date of cover note received from the office.

Receipt Date

Enter the date manually or select the date from the calendar help that is accessed by using LOV. This refers to the receipt date of cover note.

Return RO Y/N

Select this checkbox if the book has been returned from Regional Office.

Issue Office Description

The corresponding description of issue to office code is displayed in this field.

Cover Book Status

The corresponding status description is displayed in this field.

Remarks

Enter remarks if any for future reference.

On completing the field entries, click 'Save'.

CLAIMS MASTER

Introduction

Claims refers to a policy owner's request or demand on the insurance company for payment of benefits according to the provisions of a policy. In order to handle claims, a record of all the codes connected to claims has to be created. Added to this, Claims Master allows the user to add/modify the various parameters attached to it.

The 'Claims Masters' menu comprises of the following sub-menus:

-	Claims Master
o	Nature of Loss Master
o	Cause of Loss Master
o	Reserve Setup
+	Checklist
+	Flexi Setup
o	Event Codes Master
o	Claim Status Master
o	Claim Close/Reopen Reason
o	Spares Parts Master
o	Court Detail Master
o	IDV Calculation Setup

Fig. 138 – Sub-menus – Claims Master

The usability of these menu items and their field-level validations are explained in the respective sections.

NATURE OF LOSS MASTER

This menu helps the user to map the Nature of Loss codes to Loss Applicable Covers.

Click 'Nature of Loss' from the Claims Masters sub-menu to view the following screen:

Fig. 139 – Nature of Loss Master

Nature of Loss Master



Loss Code

Query the nature of loss code which was created in the nature of loss codes master. Press F7 and enter the nature of loss code and again press F8.

Loss Description

This field defaults the description pertaining to the Loss Code in this field.

Loss Applicable Covers

After selecting the Loss Code, the next step is to map the loss code to any one of the following codes:

- ☐ Product Code
- ☐ Product Description
- ☐ Section Code
- ☐ Cover Code

Enter, in one of this parameter code field, the code name.

Example: Enter, in Section Code field, a Section Code name.



Populate Products

Click 'Populate Products' button. All the varying parameters mapped to that code is displayed.

☒ Applicable YN

Select the check box for Product/Section/Category codes to be mapped to the Loss Code.

☒ Select All

Select 'Select All' check box for Product/Section/Category codes to be mapped to the Loss Code.

CAUSE OF LOSS MASTER

Click this menu to map the Cause of Loss codes to Loss Applicable Covers.

The system displays the screen as shown below:

Product Code	Product Description	Claim Rejection Flag
1001	Motor Commercial	☐
1002	Motor Private	☐
1003	Motor Fleet	☐
1004	Motor - Special types	☐
1005	Motor Cycle	☐

Fig. 140 – Cause of Loss Master

Cause of Loss Master



Cause of Loss Code

Query the nature of loss code which was created in the nature of loss codes master. Press F7 and enter the nature of loss code and again press F8.

Cause of Loss Code Description

This field defaults a valid description pertaining to the Cause of Loss Code.

Applicable Products

After selecting the cause of loss code, the next step is to map the loss code to any one of the following codes:

- ☐ Product Code
- ☐ Product Description



Product Code

After selecting the loss code, the next step is to map the loss code to a Product Code.

Product Description

A list of all product codes applicable to the cause of loss code is displayed in the Product Description field.

☒ Claim Rejection Flag Y/N

Select the check box, to reject any claim towards this product.

RESERVE SETUP

Reserve refers to the terms or conditions of an insurance policy as contained in the policy clauses. These provisions are to be a financial loss or a gain to an insurance company.

Click 'Reserve Setup' menu to view the screen as shown below. This screen enables the user to create the estimate codes which are used in the Claims Registration screen:

Estimate Master

Sr. No	Provision Code*	Provision Description	Provision Indicator	Provision Category	Provision Type	Recovery Type
1	007	TEST PROVISION FOR SUBROGATION	Loss Estimation	Interest	Reversal of Rec...	Other Recovery
2	008	TEST	Expense Estimation	Interest	Reversal of Rec...	Other Recovery
3	1	TEST	Loss Estimation		Reversal of Rec...	Salvage Recovery
4	1000001	PYMNT TO CLAIMANT/BROK	Loss Estimation		Payment	
5	1000002	PYMNT TO GARAGE/AGENC	Loss Estimation		Payment	Subrogation Re...

Activity Code 1* Activity Code 2*

Default Est. Amount in LC1 Short Description

Long Description

Tax Details

Sr. No	Charge Type*	Charge Description	Percentage (%)	Effective From Dt	Effective To Dt
1	001	Service Tax	5		

Fig. 141 – Reserve Setup

Estimate Master

Provision Code

Provisions refer to the terms or conditions of an insurance policy as contained in the policy clauses. These provisions are to be a financial loss or a gain to an insurance company.

Enter a new, unique Provision code in this field. Click appropriate Provision Code from the LOV.

Provision Description

The description pertaining to the Provision Code is defaulted in this field.

Provision Indicator

This field allows the user to add a parameter as to whether the provision is based on expense estimation or loss estimation. The user is able to select an indicator from the drop-down list.

Provision Category

Provision category comprise of professional fee or an interest. The user is able to select a category from the drop-down list.

Provision Type

Select the required Provision Type from the drop-down list. The available options are:

- ☐ Payment
- ☐ Recovery
- ☐ Reversal of Payment
- ☐ Reversal of Recovery

Activity Code 1

Select appropriate activity code 1 from the LOV. This field is enabled according to the selection in the header block.

Activity Code 2

Select appropriate activity code 2 from the LOV. This field is enabled according to the selection in the header block.

Default Estimate Amount in LC1

The amount which is entered here is defaulted against the estimate in the claim.

Short Description

The description pertaining to the Provision Description is defaulted in this field.

Long Description

Enter the long description of the Provision Description in this field, if required.

Tax Details

This block enables the user to add the tax component payable to the newly created provision in this field.

Charge Type

Charge Type refers to the type of tax chargeable (Example: Service Tax and Sales Tax.). The user is able to select a type from the drop-down list. The corresponding description is defaulted in the adjacent Charge description field.

Percentage (%)

Enter the percentage of applicable tax in this field.

Effective From and To Date

Enter the effective period of this reserve from the Calendar help.

CHECKLIST

DEFINITION

The first step in creating checklists is to define them. The user defines a checklist by selecting a Module Code (Instance code for a specific product) and entering the Checklist Code and a matching Description. On saving these field entries, the checklist gets mapped to the Module. The user can also attach the checklist to a product that is linked to the selected module by selecting the Product Code.

-	Checklist
0	Master Setup
0	Variants
0	Definition

Fig. 142 – Checklist Sub-menu

Click 'Checklist Definition' menu to view the following screen.

Checklist Code	Checklist Description	Start Date	End Date
101	Completely filled Claim Form	01/01/2000	31/12/2099
102	Estimate & Final Bill of Repairs	01/01/2000	31/12/2099
103	Duly Signed Discharge Voucher	01/01/2000	31/12/2099
104	Original Allocation of Vehicle Regis	01/01/2000	31/12/2099
105	Transfer Letter (Total Loss/Theft)	01/01/2000	31/12/2099

Product Code	Product Description
1001	Motor Commercial
1002	Motor Private
1003	Motor Fleet
1004	Motor - Special types
1005	Motor Cycle

Fig. 143 – Checklist Definition

Module Code

Select the code from the LOV. The module description is displayed in the adjacent field.

Checklist Code and Description

Enter the new checklist code in this field and enter its description in the field provided for the same.

Start and End Date

Enter or select the Start and End dates from the application calendar. These dates specify the validity period for the checklist.

Product Code

If the checklist is to be mapped to a product based on the selected module, select the product code from the LOV. The product description is displayed in the adjacent field.

Add Checklist Codes

Click the 'Add Checklist Codes' button to utilize an existing checklist instead of creating a new list.

On clicking this button, the system navigates to 'Checklist Master Setup' screen.

Refer the below section for more information.

MASTER SETUP

The user can map the checklist codes that have been created to various checklist attributes such as the data type, mandatory. Click Master Setup from the Checklist submenu. The following screen is displayed.

Checklist Code	Description	Description BL	Data Type	Width	Decimals	Effective From	Effective To	Mandatory YN	Remarks Mandatory YN	Codified YN
601	Completely filled Claim Fo	F_Completely filled Claim F	Text	100		01/01/2000	31/12/2099	☒	☐	☐
602	Quotation for repairs/repla	F_Quotation for repairs/repl	Text	100		01/01/2000	31/12/2099	☒	☐	☐
603	Incident Report/Circumsta	F_Incident Report/Circumst	Text	100		01/01/2000	31/12/2099	☐	☐	☐
604	Police Report(in case of th	F_Police Report(in case of	Text	100		01/01/2000	31/12/2099	☐	☐	☐
605	Fire brigade report (if appli	F_Fire brigade report (if ap	Text	100		01/01/2000	31/12/2099	☐	☐	☐

Checklist Value	Description	Description BL

Fig. 144 – Checklist – Checklist Master Setup



Checklist Code / Description

Select the code from the LOV. The codes here have been pre-defined in the 'Checklist Definition' master. The description is displayed in the adjacent field.



Data Type

Select the data type from the drop-down list. The available data types for the checklist are:

- ☐ Text
- ☐ Date
- ☐ Yes No
- ☐ Number

When the checklist is displayed in run time in the claims module, the user has the option to enter a text reply (Example: Remarks), Date (Example: Date of checklist verification), Yes No (Option as to whether the checklist item was submitted/collected) or enter Number. Four data types are selected from the drop-down list.



Width

If the Data Type selected was Text or Number, enter the width value in this field. This would determine the field size of the data in the checklist in run time.

Decimals

Enter the decimal value, if the Data Type selected is Number. This value determines the field decimal length of numbers in the checklist during run time.

Effective 'From' and 'To' Date

Enter or select the 'From' and 'To' dates from the Calendar help. These dates specify the validity period of this setup.

☒ Mandatory YN

Select the check box if this checklist is mandatory during run time.

☒ Remarks Mandatory YN

Select the check box if remarks entry for this checklist during run time is mandatory.



Checklist Value

Enter a value for the checklist.



Description

Enter the corresponding checklist description.


Description BL

Enter the corresponding checklist bilingual description.

On completing the field entries, click 'Save' button to save the details.

VARIANTS

Checklist variants screen is currently used for the Nature of Loss related checklist. This is to ensure that the checklist data that is viewed during claims processing. It showcases only the nature of loss related details. Using this screen, the user is able to map a Claims Master table (Reference Table field) with a Reference column (Reference System Identification Column, where the nature of loss checklist data resides).



The screenshot shows the 'CHECKLIST VARIANTS' form with the following fields:

- Module Code*: PGIT6_02-038
- Reference Table*: CTRL_BUTTONS
- Para Code 1: Nature Of Loss (dropdown)
- Para Code 2: Endorsement Type (dropdown)
- Effective From: (empty field)
- Description: Instance For Other Details(Mac)
- Reference Sys Id Column*: (empty field)
- Reference Column 1*: (empty field)
- Reference Column 2*: (empty field)
- Effective To: (empty field)

Fig. 145 – Checklist Variants



Module Code

Select the code from the LOV. The module description is displayed in the adjacent field.



Reference Table

Enter the Claims Master Table name in this field.



Reference System Identification Column

Select the Reference System Identification column name from the LOV. This is the column where the specific nature of loss related data resides.

Parameter Code 1-2

Enter the parameters that are applicable in this field. The form from which the LOV is derived contains multiple data. All the data might not be relevant to a particular field.

Reference Column

Enter the Reference Column name in this field.

Effective 'From' and 'To' Date

Enter or select the 'From' and 'To' dates from the Calendar help. These dates specify the validity period.

On completing the field entries, click 'Save' button to save the details.

Verified YN

Select this check box if the entered checklist is verified.

Remarks

Enter the remarks if required.

FLEXI SETUP

In addition to regular field setup, there are flexible (additional) fields attached to regular (pre-defined) fields. The various parameters options such as the caption name, data type based on which the flexi fields operate.

Flexi setup helps the user in adding/modifying the parameters of the flexi fields that are used in the claims module.

Click 'Flexi Setup' from Masters main menu. The following flexi setups are available in the claims module:

- ☐ **Loss Flexi** – The user is allowed to change the parameters or add new fields for nature of loss in this screen. Nature of Loss refers to the outcome of loss such as bodily injury, and burglary
- ☐ **Product Flexi** – The user is allowed to change the parameters or add new fields for products (insurance policies) in this field



- ☐ The field entries for Product Flexi within the Flexi Setup sub-menu are similar to that of Nature of Loss.
- ☐ Only the first field name changes from screen to screen. However, the entries for these fields too are same as the Loss Flexi which is explained in the subsequent section.

LOSS FLEXI / PRODUCT FLEXI DEFINITION

Click 'Loss Flexi' menu to view the following screen:




Fig. 146 – Loss Flexi Definition



Product Code

Enter a unique Product Code in this field or select from the LOV, the appropriate Product Code. The description pertaining to this field is displayed in the adjacent field.



Field Caption

Enter the field caption name in this field. This field caption appears as the boiler plate caption in run time.



Data Type

Select appropriate data type from the LOV. Data type comprises of Date, Number, Text or Yes/No.



Field Length

Enter the field length value in this field.

☒ **List Available**

Select this check box if there is a matching LOV that can be mapped to the flexi field.

PC Type

PC stands for Parameter Code. If the user has selected the List Available check box, the user is to enter the LOV table name in this field.

☒ **Mandatory**

Select this check box if field entry to the flexi field is necessary.

Hint Text

The user is able to notice a hint text (as indicated below) positioned on the left bottom of the screen




Fig. 147 – Hint Text

Placing a text in the hint field generates this hint.

EVENT CODE MASTER

This menu helps the user to create codes for the various event types. Click 'Event Code Master' from the Claims Masters menu. The system displays the screen as shown below:




Fig. 148 – Event Code Master

Code

Enter a new, unique event Code in this field.

Description

Enter a valid event name in this field.

Short Description

The data entered in the Description field is defaulted in this field.

Long Description

Enter the long description of the event code in this field, if required.

☒ **Code by Class**

Select the check box to enter the class of business (for example, Fire, Motor.) for which this code is valid. If the check box is cleared then the application allows this code to be used across

all classes of business.



Class

Select Class from the LOV. The corresponding description is defaulted in the adjacent field.

Value

This field is mandatory, depending on the parameter type set in the system parameters. Enter a value for the hospital code, if any. This value is used in the transactions.



Applicable Modules

Enter a code. The description of the code is defaulted in the adjacent field. The code entered in the event code field is relevant to the module mentioned in this field.

Effective From and To Date

Enter or select the effective From and To dates from the Calendar help.



Branches

Click this button to map applicable branches to the Event code.

CLAIM STATUS MASTER

The 'Claim Status Master' screen enables the user to track the status of the claim, as on a particular date.

User can enter the current status of the claim to view the status immediately and take up for processing.

Fig. 149 – Claim Status Master



- ☐ The field details displayed is similar to Event Code Master screen.
- ☐ Kindly refer 'Event Code Master' section for more information.

CLAIM CLOSE/REOPEN REASON

The 'Reason Master' screen enables the user to view the Close/Reopen history of the claim and the reasons for closing and reopening the claim.

The system displays the screen as shown below:

Fig. 150 – Reason Master

- ☐ The field details displayed is similar to Event Code Master screen.
- ☐ Kindly refer 'Event Code Master' section for more information.

SPARE PARTS MASTER

The 'Spare Parts Master' screen which is applicable for Auto product enables the user to define the spare parts details.

The system displays the screen as shown below:

Fig. 151 – Spare Parts Master



Code

Enter a new, unique Code for the spare part.



Description

Enter a valid description for the spare part.

Short Description

The data entered in the Description field is defaulted in this field.

Unit Price

Enter the unit price of the spare part.

Discount

Enter the discount value given for the spare part.

Type

Enter the appropriate type as one of the following:

☐ Labour Charge

☐ Spare Part

Effective From and To Date

Enter or Select From and To dates using the Calendar help.

COURT DETAIL MASTER

The 'Court Details' screen enables the user to define the court related details. The system displays the screen as shown below:

Court Master

Court Code * 01

Description MACT Court Annanagar

Short Description MACT Court Annanagar

Long Description MACT Court Annanagar

Court Type MACT

Outside Country (Y/N) ☐

Address* First main Road
7th Avenue
Annanagar

Country* 001 Kingdom of Bahrain

State*

City*

PIN Code*

County*

Remarks

Bi-lingual Details

Description

Short Description

Long Description

Address

Fig. 152 – Court Master



Court Code

Select the court where the case is filed from the LOV. Once the code is entered, its description is displayed automatically in the adjacent field.

Description

System defaults the field details

Short Description

The data entered in the Description field is defaulted in this field.

Long Description

The data entered in the Description field is defaulted in this field.

Court Type

Select from the dropdown list the type of court where the case is filed. Many options have been provided in the list box. The options provided are:

- ☐ NA
- ☐ Supreme Court
- ☐ High Court
- ☐ Commercial Court
- ☐ Fast Track
- ☐ Court of Appeal

Address

Enter the address details.

Country/State/City

Select from the LOV the country, State and City in this field.

Pin Code/Country

Enter the Pin Code and County


Remarks

Enter any additional remarks about the case if available.

IDV (INSURED DECLARED VALUE) CALCULATION SETUP

The 'IDV Calculation Setup Master' screen enables the user to define the depreciated or market value of the vehicle based on product and section codes.

Based on the criteria set for the vehicle, during renewal of policy, the applicable value is picked up as the vehicle value for premium calculation.



Vehicle Type	Description	No of Days Fm	No of Days To	Depr Perc	Valid Fm Dt	Valid To Dt
001	PRIVATE	1	365	10.00000	01/01/2013	10/10/2014

Fig. 153 – IDV Master



Product Code

Select the product code from the LOV for which the invoice value and depreciation % are to be defined.



Section Code

Select from the LOV, the section code associated with the Product.



Vehicle Type

Select from the LOV, the type of vehicle to define the IDV.

- ☐ Commercial
- ☐ Private
- ☐ Taxi and so on



No of Days From /To

Enter the number of days 'From' and 'To' in the respective fields. This provides the age of the vehicle to be validated for IDV calculation.

Depreciation Percentage

Enter the depreciation percentage of the product.



Ensure that the depreciation percentage is appropriate with the Vehicle type.
In case of a Commercial vehicle, the depreciation is on the higher side compared to a Private vehicle.

Valid From Date/ Valid To Date

Enter the effective period for which the depreciation percentage defined for the product is valid.

APPLICATION SETUP

Introduction

The Application Setup is primarily used for defining various parameters such as form interface, copy function, user authorization setup and Identification details of the users required for the application.

The 'Application Setup' menu comprises of the following sub-menus:

-	Application Setup
o	UW Form Interface
o	LOV Definition
o	History Instance Copy
o	User
o	Reports
o	User Approval Setup
o	User Group Id

Fig. 154 – Application Setup

The functionalities of various sub-menus are described in detail.

UW FORM INTERFACE

The 'UW Form Interface' screen enables the user to define the instances for the corresponding transactions. The system displays the screen as shown below:

Form ID Definition	
Document Type*	2
Document Code*	60-PL-03-001
Product Code*	8002
Main Form Prg Code	PGIH6_01
Main Form Inst Code	80-PCH-01_01
Static Form Inst Code	80-PCH-02_01
Dynamic Form Prog. Code	PGIH6_03
Dynamic Form Inst. Code	80-PDH-03_01
Hypothecation Inst Code	80-PDH-06_01
Discount/Loading Inst. Code	80-PDH-05_01
Claim History Inst. Code	80-PDH-07_01
Deductible Inst Code	80-PDH-04_01
Computation sheet Inst Code	PGIH0014-001
Billing Details Screen Inst Code	
Additional Insured Screen Inst Code	PGIM2001-I01
Condition Form Inst Code	
History Form Inst Code	80-PCH-01_01

Fig. 155 – UW Form ID



Instances are generated based on Programs.

Document Type

Select the document type from the LOV. The LOV displays codes pre-defined in the system.

Document code

Select the required document code from the LOV. The LOV displays codes set in the various document setups.

Product Code

Select the product code from the LOV. The system shows all the product codes available in Product Setup in this LOV.

Main Form Program Code

Select the Main Form Program Code from the LOV. This is the program code based on which the instance is generated.

Main Form Instance Code

Select the Main Form Instance Code from the LOV. This main form instance code is sourced from the Instance table available in PREMIA.

Static Form Instance Code

Select the Static Form Instance Code from the LOV. This is the policy entry (header block) code.

Dynamic Form Program Code

Select the Dynamic Form Program Code from the LOV. This is the section or the risk block code.

Dynamic Form Instance Code

Select the Dynamic Form Instance Code from the LOV. This is the Dynamic Data Block (DDB) form instance code and is sourced from the Instance table available in PREMIA.



The field entries for Hypothecation, Discount/Loading, Claim History, Deductible, Computation sheet instance codes are similar to the field entry for Dynamic Form Instance Code and hence not repeated. All these blocks appear in the appropriate places during runtime.

Hypothecation Instance Code

Select the code for Hypothecation Instance Id from the LOV.

Discount/Loading Instance Code

Select the code for Discount/Loading Id from the LOV.

Claim History Instance. Code

Select the code for Claim History Instance Id from the LOV.

Deductible Instance. Code

Select the code for Deductible Instance Id from the LOV.

Computation sheet Instance. Code

Select the code for Computation Instance Id from the LOV.

Billing Details Screen Instance Code

Select the code for Bill Instance Id from the LOV.

Additional Insured screen Instance Code

Select the code for Additional insured instance Id from the LOV.

Condition Form Inst. Code

Select the code for Conditional Instance Id from the LOV.

History Form Inst. Code

Select the code for History Instance Id from the LOV.

LOV DEFINITION

While setting up the field level information in the Masters module of the application, the List of Values (LOV's) is displayed across many fields.

The LOVs are mapped to the respective program, instance and then the field by using the 'LOV Definition' screen.

Click 'LOV Definition' menu to view the following screen:

Fig. 156 – LOV Definition

Program Code

Select from the LOV, the Program Code. This is the program code based on which the instance is generated.

Module Code

Select from the LOV, the Module Code. Module refers to the department or the class of business.

Product Code

Select from the LOV, the Product Code. Product refers to a specific policy type (Example: Cargo Vessel Insurance Policy).

Section Code

Select from the LOV, the Section Code. Section refers to the various sections available under a Product.



Block Name

Select from the LOV, the Block Name. All the screens in PREMIA are built using static blocks. For more information on blocks, check the Interface Form_For Form ID introduction.



Field Name

Select the appropriate field (using the LOV) where the LOV needs to be displayed during runtime. Within a block, there might be numerous fields.

LOV Title

Enter the title for the LOV. This is displayed during runtime in PREMIA.



Number of Columns

Enter the number of columns in this field. Each LOV comes with a certain set of columns through which the required information of the LOV is viewed during runtime. The LOV comprise of single or multiple columns based on the display requirements.



A LOV can display a maximum of four columns during runtime.



Select Statement

Enter the select statement for the column Based on the data to be displayed; a SQL Select statement is to be written to retrieve data from the database.



Column Length

Enter the column length. In case of multiple columns, separate them using a comma.



Column Heading

Enter the column heading. In case of multiple columns, separate them using a comma.



Return Field Name

Enter the return field name. Return Field Name determines the order in which the query values are to be displayed in the LOV during run time. Enter the Return Field Name.



A column-wise order has to be followed; each separated by a comma and values for all the four columns is to be assigned. If the columns are lesser than four, enter Null as the value.

Parameter Column 1-5

The form from which the LOV is derived contains multiple data. All the data might not be relevant to a particular field.

Auto Query Yes/No

Auto Query feature allows users, during runtime, to view the LOV in a single keystroke (F9) or double keystroke (F9 + F8).

Enter 1 to view the LOV in a single keystroke (F9) or enter 0 or 2 to view the LOV in double keystroke (F9 + F8).

LOV Type

Depending on the value entered here the system allows the user to select a single option in the LOV or multiple options in the LOV. The available options are:

- ☐ 1 – User is allowed to select only one value.
- ☐ 2 – Checkbox gets enabled inside the LOV window. Using the checkbox multiple values can be selected.

Initial Sort column

Enter the number of initial sort column. The available options are:

- ☐ 1 – The values available for the LOV are displayed in ascending order.
- ☐ 2 – The values available for the LOV are not in ascending order.

HISTORY INSTANCE COPY

Instance is otherwise known as duplication of the forms created by the developer. The 'History Instance' menu enables the user to create and copy an instance and to identify the forms used in the application.

Click 'History Instance Copy' menu to view the following screen:

Instance Copy	
From Instance PGIT6_01 (Main Prog.)	To Instance PGIH6_01
From Instance PGIT6_02 (Static Inst.)	To Instance PGIH6_02
From Instance PGIT6_03 (Dynamic Inst.)	To Instance PGIH6_03
From Instance PGIT6_04 (Deduct Inst.)	To Instance PGIH6_04
From Instance PGIT6_05 (Dis/Load Inst.)	To Instance PGIH6_05
From Instance PGIT6_06 (Hypo Inst.)	To Instance PGIH6_06
From Instance PGIT6_07 (Claim Hist.)	To Instance PGIH6_07
From Instance PGIT6_08 (Add. Insured Inst.)	To Instance PGIH6_08
From Instance PGIT6_09 (Bill Detl. Inst.)	To Instance PGIH6_09
From Instance PGIT6_10 (Rating Steps Inst.)	To Instance PGIH6_10
From Instance PGIT6_11 (Condit Inst.)	To Instance PGIH6_11

Ok Clear

Fig. 157 – History Instance Copy

User is able to create and copy an instance from the main program to another program.

Each different field represents each instance.

Click 'Clear' button to clear the fields in the form and Click 'Ok' button to save the instances.

Click 'Close' button to revert to main screen.

USER

The 'User' screen enables the System administrator to create new users with attributes and attach them to a user group. Also the administrator is able to attach applicable branch, Department to the user.

The Admin can also map to users to a particular menu and security group.

Click 'User' menu to view the following screen:

Fig. 158 – User

User ID

Enter manually or select the unique identification name that allows the user to login to PREMIA application.

Description

Enter the description for the new user created.

Password

Enter the password of the new user.

Reconfirm Password

Enter the password one more time to confirm.

User Session Count

Enter the number for session counts the user can open PREMIA application.

View

Select this option to assign the user to view PREMIA application.

Print

Select this option to assign the user to view and print information while using PREMIA.

Save

Select this option to assign the user to modify the contents within PREMIA and save the changes.

Login Count

Login count allows users to restrict the number of users using a particular user ID. This field is used in cases where the User IDs are generic.

☒ Bilingual Display Y/N

Enabling this check box will allow the user to view PREMIA in a bilingual mode.

Administrator Y/N

Enabling this check box will allow the user to enjoy all the privileges of an Administrator.

☒ Override Y/N

Enabling this check box, user is allowed to override the existing data.

Start Menu ID

Select a start menu ID from LOV. This restricts users from viewing menus that are relevant to their work. User is allowed to view the description for the start menu ID in the description field placed after start menu ID field.

Profile ID

Select from the LOV, the profile ID number.

Reporting To

Select from the LOV, the profile ID and screen name.

Menu Group ID

Select from LOV, the menu group to map the new user to a particular menu group.

Security Group ID

Select from LOV, the security group to map the new user to a particular security group. Security group refers to groups that hold the highest privileges.

Telephone Number

Enter the telephone number of the user.

Fax Number

Enter the fax number of the user.

E-Mail ID

Enter the e-mail ID of the user.

Mobile Number

Enter the mobile number of the user.

Printer Code

Select the applicable printer code to map to PREMIA by registering its code.

Printer Format

Select the printer type – whether it is dot matrix, laser jet or ink jet.

Copies

Set the number of prints the user has the privilege to take the copies while using PREMIA application.

Default Location

Select the Default location if the user is working on deputation at another office branch.
Click 'Save' to save the entered details.

Default Language

Select from the LOV the default language as one of the following – English or Non-English.

TAB Company

This is the default tab that enables the user to attach the user to the company code. The 'Company' block displayed as shown below:

Code	Name	Default ?
001	INSURANCE CO LTD	☒
		☐
		☐
		☐
		☐

Fig. 159 – Company

Code

Select from the LOV, the company code.

Name

Based on the company code selection, the company name is auto-generated.

☒ Default

Select this check box if the code and the company name need to be defaulted in the login screen.

On entering all these fields, click 'Save'.

TAB Branch

Click 'Branch' tab to attach the User ID with applicable branch. The system displays the screen as shown below:

Company Code	Company Name	Division Code	Division Name	Default ?
001	INSURANCE CO LTD	100	Head Office	☒
				☐
				☐
				☐
				☐

Fig. 160 – Division

Company Code

Select or enter the company code. The Company Name is automatically displayed in the adjacent field.

Division Code

Enter or select from the LOV, the division code as one of the following:

- ☐ Division 10
- ☐ Head Office
- ☐ Division 02

Division Name

Based on the division code, the division name will appear in this field by default. User is allowed to either select the division code from the LOV or enter it manually.

☒ Default

Select this checkbox to default the company/division codes and the division name during transaction.

TAB Department

Click this tab to attach the User ID with the applicable department. The system displays the screen as shown below:

Comp. Code	Division Code	Name	Department Code	Name	Default ?
001	100	Head Office	10	Motor	☒
					☐
					☐
					☐
					☐

Name:

Fig. 161 – Department



- ☐ The Company Code, Division Code, and Name are available by default in the first three fields in this tab.
- ☐ It is advisable not to change these fields.

Department Code

Department refers to the various business classes like Fire, Marine Hull, Motor etc. Select from the LOV, the relevant department code.

Department Name

Based on the department code, the department name gets defaulted in this field. User is either allowed to select the department code from the LOV or enter it manually.


☒ Default

By default, this check box is selected. The company/division codes and the department code/name will be displayed by default during transaction

Click 'Save' to save the entered details.

Copy

Click this button to create new user with user privileges. The system displays the screen as shown below:



The 'Copy User' dialog box is shown with the following fields and controls:

- From User:** Text box containing 'BD01'.
- To User:** Empty text box.
- Description:** Empty text box.
- Password:** Empty text box.
- Re Confirm Pwd:** Empty text box.
- User Privileges:** Check box (unchecked).
- Buttons:** 'Ok' and 'Cancel' buttons at the bottom.

Fig. 162 – Copy User


REPORTS

The 'Reports' screen in PREMIA facilitates the user during boilerplate generation.

Boilerplate refers to the process of setting up the display terms (headings) for various fields required in the report.

For example, a Report needs to display these texts - From Date, To Date, Branch etc while viewing on screen and also when taking prints. These display texts are furnished in this screen.

Click 'Reports' menu to view the following screen.



The 'Insurance CO LTD' Reports screen is shown. It features a menu bar with 'File', 'Edit', 'Block', 'Field', 'Record', 'Query', 'Favorites', and 'Help'. The main area is divided into two sections:

- Header Block (marked in red):** Contains fields for 'Rep Code' (APC_6000), 'Title Eng' (MARINE CARGO CERTIFICATE), 'For' (F_MARINE CARGO CERTIFICATE), 'Date Eng', 'User Eng', 'Page Eng', 'Repid Eng', and 'For'.
- Details Block (representing the tabs):** Contains a table with 10 columns and 10 rows of headings.

Column Headings 1-10	Column Headings 11-20	Column Headings 21-30	Column Headings 31-40	Column Headings 41-50	Column Headings 51-60
Head1	MARINE CARGO CERTIFICATE NO	F_MARINE CARGO CERTIFICATE No.			
Head2	NAME OF CONTRIBUTOR	F_NAME OF CONTRIBUTOR			
Head3	ADDRESS	F_ADDRESS			
Head4	VOYAGE AND CONVEYANCE	F_VOYAGE AND CONVEYANCE			
Head5	DESCRIPTION OF CARGO	F_DESCRIPTION OF CARGO			
Head6	BANK AND L/C NO	F_BANK AND L/C NO			
Head7	VALUE DECLARED	F_VALUE DECLARED			
Head8	BASIS OF VALUATION	F_BASIS OF VALUATION			
Head9	SUM INSURED	F_SUM INSURED			
Head10	TERMS OF COVERAGE	F_TERMS OF COVERAGE			

Fig. 163 – Reports

The screen is divided into two blocks. The header block (marked in red) and details block (representing the tabs).

Header Block

In this area, enter the standard information that should appear for a particular report.

For Example – When a user needs to print a report called Collection Summary Report, typically, this report would have display terms that includes Net Amount, Credit Amount, Debit Amount and Grand Total, which are variable fields i.e., may vary from transaction to transaction.

The report would also carry a standard template that would essentially have display terms like User ID, Run Date, Report Title etc.

These display terms would remain constant for all Collection Summary Reports. It is these display terms that are to be entered in the header section.

All the boilerplate display names are internally linked to their respective tables to display the data.

Report Code

Select from the LOV, the report code.

Title Eng.(Title in English)

This field displays the title for the report code in English.

For

This field displays the English title for the report code in the chosen second language.

Title Eng (Title in English)

This field displays the title for the report in English.

For

This field displays the title for the report in the chosen second language.

Date Eng.(Date in English)

This field makes the system display the date for the report in English. The Run Date entered selects the date of transaction as the date. Date would be mostly used in reports that are generated in a periodical manner (weekly, monthly etc) and would make the application generate the date of report taking appear in the field.

For

This field displays the date for the report in the chosen second language.

User Eng.(User in English)

This field displays the user name for the report in English.

For

This field displays the user name in the chosen second language.

Page Eng.(Page in English)

This field displays the page number for the report in a particular sequence (page x of y, page etc) in English.

For

This field displays the page number in the chosen second language.

Repld Eng.(ReplID in English)

This field displays the report ID for the report in English.

For

This field displays the report ID in the chosen second language.

TAB Column Headings

A report would have multiple columns. Use the column headings tab to enter the display names for all the columns. The system allows user to have as many as 60 different column names.

Column Headings 1-10	Column Headings 11-20	Column Headings 21-30	Column Headings 31-40	Column Headings 41-50	Column Headings 51-60
Head1	MARINE CARGO CERTIFICATE NO		F_MARINE CARGO CERTIFICATE No.		
Head2	NAME OF CONTRIBUTOR		F_NAME OF CONTRIBUTOR		
Head3	ADDRESS		F_ADDRESS		
Head4	VOYAGE AND CONVEYANCE		F_VOYAGE AND CONVEYANCE		
Head5	DESCRIPTION OF CARGO		F_DESCRIPTION OF CARGO		
Head6	BANK AND L/C NO		F_BANK AND L/C NO		
Head7	VALUE DECLARED		F_VALUE DECLARED		
Head8	BASIS OF VALUATION		F_BASIS OF VALUATION		
Head9	SUM INSURED		F_SUM INSURED		
Head10	TERMS OF COVERAGE		F_TERMS OF COVERAGE		

Fig. 164 – Reports Column Headings Tab

The number of columns in a report is based on its scope.

	The second field (marked in red) displays the same column names in the second language.
---	---

Parameters

Reports need to be generated based on certain parameters. It is possible to map these parameters to the column headings by using this tab. Click Parameters button. The following drop-down menu is displayed. (as highlighted in red color).

Column Headings 31-40	Column Headings 41-50	Column Headings 51-60
	F_MARINE CARGO CERTIFICATE No.	
	F_NAME OF CONTRIBUTOR	
	F_ADDRESS	
	F_VOYAGE AND CONVEYANCE	
	F_DESCRIPTION OF CARGO	
	F_BANK AND L/C NO	
	F_VALUE DECLARED	
	F_BASIS OF VALUATION	
	F_SUM INSURED	
	F_TERMS OF COVERAGE	

- Column Headings 1-10
- Column Headings 11-20
- Column Headings 21-30
- Column Headings 31-40
- Column Headings 41-50
- Column Headings 51-60
- Column Headings 61-70
- Column Headings 71-80
- Column Headings 81-90
- Column Headings 91-100
- Parameters
- Others

Fig. 165 – Reports – Parameter Tab

Select Parameters. The following screen is displayed.

Id	From Eng	To	From For	To
186800				

Fig. 166 – Parameter screen

ID

Based on the Report Code selection in the header block, an ID is displayed here by default.

From English

Enter the 'From' parameter information to be displayed as boiler plate heading in run time in this field.

Example: Enter a standard report parameter such as From Date, From Main A/C Code and From Department Code.

To English

Enter the 'To' parameter information to be displayed as boiler plate heading in run time in this field.

Example: Enter any standard report parameter like To Date, To Main A/C Code, To Department Code etc.



- ☐ The 'From For' and 'To' fields enables the application to display the report ID in the chosen second language.
- ☐ If there are more parameters to add, add them in the Others tab.

USER APPROVAL SETUP

Approvals play a significant role in any transactions and without them the transaction is not processed to the next stage. As the transactions vary (Claim, New Policy.), the authorizing group also varies. In User Authorization, the user defines the properties incorporated in the authorization process to be carried out for an instance code and a policy code along with field information on the variants and the parameters.

Click 'User Approval Setup' menu to view the following screen:

INSURANCE CO LTD

User Authorization Setup

Group Id* MEA

User Id* ADMIN PREMIA Administrator

General Underwriting Claims Reinsurance Appl. Endt.

Modify Cust Detail Y/N ☐

Modify Tax Y/N ☐

Fig. 167 – User Authorization Setup



Group Id

Enter the Group Id to which the user authorization needs to be allotted.

User Id

Select from the LOV, the User Identification details. The user name pertaining to the user identification is displayed in the adjacent field.

TAB General

☒ Modify Cust Detail YN

Select the check box to specify whether the user is allowed to modify the customer details.

☒ Modify Tax YN

Select the check box to specify whether the user is allowed to modify the tax details.

TAB Underwriting

Click 'Underwriting' tab to view the following screen:

Fig. 168 – User Authorization – Underwriting

The Underwriting section allows the user to set the properties for each and every field employed all through the application.

Fields on the Left side

- ☐ Class Code – The line of business is selected from the LOV
- ☐ Maximum Risk Level LC Discount Value – The maximum amount to be discounted from the premium during risk is entered here
- ☐ Maximum Policy Level LC Discount Value – The maximum amount in local currency to be discounted from the premium during risk is entered here
- ☐ Maximum LC Policy SI Value – The maximum sum insured value for the Policy is specified here
- ☐ Maximum Policy Level Discount % – Enter the maximum discount percentage to be given for a premium
- ☐ Maximum Risk Level Discount % – Enter the maximum risk discount percentage to be given for a claim
- ☐ Override Broker Commission % Y/N – This field allows the user to override the broker commission percentage defined by someone already
- ☐ Maximum Broker Commission % – Enter the maximum amount for broker commission
- ☐ Broker Modifiable Type – The four options listed in the drop down list are
 - o Modify entire block – This feature allows the user to modify the entire block
 - o Modify only Broker Commission Amount – This feature allows the user to modify only the Broker commission amount
 - o Modify All except Broker Commission Percentage – This feature allows the user to modify all the details except the broker commission percentage

oNone of the fields are modifiable – This feature when selected, no modifications are possible

☐ Modify Coinsurance Business Type Y/N – This field is selected if the type of business needs modification. The two available options are:

☐ Direct with coinsurance

☐ Direct without coinsurance

☐ Modify Default A/c Segment Y/N – This field allows the user to modify the default account segment

☐ Modify Exchange Rate Y/N – If the exchange rate is set to be modifiable then this field is marked

Fields on the Right side

☐ Modify Deductible Y/N – This field is selected if the deductibles are to be made modified

☐ Override Discount Loading Y/N – This field enables the user to override the discount loading defined already

☐ Approve Policy Y/N – If the approval of policy is to be queried during the time of approval, then this field is marked

☐ Approve Long Term Policy Y/N

☐ Modify Issue Date. Y/N – This field is marked in order to modify the date of issue of policy

☐ Back Dating Policy From Date Y/N – If there is back dating in the policy then this field is to be marked

☐ Back Dating Policy Issue Date Y/N – This field allows the user to back date the policy issue date if necessary

☐ Convert Quotation to Policy Y/N – In order to convert quotation to policy, this field is marked to query for acceptance

☐ Modify A/c Gen Type Y/N – If the account generation type is to be modified then this field is marked

☐ Modify Issue Date Y/N – This field allows the user to modify the issue date

☐ Renew Policy Y/N – This field is marked to ensure the renewal of policy

TAB Claims

Click 'Claims' tab to view the following screen. Through this block the issues regarding claims are set.

User Authorization Setup

Group Id* MEA

User Id* ADMIN PREMIA Administrator

General Underwriting Claims ReInsurance Appl. Endt.

Class Code* 90 Oil and Gas

Approve Broker Licence Expired Claims Y/N ☒

Claim Close Reopen Y/N ☒

Claim Estimate Creation Allow Y/N ☒

Appr. Req'd. For Intrn Date Outside the Period Y/N ☒

Claim Approval or Modify Y/N ☒

Allow Duplicate Claims on same loss Date ☒

Maximum LC Claim (Approval)

Maximum LC Claim (Estimate)

Claim Settled Allow Y/N ☒

Estimate Close Allowed Y/N ☒

Maintenance Period Claim Y/N ☐

Claim beyond the Notification Period Y/N ☐

Allow Claim when Risk is in Silent Period Y/N ☐

Fig. 169 – User Authorization – Claims

Class Code: The line of business is selected from the LOV.

- ☐ Approve Broker License Expired Claims Y/N – This field allows the user to approve the broker license expired claims if selected
- ☐ Claim Close Reopen Y/N – This field allows the user to reopen the closed claim if selected
- ☐ Claim Estimate Creation Allow Y/N – This field allows the user to create the claim estimation if selected
- ☐ Approve. Required. For Intimation Date outside the Period Y/N – This field allows the user to approve required for intimation date outside the period if selected
- ☐ Claim Approval or Modify Y/N – This field allows the user to approve or modify the claim if selected
- ☐ Allow Duplicate Claims on same loss Date – This field allows the user to enter duplicate claims on same loss date if selected
- ☐ Maximum LC Claim (Approval)
- ☐ Maximum LC Claim (Estimate)
- ☐ Claim Settled Allow Y/N – This field allows the user to settle the claim if selected
- ☐ Estimate Close Allowed Y/N – This field allows the user to estimate close allowed if selected

TAB Reinsurance

Click 'Re-insurance' block to view the following screen. This screen allows the user to select the options for fields regarding Re-insurance.

User Authorization Setup

Group Id* MEA

User Id* ADMIN PREMIA Administrator

General Underwriting Claims **ReInsurance** Appl. Endt.

Approve FAC RI Y/N ☒

Modify Treaty Allocation Y/N ☒

Re-insurance allocation allowed Y/N ☒

Modify CQS% Y/N ☒


Modify Inward CQS% Y/N ☒

Fig. 170 – User Authorization – Reinsurance

- ☐ Approve FAC RI Y/N – Select this checkbox if facultative reinsurance has to be approved
- ☐ Modify Treaty Allocation Y/N – Select this checkbox if treaty allocation has to be modified
- ☐ Re-insurance allocation allowed Y/N – Select this checkbox if re-insurance allocation has to be allowed
- ☐ Modify CQS% Y/N – Select this checkbox if compulsory quota share has to be modified
- ☐ Modify Inward CQS% Y/N – Select this checkbox if inward compulsory quota share has to be modified

TAB Appl. Endt.

Click 'Applied Endorsement' block to view the following screen. This screen enables the user to select the endorsement type and map it to the user.



User Authorization Setup

Group Id* MEA

User Id* ADMIN PREMIA Administrator

General Underwriting Claims Reinsurance **Appl. Endt.**


Endt. Type*	Endt. Description	End Type Allowed Y/N?
013	Change in Broker / Agent	☒
006	Reduction of Period	☒
		☐
		☐
		☐
		☐
		☐
		☐
		☐
		☐
		☐
		☐
		☐
		☐
		☐

Fig. 171 – User Authorization – Applied Endorsement

- ☐ Endorsement. Type – Select the type of endorsement from the LOV as per the requirement
- ☐ Endorsement. Description – Endorsement description is defaulted once the Endorsement type is selected
- ☐ Endorsement Type Allowed Y/N – This field is marked when the endorsement type is allowed for the transaction

USER GROUP ID

This menu allows the user to create new user group. Click 'User Group Id' menu to view the following screen:



User Group Id

INSURANCE CO LTD

3i Infotech
Innovation • Insight • Integrity

PREMIA
On Risk Control

Authorization Group Master

Group Id MEA

User Id*	User Desc
BD01	BD USER
PDC01	PDC USER
RIU01	RIU01

Fig. 172 – User Group ID

Group Id

Enter the Group Id to which the users have to be allotted.

User Id

Select from the LOV, the user to be mapped with the group.

User Name

The user name pertaining to the user identification appears in the adjacent field.

WORKFLOW / DMS SETUP

Workflow Management System (WMS) is a user-friendly application which is integrated with PREMIA application. Based on the user login for the PREMIA interface, this application revolutionizes form opening, flexibility and navigability during the 'Underwriting' and 'Claims' stages of a transaction.

Workflow steps defined here facilitates the user to complete an underwriting transaction for the defined users – quotation with Scheduler, conversion of quotation to policy, approval of policy with Scheduler, completion, endorsement, Renewal RI Confirmation and RI approval.

User is able to complete a claims transaction in PREMIA based on the various defined workflow steps for the defined users - claims intimation entry, claims registration entry and approval, reserve entry and approval, settlement entry and approval.

The workflow process is explained in steps given below:

Step 1 – Enable Workflow/DMS related System parameter

To enable the Work Flow DMS,

User needs to enable certain system parameters in 'System Parameter' screen –

- ☐ WF_SCH_YN – Quotation Scheduler is required or not in workflow. When set as '1', the quotation/policy scheduler is attached in the mail.
- ☐ WF_DMS_YN – Workflow / DMS is required or not. When set as '1', the Workflow Remark button gets enabled in all the transaction screens
- ☐ WF_ENBL_YN – 1--Work Flow is enabled, 0--Work Flow is disabled
- ☐ DMS_APPL_YN – If set as '1', then Image Upload is disabled and DMS icon is enabled in all the transaction screens.
- ☐ UP_REP_PATH – To set the report bin path for mail and scheduler

The System Parameter screen as shown below:

Parameter Code	Parameter Sub Code	Parameter Name	Parameter Value	Upd
DMS_APPL_YN	DMS_APPL_YN	DMS_APPL_YN	0	☒
WF_DMS_YN	WF_DMS_YN	Workflow/DMS is required or not	0	☒
				☐
				☐
				☐
				☐
				☐

Remark: 0-WF/DMS is not used/1-WF/DMS is used

Fig. 173 – Parameter Setup for Workflow

Once the DMS parameter is enabled the system disables the 'Image Upload' button and enables the DMS WORK FLOW button.

Step 2 – Define the Bucket Code based on Transaction

The system displays the screen as shown below:

Code	Main Bucket Code	Workstep Id	Description	Sr No	Enable Yn	Mail Only Yn	SMS Yn
REND	UNDERWRITING	REINST_ENDORSEMENT_A	Reinst Endorsement Approval	9	☒	☐	☐
CSD	CLAIMS	CSD	CSD	15	☐	☐	☐
CSA	CLAIMS	CSA	CSA	14	☐	☐	☐
CSE	CLAIMS	CLAIM_SETTLEMENT_ENTR	Claim Settlement Entry	13	☐	☐	☐
EC	CLAIMS	ESTIMATE_CLOSE	Estimate Close	16	☐	☐	☐

Fig. 174 – Workflow/DMS Setup

☐ Work Flow and DMS Enable YN – Select the check box to enable workflow and DMS in the transaction flow

☐ Work Flow Enable YN – Select the check box to enable work flow only during the transaction

TAB Bucket Code

Click this tab to set the bucket codes (list of transactions in the workflow – Policy Entry, Renewal, Claim Intimation, RI Confirmation and so on).

For every workflow step there is a code (REND) mapped to a bucket code (UNDERWRITING) with work step Id (REINST_ENDORSEMENT_APPRL) and its description in chronological order (Reinst Endorsement Approval).

Code	Main Bucket Code	Workstep Id	Description	Sr No	Enable Yn	Mail Only Yn	SMS Yn
REND	UNDERWRITING	REINST_ENDORSEMENT_A	Reinst Endorsement Approval	9	☒	☐	☐
CSD	CLAIMS	CSD	CSD	15	☐	☐	☐
CSA	CLAIMS	CSA	CSA	14	☐	☐	☐
CSE	CLAIMS	CLAIM_SETTLEMENT_ENTR	Claim Settlement Entry	13	☐	☐	☐
EC	CLAIMS	ESTIMATE_CLOSE	Estimate Close	16	☐	☐	☐

Fig. 175 – Bucket Code

Code

The system displays the defined bucket codes.

Main Bucket Code

The system displays the corresponding transaction screen for specific bucket 'Code'.

Workstep Id

The system displays the description corresponding to the bucket 'Code'

Sr No

The system displays the order in which the work steps needs to be displayed in the Workflow Inbox screen.

☒ Enable YN

On selecting this check box, for the specific 'CODE', the selected transaction gets enabled for WORKFLOW.

☒ Mail Only YN

Select this check box to trigger Mail to the respective mapped users.

☒ SMS YN

Select this check box to send message to the respective mapped user's mobile numbers.

TAB Work step Mapping

Click this tab to view the list of field columns that are mapped to the specific Bucket code.

Code	Process Id	Workstep Id	Rule Id	Table Name*	Rule Param Id*	Ret. Type
REND	UNDERWRITING	REINST_ENDORSEMENT	Dept Name	PGIT_POLICY	POL_DEPT_NAME	3
REND	UNDERWRITING	REINST_ENDORSEMENT	Customer Code	PGIT_POLICY	POL_CUST_CODE	3
REND	UNDERWRITING	REINST_ENDORSEMENT	Customer Contact N	PGIT_POLICY	CUST_CONTACT_1	3
REND	UNDERWRITING	REINST_ENDORSEMENT	Customer Email ID	PGIT_POLICY	CUST_EMAIL1	3
REND	UNDERWRITING	REINST_ENDORSEMENT	Endorsement Name	PGIT_POLICY	POL_END_CODE	3

SQL Statement: SELECT DEPT_NAME FROM FM_DEPARTMENT,PGIT_POLICY WHERE POL_SYS_ID = P_VALUE_1 AND DEF

Field 1: POL_SYS_ID Field 4:
Field 2:
Field 3:
Field 5:

Fig. 176 – Work step Mapping

The system displays the following field details:

- ☐ Code – The selected Bucket code
- ☐ Process Id – The description of the main bucket code
- ☐ Workstep Id – The work step identification
- ☐ Rule Id – Displays the corresponding fields available in the workstep screen
- ☐ Table Name – Displays the corresponding fields available in the PREMIA database table
- ☐ Rule Param Id – Displays the respective Table name - Id
- ☐ Ret Type – Displays the table number to Retrieve the data

TAB Mail User Group

Click this tab to map the Mail User Group with single code (") to the bucket code. If there is more than one group then user needs to use a COMA (,) and then continue to map to the group.

Bucket Code*	Description	Appr. Sts*	Description	WF Sts.*	Description	Mail Usgrp	Usgrp To Modify	Esc Usgrp 1	Esc Usgrp 2
REND	Reinst Endorsement Approval	C	Complete			'MEA','RIG','UM'	BD01','RIU01'		

Fig. 177 – Mail User Group

Bucket Code

The system displays the action of the transaction workflow. For example for Quotation Approval the Bucket code will be displayed as 'QA'.

Appr Sts (Approval Status)

Select from the LOV the approval status of the task.

- ☐ C – Complete
- ☐ A – Approval
- ☐ I – Incomplete
- ☐ RI – RI Confirmation

Mail Usgrp

To attach users / multiple users who will receive the mail based on the transaction workflow by using a comma.

Workflow Status

Select from the LOV, the status of the workflow. For example, if the approval status is I- Incomplete, the user needs to select the workflow status as 'MI- Missing Info' and so on.

Usgrp To Modify

The users mapped under the respective user group. If there is more than one user, then user needs to use a COMA (,) and then continue to map to the user group

Esc Usgrp 1 / 2 (Escalation user group)

If bucket 'Code' is selected as 'EC', then enter the user group and respective users with single quote. If more than one user group or users; continue to map with commas.

Step 3 – Map User's Approval

Click Master ➤ Application Setup ➤ User Group Id. In the User Group Id screen, map the users to the respective User Groups (Group Id). Based on the User Group available in the LOV, the User Id will default.

Step 4 – Map E-mail Id to respective User / User Group to trigger mails

Click Master ➤ Admin and Tools ➤ User.

Enter the E-mail ID to map the mail group id (Mail Usgrp) for the user group as shown below:

The screenshot shows the 'User Group Id' screen. The 'User ID' field is highlighted with a red box and contains the value 'MEA'. The 'E-mail ID' field is also highlighted with a red box and contains the value 'sathish.murugesan@3i-in'. The 'Menu Group ID' field contains 'MEA' and 'SEC'. The 'Security Group ID' field contains 'SEC'. The 'E-mail ID' field has a 'Copy' button next to it. The 'Mobile No' field is empty. The 'Printer Code' field is empty. The 'Printer Format' field is empty. The 'Copies' field is empty. The 'Default Location' field is empty. The 'Default Language' field is empty. The 'Start Menu ID' field is empty. The 'Flex Fields' section shows 'Company', 'Branch', and 'Department' tabs. The 'Code' and 'Name' columns are visible, with '001' and 'INSURANCE CO LTD' listed. The 'Default ?' column has a checkbox checked for '001'.

Fig. 178 – Mail Group Id

The next step is to map the mail id to the users coming under User group (Usgrp To Modify)

Step 5 – Capture mobile number to trigger SMS to user / user group

Enter the Mobile number in the User screen (ensure that the mobile number is linked with the company's service provider to trigger the SMS).

Step 6 – Configure Workflow setup in DMS application

Logon to PREMIA DMS application with the user login credentials as shown below:

Fig. 179 – PREMIA DMS - Login screen

Enter the User Id and Password to logon to the application. The Welcome page is displayed as shown below:

Fig. 180 – PREMIA Workflow Menu

The menus available are:

- ☐ Workflow
 - o Email Template
 - o View Email History
 - o Turn Around Time
- ☐ Admin
 - o Maintain User
 - o Upload User
 - o Maintain Folder Mapping

Workflow

E-mail Template

Click this menu to create own template. The system displays the screen as shown below:

The screenshot shows the 'Template for Worksteps' screen. At the top, there's a header with the Infotech logo, a language dropdown set to 'English', a 'MENU' button, and a 'User Id : DOL_SUPERVISOR' label with a 'Logout' link. Below the header is a table with columns: Process Id, Workstep, Approval Status, Workflow Status, and User Group. The table lists several 'UNDERWRITING' worksteps, all with 'Ready to Convert to Policy' as the workstep and 'A' as the approval status. The 'User Group' column shows 'CUSTOMER', 'UWG', 'Escalation', 'Origin', and 'SMS'. A red box highlights the first row's checkbox. To the right of the table is a 'Fields' dropdown menu with 'Create User Name' selected, an 'Insert' button, and a 'Subject' field containing 'Quotation Approval'. Below these is a 'Save' button. The bottom half of the screen is a rich text editor with a toolbar and a text area containing a draft email template with placeholders like '<%POL_CUST_NAME%>', '<%POL_NO%>', and '<%POL_PREM_LC_1%>'.

Fig. 181 – E-Mail Template

The header screen displays the Template for Work steps with Process Ids, Approval & Workflow Status along with the User Group Name.

Checkbox

Select the check box against the specific Process Id to create the e-mail template.

Fields

The system displays the list of field names to be inserted in the e-mail template.

Subject

Based on the work step the system displays the subject for the e-mail template being created.

Enter the body text for the e-mail in the white space.

Insert

Click this button to select and insert the field name to be entered the body text of the e-mail.

Click 'Save' to save the e-mail template. The template is saved successfully.




Fig. 182 – Success Message

View E-mail History

Click this menu to view the History details of the e-mail transactions sent to user/usergroups.

View Email History

English MENU User Id : DOL_SUPERVISOR Logout

CLAIMS

Claim Intimation

To	Subject	Date	Time	
sathish.murugesan@3i-infotech.com	Intimation of your Claim No. CN50030000016	12/11/2013	19:13:07	View
marichetty.sreenivasulu@3i-infotech.com	Intimation of your Claim No. CN50030000014	23/09/2013	17:08:58	View

Claim Closure

To	Subject	Date	Time	
marichetty.sreenivasulu@3i-infotech.com	Alert- Claims close	23/09/2013	17:54:43	View
marichetty.sreenivasulu@3i-infotech.com	Alert- Claims close	23/09/2013	17:39:49	View
sathish.murugesan@3i-infotech.com	Alert- Claims close	12/09/2013	19:37:33	View

Claim Registration

UNDERWRITING

Ready to Convert to Policy

To	Subject	Date	Time	
sathish.murugesan@3i-infotech.com	Quotation Approved	13/11/2013	13:18:52	View
marichetty.sreenivasulu@3i-infotech.com	Quotation Approved	04/10/2013	12:52:51	View
marichetty.sreenivasulu@3i-infotech.com	Quotation Approved	04/10/2013	12:27:33	View
marichetty.sreenivasulu@3i-infotech.com	Quotation Approved	24/09/2013	12:40:50	View

Fig. 183 – View E-mail History

Click 'View' to view the log file.

Filter

Click 'Filter' button to search for e-mails based on the search criteria as shown below:

Filter -- Webpage Dialog

To:

Subject:

From Date: ...

To Date: ...

Fig. 184 – Filter Criteria

Turn Around Time

Click this menu to set the turnaround time for the user and set the shift time at various workflow stages. The system displays the screen as shown below:

The screenshot shows the 'Shift Time / Turn Around Time' configuration screen. The 'Turn Around Time' tab is selected. The screen displays a table of workflow steps with their respective turnaround times and 'Edit' links. A mouse cursor is hovering over the 'Edit' link for 'Claim Settlement'.

Workflow Step	Turnaround Time	Action
Claim Reopen	0 day(s) 0 hr(s) 0 min(s)	Edit
Claim Registration	0 day(s) 0 hr(s) 1 min(s)	Edit
Claim Registration	0 day(s) 0 hr(s) 1 min(s)	Edit
Claim Registration with survey	0 day(s) 0 hr(s) 0 min(s)	Edit
Claim Registration Entry	0 day(s) 0 hr(s) 1 min(s)	Update Cancel
Claim Settlement SMS	0 day(s) 0 hr(s) 1 min(s)	Edit
Claim Settlement	0 day(s) 0 hr(s) 1 min(s)	Edit
Claim Settlement	0 day(s) 0 hr(s) 0 min(s)	Edit
Claim Settlement Entry	0 day(s) 0 hr(s) 0 min(s)	Edit

GL

Workflow Step	Turnaround Time	Action
Journal Voucher	0 day(s) 0 hr(s) 1 min(s)	Edit

UNDERWRITING

Workflow Step	Turnaround Time	Action
Quotation Entry	0 day(s) 0 hr(s) 1 min(s)	Edit
Quotations Pending for Approval	0 day(s) 0 hr(s) 0 min(s)	Edit
Endorsement Initiation	0 day(s) 0 hr(s) 1 min(s)	Edit
Ready to Convert to Policy	0 day(s) 0 hr(s) 1 min(s)	Edit
New Policies Converted From Quotation	0 day(s) 0 hr(s) 1 min(s)	Edit
Policy Entry	0 day(s) 0 hr(s) 0 min(s)	Edit
RI Confirmation	0 day(s) 0 hr(s) 1 min(s)	Edit

Fig. 185 – Turn Around Time

TAB Turn Around Time(TAT)

Click this tab to set the TAT.

Click 'Edit' to edit the turnaround time for the specific workflow step.

TAB Shift Time

Click this tab to set the shift timings and to set holidays for the month and also working hours for the week:

English

Menu

User Id : DOL_SUPERVISOR

Logout

Shift Time Turn Around Time

Working Time

	From	To	
Sunday	9.00	18.00	Clear
Monday	9.00	18.00	Clear
Tuesday	9.00	18.00	Clear
Wednesday	9.00	18.00	Clear
Thursday	9.00	18.00	Clear
Friday	9.00	18.00	Clear
Saturday	9.00	18.00	Clear

Holiday Details

List of Holiday(s)

30/11/2013=>Holiday

Date

Reason

Fig. 186 – Shift Time and Turn Around

Enter the 'Working From / To' against the days specified.

Enter the 'Date & Reason' in the Holiday Details block.

Click 'Clear' to clear the details.

Click 'Add' to add the entered holidays in the 'List of Holiday(s)' block.

Click 'Save' the details. The data is saved successfully.

Admin

Maintain User

This menu enables the Admin user to assign users to the workflow groups and provide user rights. Also to synchronize the new user rights with the PREMA database.

The system displays the screen as shown below:

		Group	User / UserId	User Rights	Flag
Delete	Edit	CLMG	CLM01	ADEIMP	E
Delete	Edit	CLMG		D	E
Delete	Edit	MEA	BDD01	DEIM	U
Delete	Edit	MEA	PDC01	DEIMP	E
Delete	Edit	RIG	RIU01	DEIMP	E
Delete	Edit	UWG	UW01	DEIMP	E

Fig. 187 – Maintain User

User Group

Select the user group from the drop-down list to assign the user(s).

User Id

Select the user id check box (es) to assign user to the user group.

User Rights

The system displays the list of user rights available in the system. Select the required check box to enable the right to perform the action.

- ☐ Admin
- ☐ Export
- ☐ Index
- ☐ Delete
- ☐ Modify
- ☐ Print
- ☐ All

Product

Select the product to assign the users under the user group.

Add

Click 'Add' to add the users to user group. The data is added successfully as shown below:

Maintain User

User Group:

User Id:

User Rights:

- ☐ Admin
- ☐ Export
- ☐ Index
- ☐ Delete
- ☐ Modify
- ☐ Print
- ☐ All

Product:

		Group	User / UserId	User Rights	Flag
Delete	Edit	CLMG	CLM01	DIM	U
Delete	Edit	CLMG		D	E
Delete	Edit	MEA	BDD01	DEIM	U
Delete	Edit	MEA	PDC01	DEIMP	E
Delete	Edit	RIG	RIU01	DEIMP	E
Delete	Edit	UWG	UW01	DEIMP	E

Fig. 188 – Maintain User – new user added

The lower grid in the screen displays the list of Group with User/user id and User rights.


Flag

The flag shows the assigned privileges to User id's under the User group.

- ☐ A – All rights
- ☐ U – Except Admin rights
- ☐ E – Not synchronized

Synchronize

Click this button to synchronize the newly added user with PREMIA database. After doing the synchronization, the status of the Flag is displayed as 'E'. The Data is synchronized successfully.




The screenshot shows the 'Maintain User' interface. At the top, there's a header with the Infotech logo, language dropdown (English), and user ID (DOL_SUPERVISOR). The main area has a 'User Group' dropdown set to 'CLMG' and a 'User Id' list containing 'CLM01' and 'CLU01'. To the right, there's a 'User Rights' section with checkboxes for Admin, Export, Index, Delete, Modify, Print, and All, along with an 'Add' button. Below this is a 'Product' dropdown set to 'CLAIM'. A 'Synchronize' button is located below the 'User Rights' section. At the bottom, there's a table with columns: Group, User / UserId, User Rights, and Flag.

	Group	User / UserId	User Rights	Flag
Delete Edit	CLMG	CLM01	DM	E
Delete Edit	CLMG		D	E
Delete Edit	MEA	BD01	DEMP	E
Delete Edit	MEA	BDD01	DEIM	E
Delete Edit	MEA	PDC01	DEMP	E
Delete Edit	RIG	RIU01	DEMP	E
Delete Edit	UWG	UV01	DEMP	E

Fig. 189 – Synchronize

Upload User

This menu enables to upload .csv file containing user data into PREMIA database. The system displays the screen as shown below:



The screenshot shows the 'Upload User' interface. It features a 'User Synchronization' form with a 'CSV File Name' input field and a 'Browse...' button. Below the input field is a 'Synchronize' button. The interface also includes the Infotech logo, language dropdown (English), and user ID (DOL_SUPERVISOR) at the top.

Fig. 190 – Upload User

Maintain Folder Mapping

This menu enables the user to assign and un-assign folder access to users/user groups. The system displays the screen as shown below:

Group Id	User Id	Folder	Flag
MEA	BD01	BD01	E
MEA	PDC01	PDC01	E
RIU	RIU01	RIU01	E
UWG	UW01	UW01	E

Fig. 191 – Mapping Folder(s) to User

Step 7 – Perform Workflow Transaction

Login to PREMIA application with the user login attached to Workflow (User Group Modify).

Go to Transaction screen to view the DMS icon enabled and the Workflow Remark button (as highlighted and shown below).

Fig. 192 – PREMIA Quotation Screen



☐ DMS icon is enabled when the system parameter is set as '1' for DMS_APPL_YN

☐ Workflow Remarks is enabled when the system parameter is set as '1' for

WF_DMS_YN

Step 8 – Transaction Using DMS

The screens displayed below shows the Bucket Code, Mail User Grp defined and the configured e-mail id for Quotation Approval Process.

WorkFlow / DMS Setup

Work Flow Enable Y/N ☒
Work Flow and DMS Enable Y/N ☒

Bucket Code **Workstep Map.** **Mail User Grp.**

Code	Main Bucket Code	Workstep Id	Description	Sr No	Enable Yn	Mail Only Yn	SMS Yn
PA	UNDERWRITING	POLICY_APPROVAL	Approved Policies	7	☒	☒	☒
					☐	☐	☐
					☐	☐	☐
					☐	☐	☐

Bucket Code **Workstep Map.** **Mail User Grp.**

Bucket Code*	Description	Appr. Sts*	Description	WF Sts.*	Description	Mail Usgrp	Usgrp To Modify	Esc Usgrp 1	Esc Usgrp 2
PA	Approved Policies	C	Complete			MEA;RIG;UM	PDC01;BD01		

3i Infotech
Innovation • Insight • Integrity

INSURANCE CO LTD

PREMIA
One Risk Control

User ID

BD01

Description

BD USER

Password

Re Confirm Pwd

Option

☒ View
☐ Print
☐ Save

Login Count

0

Administrator Y/N

☒

Lock User Y/N

☐

Override Y/N

☒

Start Menu ID

*

User Session Count

999

BI-Lingual Display Y/N

☒

Profile ID

EQC Test

Reporting To

Menu Group ID

MEA

Security Group ID

Telephone No

Fax No

E-mail ID

saraswathy.shrikanthan@

Mobile No

9884185505

Printer Code

Copies

Default Location

Default Language

ENG

Tel Extn

Printer Format

Copy

Flex Fields

Company

Branch

Department

Code	Name	Default ?
001	INSURANCE CO LTD	☒
		☐
		☐
		☐

Fig. 193 – Transaction Screens for DMS

Now, approve the Policy to view the complete status.

INSURANCE CO LTD

New Policy / Complete

Created by: BD01 Approved by: BD01 Accounting date: 21/11/2013 18:23

Branch Code* 100 Department* 50 Product* 5003 Personal Accident

Policy Type* 5003 Personal Accident Business Type* 1 Direct without coinsurance

Policy No P/100/5003/2013/00228 Index no 0 Quotation Number Q/100/5003/2013/0 Quot Rcvd Dt 21/11/2013 00:00

Customer* AG0000006 Mr.Madhivanan Balakrishnan.M Insured* 148 Mr.Madhivanan Balakrish M Insured Det...

Source Type* 2 Agent Source Code* AG0000006 Mr.Madhivanan Balakrishnan.M

Unit* Day Period 365 Pol. Issue Dt 21/11/2013 18:10 Period From 21/11/2013 16:00 To 21/11/2014 15:59

Prem Calc Type* 3 Normal/Annual SI Curr.* 001 US DOLLAR Prem. Curr.* 001 US DOLLAR

Mode of Payment* CC Credit Customer Instl. Y/N Method* No

Hypothecation Y/N Pre Insp Req Y/N Our Share : % SI. Prem.

Territory/Jurisdiction Issued At Head Office Social Security ID* 121545 Old Pol No.

Address Risk Dtls Other Details CBC Y/N

Address Mumbai

Area*

State*

Country*

Outstanding Det...
Workflow Remar...
Acnt. Query
Doc. Print
Prem.Comp.Sheet
Approve
Copy
Endorsement
RI Details
Treaty Allocation
FAC Placement
Image Upload
Totals
Entry Complete
Revert Entry
RiskTotals
UW Rules

Fig. 194 – Policy Transaction – Complete status

An e-mail is triggered to the configured user e-mail id with the Policy Scheduler attachment along with e-mail template mapped in Workflow. The screen as shown below:

Sub:- Policy Approval - Message (HTML)

From: jayapal.reddy@3i-infotech.com Sent: Thu 11/21/2013 6:36 PM

To: saraswathy.shrikanthan@3i-infotech.com

Cc:

Subject: Sub:- Policy Approval

Message P-100-5003-2013-00228-165536.pdf (160 KB)

Dear Origin

This is to inform you that Policy Number P/100/5003/2013/00228 having a sum insured of (100000) has been issued. The relevant details are as under.

1. Office code and Name : 100 - Head Office
2. Name of Insured : Mr.Madhivanan Balakrishnan
3. Sum Insured : 100000
4. Policy Period : 21/11/2013 To 21/11/2014
5. Premium : 10000
6. Product : Personal Accident

E-mail Template

This is for your information and record. This is the system generated email, kindly donot reply.

Now, click the DMS icon to view the dashboard of the particular line of business.




Fig. 195 – DMS Dashboard

Click the work step (as highlighted and shown above) to view its timeline breakups.

Menu

Click Menu hyperlink. Based on login user rights, the DMS application displays the corresponding menus as shown below:




Fig. 196 – DMS – Menu Listing

Scanning

- ❑ Scanning –To scan documents through Scanner and link to the transaction or upload to Inbox

- ☐ Import – To import image / Non Image (PDF, Ms Word, Excel etc) and link it to the transaction or upload to Inbox
- ☐ Report – Report showing the failed uploaded document list which can be re-uploaded

Document Inbox

- ☐ Document Inbox – Displays user based documents Inbox. User can link to the transaction or forward the selected document to other users

Linked Docs

- ☐ Linked Docs – View the linked documents of that transaction
- ☐ Search – Search documents attached to other transaction with various search criteria within the Module
- ☐ Global Search – Search documents attached to other transaction with various search criteria across the Module

Workflow

- ☐ In Box – View the workflow items of the user and perform necessary action
- ☐ View Email History – View the Email sent to user / customer from DMS application (Only for Admin User)
- ☐ Turn Around Time – Set Turnaround time / Holiday calendar for the work flow process (Only for Admin User)

REINSURANCE

MASTERS

Refer Reinsurance User Manual for more information on RI Masters.

SETUP

Refer Reinsurance User Manual for more information on RI Setup.

ADMIN AND TOOLS

Introduction

The 'Admin and Tools' module enables the user to

- ☐ Create Users
- ☐ Create User Groups
- ☐ Assign rights to a User
- ☐ Define Menus
- ☐ Assign Menu Privileges to the Users
- ☐ Create Instances
- ☐ Create User Profile

The 'Admin and Tools' menu comprises of the following sub-menus:




Fig. 197 – Admin and Tools – Menus and Submenus

MENU ADMINISTRATION

The 'Menu Administration' menu allows the user to customize and map the business processes, create user groups, users and assign privileges to them.

The 'Menu Administration' menu enables the following:

- ☐ Create new users
- ☐ Assign rights to those users
- ☐ Permit or limit the user access to PREMIA application
- ☐ Define Menus
- ☐ Assign Menu privileges to the various levels of users



Only System Administrators are allowed to work on the 'Menu Administration' menu.

User Group

The 'User Group' submenu enables users to create user groups. User Groups are created for providing menu/data access to the Users. Users are attached to the user groups and all the users in a group are given similar menu accesses.



Menu Groups for Data Security are not implemented by using the 'Menu Administration' menu. Since the data security is mandatory for any user in the application, a default Security Group is created and linked to all the users. Data

access is provided by setting up the applicable divisions and departments in the User module.

The 'User Group' screen displayed as shown below.




Fig. 198 – Creating User Groups

Group ID

Enter the name of the new group ID.

Group Description

Enter the description of that group.

Group Type

Click the icon  to display the LOVs for the group types. Two types of group types are defined in PREMIA.

- ☐ Security User Group (S)
- ☐ Menu User Group (M)

Select the group type from the LOV.

Similarly user can create any number of user groups. After creating the new user group, click 'Save' button to save the newly entered details. Click the 'Query' button to view the existing user groups.

User

This screen enables the user to create a User ID for any individual user with menu user privileges and access rights specific to that User ID. This User ID is the identity log for that user to enter into the PREMIA. Only system administrators have rights to create new users, map them to a particular division or department, and to a particular menu group.

Click 'User' menu to create new User ID as shown below.

Fig. 199 – Creating New User Id

User ID

User ID refers to the name with which, a particular user is allowed to login to PREMIA. Enter the User ID. Click LOV to view the existing User IDs.

Description

Enter a description about the user being added to the group.

Password

Enter the password in this field.

Reconfirm Password

Retype the password to confirm it.

Option

- ☐ Select the 'View' option, if the user needs to view only the PREMIA
- ☐ Select the 'Print' option, to view and print while using the PREMIA
- ☐ Select the 'Save' option, to modify the contents within the PREMIA and save those changes

Login Count

Specify the number of failed login attempts allowed for a user before the administrator aborts.

☒ Bilingual Y/N

Select the check box pertaining to this record to allow the user to view the PREMIA in a bilingual mode.

☒ Administrator Y/N

Select the check box pertaining to this record, to allow the user to enjoy all the privileges of an administrator.

☒ Lock User Y/N

Select the check box to lock the account.



The check box gets selected automatically, when the user's login exceeds the number of failed attempts given in the 'Lock after No of Failed Attempts' field in the 'User Profile' screen.

Override Y/N

Select the check box to allow the user to override the existing data.

Start Menu ID

This field refers to the menus that are viewable by the newly created user, once logged into the PREMIA. Select the start menu ID from the LOV. (Click the icon  to display the LOVs for the 'Start Menu ID' field.) The newly created user ID is allowed to see the only the menus starting from the menu ID selected in this field. This will restrict the users from viewing the other menus. On selecting the start menu ID, the textbox displayed adjacent to the start menu ID gets defaulted with the menu ID description.



On selecting the asterisk '*' in the 'Start Menu ID' field, then the newly created user is allowed to view all the menus.

Profile ID

Enter or select the profile id by clicking  button to attach with login user ID. The id description is defaulted in the adjacent field.

Reporting To

Enter or select the users reporting authority by clicking  button. The description is defaulted in the adjacent field.

Menu Group ID

Select the Menu Group ID from the LOV. (Click the icon  to display the LOVs for the 'Menu Group ID' field.) On selecting the menu group ID, the text box displayed adjacent to the menu group ID gets defaulted with the menu group ID's description. A number of users can be attached to a menu group. When user attaches 'n' number of users to the same menu group, all these users are given the same set of privileges.

Security Group ID

Select the security group ID from the LOV. (Click the icon  to display the LOVs for the 'Security Group ID' field.) On selecting the security group ID, the text box displayed adjacent to the security group ID gets defaulted with the security group ID's description.

Telephone No

Enter the user's telephone number in this field.

Tel Extn

Enter the user's telephone extension number in this field.

Fax No

Enter the user's fax number in this field.

E-Mail ID

Enter the user's e-mail ID in this field.

Mobile No

Enter the user's mobile number in this field.

Printer Code

User can map the applicable printer code for the user. Select the printer code from the LOV. (Click the icon  to display the LOVs for the printer code.)

Printer Format

Select the printer format from the LOV. (Click the icon  to display the LOVs for the printer format.) The printer format may be dot matrix, laser jet or ink jet.

Copies

User can restrict the number of prints that a user can take while using PREMIA. Enter the number of copies the user can print.

Default Location

Specify or select the default location from the LOV to which the user is attached.

Default Language

Select the default language code from the LOV. The default language name appears in the textbox adjacent to the textbox displaying the language code.

After entering the user details, the next step is to include the user's company, division and the department details.

TAB Company

After creating the User, the first step is to attach the set user to a company code. This is done by using the 'Company' tab. This tab is enabled by default in the User submenu as shown below.

Code	Name	Default ?
001	INSURANCE CO LTD	☒
		☐
		☐
		☐
		☐

Fig. 200 – User — Company Tab

Code

Select the company code from the LOV.

Name

On selecting the company code, the respective company name to that code appears in the 'Name' field.

☒ Default

Select this check box if the code and the company name entered here are to be defaulted in the login screen.

After entering the values to these fields, click 'Save' to attach the company to the newly created user.

TAB Branch

The 'Branch' tab is used to attach the newly created user to a division within the company.

Click the 'Branch' tab to view the screen as shown below:

Company		Division		Default ?
Code	Name	Code	Name	
001	INSURANCE CO LTD	100	Head Office	☒
				☐
				☐
				☐
				☐

Fig. 201 – Creating New User — Branch Tab

Company Code

Enter or select the company code from the LOV. The company name gets defaulted in the 'Name' field.

Division Code

Select the division code from the LOV.

Division Name

On selecting the division code, the division name gets defaulted in the 'Name' field adjacent to the 'Division Code' field.

User can also enter the division's name manually for the code selected.

Default

If the company/division's codes and the division's name are default for the user group that user is defining, then select this checkbox.

TAB Department

The 'Department' tab is used to attach the newly created user to a department within the company. Click the 'Department' tab. The fields in the 'Department' tab are displayed as follows.

Comp. Code	Division Code	Name	Department Code	Name	Default ?
001	100	Head Office	10	Motor	☒
					☐
					☐
					☐
					☐

Name:

Fig. 202 – Creating New User — Department Tab

 The Company Code, Division Code and the Name attached to the newly created user get defaulted in the respective fields. Do not change the values to these fields.

Department Code

The field 'Department Code' refers to the code for various business classes such as Fire, Marine Hull, and Motor etc. Select the department's code from the LOV.

Department Name

On selecting the department code, the department name gets defaulted in the 'Name' field present adjacent to the 'Department Code' field.

User can enter the department name manually for the department code selected.

To change the department name, user can either select the department code from the LOV or enter it manually.


 The checkbox for the 'Default' field gets selected automatically. Click on the checkbox to uncheck it.

After entering values to these fields, click 'Save' to attach the department to the newly created user.

Menu Parameter Maintenance

The 'Menu Parameter Maintenance' screen is used to define the description and value for new parameters which is accessed through the instance.

Double-click the 'Menu Parameter Maintenance' menu; the following screen is displayed as follows.



Parameter Code	Parameter Description	Parameter Value
ACBA	1 Main Account Bank Category	BA
ACBA	1 Main Account Bank Category	BA
ACBA	1 Main Account Bank Category	BA
ACCA	1 Main Account Cash category	CA
ACCA	1 Main Account Cash category	CA
ACCA	1 Main Account Cash category	CA
ANA_NAME	1 Analytics Schema Name	NIKO_UAT_1_ANALYTICS
ANA_NAME	1 Analytics Schema Name	P10BASE_QC92_ANA
BUT_STYLE	1 Button Style Icon/Button	ICON
BUT_STYLE	1 Button Style	ICON
BUT_STYLE	1 Button Style Icon/Button	ICON
CFBD	1 CURRENT FINANCIAL BEGIN DATE	0101
CFBD	1 CURRENT FINANCIAL BEGIN DATE	0101
CFBD	1 CURRENT FINANCIAL BEGIN DATE	0101
CFED	1 CURRENT FINANCIAL ENDING DATE	0112
CFED	1 CURRENT FINANCIAL ENDING DATE	0112
CFED	1 CURRENT FINANCIAL ENDING DATE	0112
CMTH	1 Current Processing Month	200412
CMTH	1 Current Processing Month	200603
CMTH	1 Current Processing Month	200412

Fig. 203 – Define New Parameter

Parameter Code

Enter a unique parameter code.

Parameter Description

Enter a relevant description for the parameter code entered.

Parameter Value

Enter a relevant value for the parameter code entered

Click the 'Save' icon to save the created parameter.

Menu Screens

The 'Menu Screens' menu is used to define the various levels of menus such as parent menu, main menu, submenu, etc. to be accessed through the instance. User is able to organize, rename, enter help text, and set parameter for the defined menus.

The screen to define the menu is displayed as shown below:

Menu Parameters	Buttons	Buttons 2
01		11
02		12
03		13
04		14
05		15

Fig. 204 – Menu Screen

Menu ID

Enter the Menu ID.

Screen Name

Enter a name for this screen.

Description

Enter the corresponding description to the screen name entered.

Parent ID

The 'Parent ID' field is used to map the secondary IDs and other base level IDs to the primary menu ID. Select the parent ID from the LOV. The description corresponding to the selected parent ID gets displayed in the text box adjacent the parent ID.

Disp. Seq. No (Display Sequence Number)

The sequence number refers to the order of the menu appearance. Enter the required sequence number.

Database Caption Y/N

Select this checkbox, to default the screen name as default database caption name.

Action Type

Each action type indicates a form, and selecting one of them allows users to set a certain level of privilege to a user. Select an action type from the drop-down menu. The following action types are available:

- ☐ U – Update Form
- ☐ R – Report
- ☐ M – Menu
- ☐ I – Interface
- ☐ Q – Query
- ☐ H – History
- ☐ D – Discoverer

☐ B – BIRT - Business Intelligence Reports

Action

Enter the instance code in this field. This code allows the program to map an instance with the chosen menu.

Password Flag

Checking this field allows the user to set password to access a menu during the run time. A user can access that menu only after entering the password, if this field is checked.

Help Text

Enter the help text for the newly created menu. This is displayed at the bottom of the screen, on placing the mouse on the menu during the run time.

TAB Menu Parameters

Click this tab to attach the form/parameters to the newly created menu ID. The 'Menu Parameter' tab gets selected by default in the 'Menu Screens'.

User can specify a maximum of 20 parameters. Each parameter can have values upto 250 characters. Every Menu ID (which is predetermined) has 10 optional parameters attached to it, for correct functioning of the program. The list of menu ID and parameters is available at the time of installation of the software. Enter the correct parameter relevant to the menu ID.

Menu Parameters	Buttons	Buttons 2
01		11
02		12
03		13
04		14
05		15
06		16

Fig. 205 – Menu Parameters Tab

Each field in this tab indicates a particular attribute of a menu.

For Example: The eleventh field indicates whether the menu is a Quotation/Proposal or a Policy, The twelfth field indicates the Document Type and so on.

User Group Privileges

The 'User Group Privileges' menu enables the user to map the Menu IDs and the User Group IDs, , thereby restricting the users from transacting and allowing them only read / query privilege.

Click the 'User Group Privileges' menu to view the screen as shown below:

Menu ID	Group ID	Insert	Update	Delete
O-0101010802	INS	☒	☒	☒
O-010102	INS	☒	☒	☒
O-0101020101	INS	☒	☒	☒
O-0101020102	INS	☒	☒	☒
O-0101020105	INS	☒	☒	☒
O-0101020106	INS	☒	☒	☒
O-0101020201	INS	☒	☒	☒
O-0101020202	INS	☒	☒	☒

Menu Desc:

Menu Desc:

Fig. 206 – User Group Privileges

Menu ID

Select the required Menu ID from the LOV. The description for the menu ID is displayed in the first 'Menu Description' field (indicated by a black arrow in Fig .10).

Group ID

Select from the LOV the Group ID to which this menu ID is to be attached. The description for the group ID is displayed in the second 'Menu Description' field (see Fig. 10).

☒ Insert

To enable a user of a user group to enter data in the selected menu ID, select the checkbox for the 'Insert' option.

☒ Update

To enable a user in the selected user group to update data in the selected menu ID, select the corresponding checkbox under the 'Update' option.

☒ Delete

To enable the user of a user group to delete data in the selected menu ID, select the corresponding checkbox under the 'Insert' option.

After setting up the menu user privileges, click 'Save' icon to save the details.



If none of the check boxes are selected, then the logged in users only have the privilege to read / query the user group details at transaction level.

Report Boiler Plate

The 'Report Boilerplate' screen enables the user to configure labels for the parameters that are to be generated in a report for an entity.

For example, reports need to display the words From Date, To Date, Branch etc while viewing on screen and also when taking prints. These display terms are to be furnished in this screen.

Column Headings 1-10	Column Headings 11-20	Column Headings 21-30	Column Headings 31-40	Column Headings 41-50	Column Headings 51-60
Head1	MARINE CARGO CERTIFICATE NO	F_MARINE CARGO CERTIFICATE No.			
Head2	NAME OF CONTRIBUTOR	F_NAME OF CONTRIBUTOR			
Head3	ADDRESS	F_ADDRESS			
Head4	VOYAGE AND CONVEYANCE	F_VOYAGE AND CONVEYANCE			
Head5	DESCRIPTION OF CARGO	F_DESCRIPTION OF CARGO			
Head6	BANK AND L/C NO	F_BANK AND L/C NO			
Head7	VALUE DECLARED	F_VALUE DECLARED			
Head8	BASIS OF VALUATION	F_BASIS OF VALUATION			
Head9	SUM INSURED	F_SUM INSURED			
Head10	TERMS OF COVERAGE	F_TERMS OF COVERAGE			

Fig. 207 – Report Boiler Plate

Refer [Reports](#) under Application Setup for more information.

User Profile

The User Profile screen enables the user to create new user profile as shown below.

Fig. 208 – Create / View User Profile



Profile ID

Enter the unique profile Id of the user for whom the user profile is created.



Profile Description

Enter the description for the new profile.



Maximum Password Age (In Days)

Enter the maximum number of days the password stays active. (Password expiry days).



Prompt User to change password before (in Days)

Enter the number of days from when the system starts to prompt for change of password. An alert message (based on the numbers of days) prior to expiry is sent to login user prompting to change password (Where 'x' is parameter configurable as part of the profile definition).



Password Minimum Length

Enter the minimum number of character allowed for the password.



Password Maximum Length

Enter the maximum number of character allowed for the password.

No. of Password History

Enter the maximum number of password history which refers to the count of passwords the history must store. This prevents users from using 'x' number of previous passwords.

☒ **Enforce Password Change after password reset**

Select the check box, if password change is needed after the password is reset.



Lock after No of Failed Attempts

Enter the maximum number of failed attempts allowed after which the system gets locked.

Password Type

Enter the password type from the drop-down list provided. The available options are:

- ☐ Numeric
- ☐ Alpha
- ☐ Alphanumeric

☒ **Prefix Zero Y/N**

Select the check box if zero is to be prefixed in the password.

☒ **Suffix Zero Y/N**

Select the check box if zero is to be suffixed in the password.

☒ **Special Char Allowed**

Select the check box if special character is allowed in the password setting.

☒ **Special Char Mandatory**

Select the check box if special character is mandatory in the password setting.

☒ **Default Profile**

Select the check box if the current profile should be the default profile.

Special Chars Not allowed in Password

Enter the special characters that are not allowed in the password setting.



This field gets displayed only if the 'Special Char Allowed' check box is selected.

PROGRAM REGISTRATION INSTANCES

Program registration is the process of defining a new or the existing program (FMB) along with the information about storage location, the type of program, the version of Oracle used, and the likely end result from this screen. Added to this, the Program registration also allows users to register, compile, create exceptions or register and create exceptions to the existing or the new programs — Form Module Builder (FMB).

Double-click the 'Program Registration and Instances' menu.

Program Registration Process

The 'Program Registration Process' menu enables to register/compile/create exceptions for a program. It connects the backend with the client end.

Double-click the 'Program Registration Process', a screen is displayed as follows:

Fig. 209 – Program Registration Process

Oracle Home

Enter the path of the Oracle server set up for PREMIA.

Source Directory

Enter the path of the base form stored in the server.

File Name

Enter the file name of the new program (FMB) that is to be registered/compiled/entered as an exception, or to be registered and entered as an exception. User is allowed to enter the file name of an existing program (FMB) that is to be modified.

The fields 'Database User ID', 'Database Password' and 'Connection String' get defaulted with the values that get populated based on the prior settings done, while installing Oracle server.

Forms Version

PREMIA supports Oracle 6i, Oracle 9i and the Oracle 10g R2. Select the form version based on the requirement.

Select the form 10g R2 for Allied.

Program Type

If the program is to be newly created, then select the 'New' option. Else, select the 'Old' option.

Form Type

Based on the requirements, various types of forms can be created in PREMIA. Select the option

- ☐ 'Master', to create a master form with the file name PGIM
- ☐ 'Transaction', to create a transaction form with the file name PGIT
- ☐ 'LOV', to create list of values form with the file name PGIL
- ☐ 'Interface', to create interface form with the file name PGII
- ☐ 'Query', to create query form with the file name PGIQ

Process Type

Four types of processes can be performed in the selected form type. Select any from the options listed below

- ☐ 'Registration', if the program is to be registered for the first time
- ☐ 'Compilation', if a program that is already registered but need to be compiled
- ☐ 'Exception'
- ☐ 'Registration and Exception'

Delete All Existing Instance

If the program type is old, select the option

- ☐ 'Yes' to delete the existing instances and replace with the newly created instances
- ☐ 'No' to retain the existing instances.



Generate

After entering the respective values in the fields, click the 'Generate' button to register the newly defined program.

Once the program is registered, a screen with the message 'Registered Successfully' is displayed.



Fig. 210 – Successful Registration of the Program

Program Definition

The 'Program Definition menu enables users to define the functionalities and characteristics of a program (FMB). There are five tabs available in the Program Definition screen.

- ☐ **Block** — The smallest unit of storage in an Oracle database. The database block contains header information such as block name, table name, sequence number and the other options available for a field.
- ☐ **Field** — The 'Field' tab contains information about a block such as its data type, display length, default value (if any), 'x' and 'y' position, its hint etc.
- ☐ **Canvas** — A canvas is a surface—inside a window container—on which the interface items and boilerplate objects are placed and boilerplate objects where the end users are allowed to interact when the form is run.
- ☐ **Menu** — The 'Menu' tab that contains information about the forms such as its menu type, action, etc are Lists of items that end users use to select specific functions or operations. Each item on a menu represents a command or a submenu.

External Validation — The 'External Validation' tab contains information about the validations obtained for the program. It refers to the non-PREMIA tables as well as to tables that are to be picked up from other PREMIA sources.

The fields in these tabs essentially form the characteristics for the program.



- ☐ All the tabs in the 'Program Definition' screen reflect the data stored in the back-end form. User can only view the information in the fields of these tabs, and are not allowed to modify or delete any of them.
- ☐ The characteristics of any existing program alone can be viewed.
- ☐ User is not allowed to set these values as parameters for a new program

Double-click the 'Program Definition' menu to view the screen as shown below:




Fig. 211 – Program Registration Screen

Program Code

The 'Program Code' refers to the file name that is registered in the 'Program Registration Process' menu. Enter manually or select the program code from the LOV, and click the query button. The program name gets defaulted in the adjacent textbox.

Program BL Desc (Program Bilingual Description)

The bilingual description for the selected program code is displayed in the 'Program BL Desc' field.

On selecting the program code, the parameters for various levels such as block level, field level can be viewed.



To provide maximum security to the product and to ensure that there is no conflict arising out of unconscious mistakes do not change any field entries or mark/unmark check boxes of the parameters present in the 'Block', 'Field', 'Canvas', 'Menu' and 'External Validation' tabs.

Click the respective tabs to view the parameters in the tabs.

TAB Block

The fields in the 'Block' tab are displayed by default upon opening the 'Program Registration' screen. The 'Block' tab provides information about the block names, respective table names, master block name, sequence number of the queried program code. Also provides the

information on, whether the values for a block can be inserted/modified/deleted/queried.

Select the check box (es) available - 'Insert?' / 'Update?' / 'Delete?' / 'Query?' to indicate that these options are enabled for a block.

Block Name	Table Name	Master Block Name	Seq.No.	System Defined ?	System Disable ?	Insert ?	Update ?	Delete ?	Query ?
AP_DEPR_PROCE	AP_DEPR_PROCE		1	☐	☐	☒	☒	☒	☒
AP_DEPR_DETAIL			2	☐	☐	☒	☒	☒	☒
BLOCK_DEPR_DE			3	☐	☐	☒	☒	☒	☒
AT_ERROR_LOG	AT_ERROR_LOG		4	☐	☐	☒	☒	☒	☒
BOOK_DETAIL			5	☐	☐	☒	☒	☒	☒

Block Desc: AP_DEPR_PROCESS
Block BL Desc: F_AP_DEPR_PROCESS

Records Display: 1

Fig. 212 – Program Registration — Block Tab

The 'Bloc Desc' and 'Block BL Desc' fields show the respective description for the selected block name / table name in English and in the foreign language, respectively.

TAB Field

Click the 'Field' tab to view the characteristics of each block. Place the cursor on the 'Block Name' field and press the down / up arrow to view the characteristics of the other block names. The 'Field' tab provides information such as data type, field length, display length, 'x' and 'y' position, and the sequence number of the blocks in the form etc.

Block Name: BOOK_DETAIL
Field Name:
Field BL Desc:
Data Type:
Item Type:
System Defined ? ☒ Base Table ? ☐
Mandatory ? ☒ Key/Non Key ? ☐
Field Length:
Display Length:
Hide ? ☐ Enterable ? ☐
Update ? ☐ Fixed Length ? ☐
Default Value:
Upper Case ? ☐ Case Insensitive Query ? ☐
Canvas Name:
Tab Name:
Radio Group Name:
Hint:
BL Hint:
Prompt:
BL Prompt:
Prompt Display Style:
Prompt Edge:
Prompt Edge Align:
Prompt Text Align:
Prompt Edge Offset:
Record Displayed:
X Position:
Y Position:
Sequence Number:
Boiler Plate ? ☐

Fig. 213 – Program Registration — Field Tab

TAB Canvas

Click the 'Canvas' tab. User can view the canvas type, label name of a canvas, and the location details.

Type Name	Window/Canvas/Button Name	Tab Page Name	Label	BL Label	Hide
B	PB_BLOCK_DEPR_CLOSE		Close	F_Close	☐
B	PB_BOOK_DETAIL_CLOSE		Close	F_Close	☐
B	PB_DEPR_DETAIL		Depr Detail	F_Depr Detail	☐
B	PB_DEPR_DETAIL_CLOSE		Close	F_Close	☐
B	PB_ERROR_LOG_CLOSE		Close	F_Close	☐

Type Desc: Tab Page Desc:

Canvas Desc: X Position: Y Position:

Canvas Type: Canvas Width: Canvas Height:

Vertical Scroll Bar Y/N: Viewport Width: Viewport Height:

Fig. 214 – Program Registration — Canvas Tab

TAB Menu

Click the 'Menu' tab. Menu tab provides information on the menu name and menu placement.

Example: Fire is a submenu under Underwriting main menu. User can find that out by looking at the Pull Menu Code (the code for Fire) and Parent Pull Menu (the code for Underwriting), the call type (codified based on primary level, secondary level etc)

Pull Menu Code	Parent Pull Menu Code	Call Type	Call Name	Caption	BL Caption
STD_MENU	STD_MENU02	S		Action	F_Action

Pull Menu Desc: Parent Pull Menu Desc:

Call Type Name:

Fig. 215 – Program Registration — Menu Tab

As noticed, all the field level entry would be populated and the check boxes marked or unmarked.

TAB External Validation

Click the 'External Validation' tab to define those details that are necessary to take care of certain specific business rules, conditions, updations and validations for a program. These validations refer to the non-PREMIA tables.

Type	Trigger Type	Block Name	Field Name	Statement Type	Statement	S.No.	Code	Error Code	Error Type
U	POST-UPDATE	PGIT_POL_RISK_		D	Ext_Fir_Con_Kutchu_Del(PGIT_POL_RISK_	2	01		N
V		PGIT_POL_RISK_	PRC_CODE	D	EXT_FIRE_RSMD_COVER(PGIT_POL_RIS	1	01		N
V		PGIT_POL_RISK_	PRAI_DATA_07	D	EXT_FIRE_OCCUP_CODE(PGIT_POL_RIS	1	01		N
U	PRE-INSERT	PGIT_POLICY		D	EXT_FIRE_SHRT_PRD_POL(PGIT_POLIC	1	01		N
U	PRE-UPDATE	PGIT_POLICY		D	EXT_FIRE_SHRT_PRD_POL(PGIT_POLIC	1	01		N

Type Desc: Trigger Type Desc:

Block Desc: Field Desc:

Statement Desc: Error Desc:

Enter the Program Code

Record: 11/? <OSC>

Fig. 216 – Program Registration — External Validation Tab

Place the cursor on the block name to view its type description, trigger type description, block description, field description, statement description and error description

Instance Definition

The base program may have a whole lot of data elements to capture certain policy details. If these are not required for a specific implementation, then the implementer can change the property of these fields which is possible through a GUI. The Policy Entry module is displayed without those data elements, allowing the user to see a clutter-free screen, and capture only relevant information.

This facility achieved is through the Instance Definition module making it easy to deploy different screens for the same function depending on the channel or media through which such information is being captured.

New products can be launched instantly by simply setting up the features required for the product. This is done through the instance, which is a mirror image of the program. Based on a program, any number of instances can be created. This helps any system / application administrator to set up the product quickly and deploy for use across the organization without any loss of time. Any modification in the product feature can similarly be configured. This gives a tremendous advantage in the insurance industry where change is constant.

The instance definition is done through the System Administration module of PREMIA

In 'Program Definition', user can view various programs available in PREMIA. Using these programs, user can define the new instances. The 'Instance Definition' menu enables the user to:

- ☐ Create multiple mirror forms faster
- ☐ Use the base form and create mirror forms that appear different. User need not create the individual data group forms; the base form is kept intact.
- ☐ Change the parameters within a block
- ☐ Change the x and y position of a field, thereby modifying its position in the form
- ☐ Change the label for a button using the 'Canvas' tab
- ☐ Change the menu hierarchy using the menu screen. For example: User can change a submenu 'Fire' into a main menu.

In short, user can define/change the characteristics, behavior, design and functionality for a

newly created form without changing the base form.

Click 'Instance Definition' menu, a screen to define an instance for a program is displayed.

Fig. 217 – Creating Instances

Instance Code

Enter a new instance code.

Instance Name

Enter a new instance name in this field.

Instance BL Name

Enter the bilingual name for the new instance.

Program Code

Select the program code from the LOV. The program name gets defaulted in the adjacent textbox. The instance is created using this program code as a base form.

Remarks

Enter any relevant remarks about the new instance in this field.

TAB Block

The screen defaults the fields/parameters present in the 'Block' tab (as shown below):

Fig. 218 – Instance Registration — Block Tab

Block Name

A list of all the blocks mapped to the Program Code is displayed in this field.



Sequence Number

Based on the order of the block's appearance in the base form, the sequence number appears. User is allowed to change the sequence number based on the requirement. The sequence number acts as a display sequence for the blocks.

☒ Disable?

Select this checkbox, to disable the field.



This feature is not currently available for PREMIA users.

☒ Insert?

Select this checkbox to allow the users to enter records into the block during runtime.

☒ Update?

Select this checkbox to allow users to modify the existing records in the block during runtime.

☒ Delete?

Select this checkbox to allow the users to delete the records in the block during runtime.

☒ Query?

Select this checkbox to allow the users to use the query feature (F7 and F8) within the block during runtime.

Display Records

Blocks can show a single record or multiple records in runtime. Enter a value based on the number of records that needs to be displayed.



EV

This option enables users to define any external validation.

Remarks

Enter any relevant remarks about the new instance in this field.

After setting up the block information, click the 'Save' icon to save the details.

TAB Field

Click the 'Field' tab to view the fields and to set the parameters for the newly created instance. The system displays the screen as shown below.

Fig. 219 – Instance Registration — Field Tab



Block Name

Select from the LOV the block code that users need to include in the program. Its corresponding description gets defaulted in the adjacent text box.



Field Name

Select from the LOV the field name that is associated with the selected block. Its corresponding description gets defaulted in the adjacent text box.

Class Code

Class code refers to the Class of Business code. Enter a class code in this field.

☒Mandatory?

Select the check box, if the field has to be a mandatory field in the program.

☒Enter?

Select the check box to allow users to enter data in this field during runtime.

☒Update?

Select the check box to allow the users to update the fields during runtime.



Hide?

Select the check box to hide the chosen field.

☒Override?

Select the check box, to allow the user to override the data entered in this field during runtime. By default, the value is set as 'No'.



Data Type

There are three data types that can be mapped to a field.

☐Character (C)

☐Date (D)

☐ Number (N)

Select the required type from the LOV.

☒ **Fixed Length**

Select the checkbox to avoid users from entering data lesser or more than the fixed field length.

☒ **Upper Case?**

Select the check box if the selected field information needs to appear in upper case.



Field Length

Enter value in the 'Field Length'. This value determines the length of the field in the form.

Display Length

Enter the overall display length in this field. This is the display length that will be seen during runtime.



In some instances, the field length might be more than the display length (ex: Login Name) and vice versa (ex: Policy Number)

Default Type

Certain fields in PREMIA cannot carry a null value. These fields require a hidden value that would be fetched internally during transactions. Hence, enter a constant or a global constant value (example: zero) or a SQL statement in this field. Select the default type code for this field from LOV.

The three codes displayed in LOV are:

☐ Constant (C)

☐ SQL Statement (S)

☐ Global Constant (G)

Default Before/After

Select whether the default should appear before or after the field from the two choices provided.

Default Value

Enter the default value for the set default type.



This field is mandatory, if the 'Default Type' is 'SQL Statement' or 'Global Constant'.

Boiler Plate

Select this option, to make the prompt name to appear as the boiler plate.

Canvas Name

Enter the canvas name to which this particular field would be linked.

Tab Name

If the field is to appear within a tab, then enter the tab name.

Validate

Select this option, to allow the user to have validation privileges. By default, the value is set as 'No'.

Value Set

Set the valid Value Set (if any) for the field. The value set name for the code, which has to be attached or validated to a field gets automatically displayed.



If validation is set as 'Yes', then this field becomes mandatory.

Prompt

Prompt is the field title. Enter an appropriate field title in this field.

Prompt Display Style

The 'Prompt Display Style' field describes the style of the prompt. Three types of prompt display styles are available in LOV. Select the option

- ☐ 'First', if user wants to place the Prompt above or within the table, but not allowed to exceed more than one entry. For example, see the tables 1 and 2 below. Table 1 shows the appearance of prompt '**Your Prompt Name**' above the table and table 2 shows the appearance of prompt '**Your Prompt Name**' within the table.

Your Prompt Name

Table 1

Your Prompt Name		

Table 2

- ☐ 'All', if the Prompt is to be repeated in the first columns of the table (see table 3 for reference).

Example:

Your Prompt Name		
Your Prompt Name		
Your Prompt Name		
Your Prompt Name		

Table 3

- ☐ 'Hidden', if user wants the prompt to be hidden.

Prompt Edge

The 'Prompt Edge' describes the exact location of the prompt placement. Four prompt edge types are available in PREMIA. They are listed below:

- ☐ **Start**: Select this option from the LOV, if user wants the prompt to appear before a field
- ☐ **End**: Select this option from the LOV, if user wants the prompt to appear at the end of a field
- ☐ **Top**: Select this option from the LOV, if user wants the prompt to appear above a field
- ☐ **Bottom**: Select this option from the LOV, if user wants the prompt to appear below a field

Prompt Edge Align

The 'Prompt Edge Align' field enables to align a prompt to the exact point concurrent with the field box. Three prompt edge align types are available in PREMIA and are described below.

- ☐ **Start**: Select this option from the LOV, if user wants the prompt name to appear at the beginning. (See the phrase 'Your Prompt Name 1' in the table below.)

☐ **End:** Select this option from the LOV, if user wants the prompt name to appear at the end.
(See the phrase 'Your Prompt Name 3' in the table below.)

☐ **Centre:** Select this option from the LOV, if user wants the prompt name to appear at the centre.
(See the phrase 'Your Prompt Name 2' in the table below.)

Your Prompt Name 1

Your Prompt Name 2

Your Prompt Name 3

Field 1

Prompt Text Align

The 'Prompt Text Align' enables to align a field text within a prompt in a table to left/center/right.
Select the option

☐ 'Start' from the LOV, if user needs to align the prompt text to the left

☐ 'End' from the LOV, if user needs to align the prompt text to the right

☐ 'Center' from the LOV, if user needs to align the prompt text to the centre

Prompt Edge Offset

This field allows the user to increase or decrease the spacing between the prompt and the field.
Enter a pixel value for the adjustment.

Record Displayed

The 'Records Displayed' field determines the number of records that a user is allowed to view.
Enter a numeric value in this field.

Tool Tip

Enabling this checkbox allows the user to view the tool tip.

☒ Case Insensitive Query?

Select this check box. User can query the selected field in both upper and lower case.

Hint

Entering a hint text for a field displays the hint text at the left bottom of the screen (see the figure below), when user places the cursor over the field.

Enter manually the text of the hint for the field.

X Position

This field determines the 'x' axis position of the field in the form.

Enter the x-axis position of the field in the display screen.

Y Position

This field determines the 'y' axis position of the field in the form.

Enter the y-axis position of the field in the display screen.

Form Item Type

Select from the LOV the form item type as required.

☐ If user needs the item to appear as a text, select the 'Text Item (T)' option

☐ If user needs the item to have a radio button, select the 'Radio Button (R)' option

☐ If user needs the item to have a check box, select the 'Check Box (C)' option

☐ If user needs the item to have a list box, select the 'List Box (L)' option

☐ If user needs the item to be a display, select the 'Display Item (D)' option

Remarks

Enter any relevant remarks about the new field information in this field.

Radio Group Name

Radio Group refers to combination of two or more radio button names. Example: A radio button group called Sex can have two options: Male or Female.

Enter the radio group name, if the field information entered has a radio button type field.

After setting up the block information, click the 'Save' icon to save the details.

TAB Canvas

Click the 'Canvas' tab to view and define the fields/attributes for the newly created instance as shown below.

Fig. 220 – Instance Registration — Canvas Tab

Type

The 'Type' field refers to the category of canvas. Select the type from the LOV. A canvas can be:

- ☐ Window Title (W)
- ☐ Push Button Label (B)
- ☐ Tab Page Heading (T)

Windows/Tab Canvas/Button Name

Select the windows/tab canvas/button name from the LOV.

Tab Page Name

If the canvas is for a tab, then select the tab page name from the LOV.

Label

Enter the label name for the windows/tab canvas/button in this field.

Bi-Lingual Label

Enter the label name in bilingual language for the windows/tab canvas/button in this field.

Hide?

Select this checkbox, to hide the canvas, if required.

On placing the cursor on the 'Windows/Tab Canvas/Button name, user can view their respective descriptions in the fields 'Type Desc', 'Tab Page Desc', 'Canvas Desc' and their 'x' and 'y' positions in the form. User can modify the values in these fields.

After setting up the values in the fields, click the 'Save' icon to save the configurations.

TAB Menu

Click the 'Menu' tab to view, define, and customize the menus for the newly created instances as shown below.

Fig. 221 – Instance Registration — Menu Tab

Pull Menu Code

The 'Pull Menu Code' field refers to the menu code that requires to be customized. Select a menu code from the LOV.

Parent Pull Menu Code

If the pull menu code selected is a submenu, select the parent pull menu code from LOV. The description for the respective parent pull menu code gets defaulted in the 'Parent Pull Menu Desc' field.

Call Type

Select a call type from the LOV. Select the call type as

- ☐ 'A (Actions)', if the menu is an action menu
- ☐ 'I (Instance)', if the menu is an instance type menu
- ☐ 'S (Sub Menu)', if the menu is a submenu
- ☐ 'R (Root Menu)', if the menu is a base or root menu
- ☐ 'P (Print)', if the menu is used for printing alone

Call Name

Enter the name for the selected call type.

Menu ID

Enter the Menu ID.

Caption

Enter a caption for the menu. This caption will appear during runtime.

Caption (bilingual)

Enter a caption for the menu in the second language for which the application is set.

After entering the respective values in the fields, click the 'Save' icon to save the configurations.

TAB Menu Control

The 'Menu Control' tab enables to map the user groups to various menus for access rights. Click the 'Menu Control' tab, a screen opens to map the user groups to various menus as shown below.

Fig. 222 – Instance Registration — Menu Control Tab

Call Type

The 'Call Type' field determines the placement of the menus in the product. For example: 'Underwriting' is a main menu, whereas, the 'Fire' is a submenu within the 'Underwriting'.

Select the call type from the LOV. The description of the type gets defaulted in the 'Menu Call Type' field. Select the call type as

- ☐ 'A (Actions)', if the menu is an action menu
- ☐ 'I (Instance)', if the menu is an instance type menu
- ☐ 'S (Sub Menu)', if the menu is a submenu
- ☐ 'R (Root Menu)', if the menu is a base or root menu
- ☐ 'P (Print)', if the menu is used for printing alone



Menu Name

Select the instance or action from the LOV, for which the user privileges are to be mapped. The name corresponding to the selected code gets displayed automatically in the 'Menu Desc' field.

Menu User Group

User Group refers to grouping based on usage within the PREMIA. Select from the LOV the menu user group to whom the privileges to view this menu are to be provided. The name corresponding to the particular code gets displayed automatically in the 'Menu User Group Desc' field.



While configuring menus, attach the menu to a user group only through the 'Menu Control' else the configuration is not complete and the menus will not appear during real runtime.

After mapping the user group to the respective menus, click the 'Save' icon to save the configured details.

TAB Menu Call Parameter

The 'Menu Call Parameter' tab enables to query for the particular record of the instances attached to the menus. For example: Say the SMI master has been attached to this menu. To view the details of a SMI during a transaction, enter the respective SMI code and click SMI. The SMI screen opens with the data retrieved for the corresponding SMI code.

If a particular feature is to be added to the menu, then the field in the current instance is to be mapped to the original field in the respective master. This mapping is done through this block.

Click the 'Menu Call Parameter' tab to view the following screen:

Fig. 223 – Instance Registration — Menu Call Parameter Tab

Call Mode

There are two call modes available:

- ☐ Normal (N)
- ☐ Query (Q)

Select the required call mode from the LOV.

Menu Name

Select from the LOV the menu name that was entered in the 'Menu Control' tab. The name corresponding to the particular code gets defaulted in the 'Menu Description' field.

Source Field Name

Select from the LOV the field name in the current instance, for which the query should be carried out. This is the field from which the menu is selected. The name corresponding to the particular field name gets displayed automatically in the 'Source Field Description' field.

WHERE Condition

This field states the conditions based on which the records can be queried. The possible conditions are as follows:

- ☐ Equals
- ☐ Less Than
- ☐ Greater Than
- ☐ Like

Select an SQL statement from the LOV to execute the WHERE Condition. The name corresponding to the particular 'where condition' gets displayed automatically in the 'WHERE

Desc' field.

Target Field Name

Select from the LOV the field in the 'target form' to which, the source field corresponds. The name corresponding to the particular code gets displayed automatically in the 'Target Field Desc' field.

After setting up the block information, click the 'Save' icon to save the details.

TAB External Validation

The 'External Validation' tab enables to define those details necessary to define the external updation and validations for a program. External validations refer to both non-PREMIA and PREMIA tables.

Click the 'External Validation' tab to open the validation screen as shown below.




Fig. 224 – Instance Registration — External Validation Tab

Type

Select the option required from the LOV. Applicable values are

☐ V (External Validations)

☐ U (External Updation)

Define whether the values are to be validated or updated from either an external source outside PREMIA or from another PREMIA table.

☐ If user selects the type as 'V', then the cursor moves first to the 'Block Name' field and then to the 'Field Name' field.

☐ If user selects the type as 'U', then the trigger type gets accepted.

Trigger Type

Set the trigger type required from the LOV. Examples of trigger types are Pre/Post Insert/Update, Approval and Amendment, etc.



This field is mandatory, if the type is selected as 'Updation'.

Block Name

Select from the LOV the block name for updation/validation.

Field Name

Select from the LOV the field name corresponding to the selected block name for validation.



This field is mandatory, if the type is selected as 'Validation'.

Statement Type

Set the statement type to be executed from the LOV. Applicable values are

- ☐ SQL command (S)
- ☐ Package (P)
- ☐ Package (D)
- ☐ Actions (A)

By default, the value is taken as 'SQL Statement'.



Statement

Enter or select the statement, SQL, or the name of the database procedure corresponding to the set statement type.



Sequence Number

Enter the sequence number for the defined statements. For example: If the same block has multiple select statements, then the sequence at which each statement has to be executed is to be specified.



Application Code

Set the application code from the LOV.

Error Code

Set the valid error code (if any) for the select statement from the LOV.



Error Type

Select the error type from the LOV.

After setting up the block information, click the 'Save' icon to save the details.

TAB LOV (List of Values)

The LOV is a scrollable popup window that provides the User with either a single or a multi-column selection list. Click the 'LOV' tab to open the screen to configure LOV for the instance created as shown below.

Instance Code	PGIT6_02-039	Script Generator
Instance Name	Instance for Other Details	
Instance BL Name	F_Instance for Other Details	
Program Code	PGIT6_02	MODULE5
Remarks		

Block	Field	Canvas	Menu	Menu Control	Menu Call Parameter	External Validation	LOV
-------	-------	--------	------	--------------	---------------------	---------------------	-----

Lov Name	
Block Name	
Lov Where Clause	
Append Where Clause?	☐
Append Where Clause	
Remarks	

Fig. 225 – Instance Registration — LOV Tab

LOV Name

Select the LOV name to be attached to the new instance from the LOV.

Block Name

Select from the LOV the block name in which, these LOV's are to appear for the instance.

LOV Where Clause

This field enables to attach a statement with respect to the positioning of the data within the LOV table. Enter the select statement, SQL, or the name of the database procedure.

Append Where Clause?

Select this checkbox, to append a where clause.

Append Where Clause

Enter a where clause statement in this field to append the LOV. This field is enabled, only if 'Append Where Clause?' field is checked.

Remarks

Enter any relevant remarks for the future reference.

Instance Copy

The 'Instance Copying' screen enables the user to copy the instance from one source to another source. The system displays the screen as shown below:

Fig. 226 – Instance Copying



Source Form Code

Enter or select the Source code from the LOV help to be copied.

Source Form Description

The source code description corresponding to the Source Code is defaulted.

Destination Form Code

Enter the destination Form Code where the form has to be copied.

Destination Form Description

Enter the corresponding description for the destination Form Code.

Click 'Save' button to save the details.

Click 'Copy' button the data is copied and sent to the destination. Now the corresponding window is displayed.




Fig. 227 – Prompt Window 1

This prompt ensures that the form has been copied to the IM_INSTANCE form.

Click 'OK' button to view the next prompt message.



Fig. 228 – Prompt Window 2

This prompt ensures that the form has been copied to the IM_INSTANCE_BLOCK_DEFN.

Click 'OK' button to view the next prompt message.



Fig. 229 – Prompt Window 3

This prompt ensures that the form has been copied to the IM_INSTANCE_FIELD_DEFN.
Click 'OK' button to view the next prompt message.



Fig. 230 – Prompt Window 4

This prompt ensures the user that the form has been copied to the IM_PROG_CANVAS_LBL.
Click 'OK' button to end the process.
Click 'Cancel' button to cancel the copy function

PREMIA PRODUCT CONFIGURATOR

PREMIA has been developed to support the concept of single version of the product with an easy-to-use product configuration setup that masks the complexity of the architecture. The Product Configuration allows insurance companies to define their products by setting up the elements that go into making up the product.

To configure a product, the user can set up the type of covers and risk details that are required to be captured. All data elements that are required to compute the premium can also be specified. The Rating engine is closely integrated with product configuration setups and can be used to set up the premium rating computations for each product.

The Product Configurator menu comprises of the following sub-menus:

- ☐ Product Setup Tool
- ☐ Product Changer Map
- ☐ Product Changer Map - Query

PRODUCT SETUP TOOL

This powerful tool enables the user to configure new insurance products in a single instance such as the:

- ☐ Set up the Product Details / Section details
- ☐ Define Applicable Blocks / Applicable Taxes and Charges
- ☐ Define External Validation
- ☐ Define /Delete Section Codes for the Product
- ☐ Define Risk Level Details for the Product
- ☐ Copy existing Product to New Product
- ☐ Delete an existing Product

The system displays the screen as shown below:

The screenshot shows the 'Product Setup Tool' interface for 'INSURANCE CO LTD'. The main section is titled 'Product' and contains the following fields:

- Code:** 1001
- Desc:** Motor Commercial
- Class Code:** 10
- Motor:** (selected from a dropdown)

Below these fields are several buttons: Product Details, Tax and Charge..., External Validat..., Other Details, Script Generator, Product Copy, and Product Delete.

The 'Sections' section displays a table with columns: Section*, Lvl No, Sr No, Block Name, Label, and EV. The table contains the following data:

Section*	Lvl No	Sr No	Block Name	Label	EV
100101	1	1	PGIT_POL_RISK_ADDL_INFO_01	Vehicle Details	EV
	1	2	PGIT_POL_RISK_ADDL_INFO_02	Driver Details	EV
	2	1	PGIT_POL_RISK_ADDL_INFO_16	Orange Card	EV

Below the table are checkboxes for: Cover Attach YN, Ded Attach YN, Dis Load Attach YN, and Smi Attach YN. There is also a 'Risk Details' button.

The 'Fields' section displays a table with columns: Sr No, Field Name*, Position, Disp Length, X Pos, Y Pos, Text, Data Type, and EV. The table contains the following data:

Sr No	Field Name*	Position	Disp Length	X Pos	Y Pos	Text	Data Type	EV
1	PRAI_RISK_ID	30	110	13		Vehicle ID*	Text	EV
2	PRAI_EFF_FM_DT	80	110	31		Veh. Entry Dt	Date	EV
2	PRAI_YN_02	40	110	49		Cert. Req'd YN	Yes/No	EV
3	PRAI_DATA_08	40	190	49		Cert. Mode	Text	EV
3	PRAI_EFF_TO_DT	80	256	31		Veh. Exit Dt	Date	EV
4	PRAI_CODE_14	40	295	49		Cert. Type	Text	EV
5	PRAI_DATA_09	30	110	66		Book ID	Text	EV
6	PRAI_DATA_05	80	256	66		Cert No.	Text	EV

Below the table are checkboxes for: Hide, Enterable, Updatable, Mandatory, Correction YN, and Claims Lookup YN. There are also input fields for 'Dft Value', 'Num Format Mask', 'Number Range From', 'To', 'Date Range From', and 'To'.

Fig. 231 – Product Setup Tool

Product

This block enables the user to configure product setup details.



Code

Enter a unique code for the product to define the setup. This code will be used across the PREMIA application. Enter the description for the code in the adjacent field.

For example, for code 1001 enter the description as Motor Commercial.

Class Code

Class code refers to the Line of business. Use this field to attach the product to its respective line of business. The pre-defined Class Codes are available through the List of Values (LOV) provided. Once the code is selected or entered, the description is automatically displayed in the adjacent field.

An example is, Class Code: 10 with description as Motor.

Click the respective buttons available in the screen to setup the corresponding details.

- ☐ Product Details
- ☐ Tax and Charge
- ☐ External Validation
- ☐ Other Details
- ☐ Script Generator
- ☐ Product Copy
- ☐ Product Delete

Product Details

Click this button to configure the product setup details. The screen displayed is similar to the screen explained in the Product Setup section under 'Others' screen.

Refer the corresponding section for more information on field details.

Tax & Charge

Click this button to define the applicable charges for the product. Charges are to be based on a fixed rate for a product or depend on the cover premium. This calculation logic and the rate are defined in this master.

Chg Type*	Chg Code*	Desc	Section*	Calc Logic*	Cvr Grp Code*
002	1001	Policy Fees		002	
002	1002	Duplicate Card fee		002	
003	2001	Service Levy		002	
004	4001	Service Tax		001	1001
005	5001	Environment Fee		001	1001

Charges:

Short Period Rate: Annual Rate: Mandatory Yn: ☐

Cust Share Perc: Round To: Refund Yn: ☐

Rate Per: Sort Order: Prem Disp Yn: ☐

Round Dec: Prem Order: Rate Modifiable Yn: ☐

Risk Level Yn: ☐

Fig. 232 – Product - Tax & Charges

The field details displayed in this screen are similar to that of [Tax and Charges](#) screen defined under 'Rating' menu.

Refer the corresponding section in this manual for more information.

External Validation

Click this button to define details that are necessary to take care of certain specific business rules, conditions, updations and validations for a program. These validations refer to the non-PREMIA tables. The EV's are defined in the backend only where user can see what all EV's are attached to the product. The system displays the screen as shown below:

External Validations

Fig. 233 – Product - External Validation

❑ Front End EV – Click this button to view the front end external validation of the Product Code

Prog Code*	Inst Code*	Trigger Name*	Block Name*	Trigger Field Name*	Action Fields	Procedure	S.No	Error No
PGIT6_03	10-PD-03_01	WHEN-VALIDATE-ITE	PGIT_POL_RISK_ADDL	PRAI_YN_02	PRAI_DATA_01,	PKG_VALIDATION.EXT_VAL_VEH	2	
PGIT6_03	10-PD-03_01	WHEN-VALIDATE-ITE	PGIT_POL_RISK_ADDL	PRAI_DATA_01	PRAI_DATA_01,	PKG_VALIDATION.EXT_VAL_VEH	2	
PGIT6_03	10-PD-03_01	WHEN-VALIDATE-ITE	PGIT_POL_RISK_ADDL	PRAI_DATA_01	PRAI_DATA_01,	PKG_VALIDATION.EXT_VAL_VEH	2	
PGIT6_03	10-PD-03_01	WHEN-NEW-RECOR	PGIT_POL_RISK_ADDL		PRAI_DATA_05,	PKG_VALIDATION.EXT_VAL_POL	1	
PGIT6_03	10-PD-03_01	WHEN-VALIDATE-ITE	PGIT_POL_RISK_ADDL	PRAI_NUM_09	PRAI_NUM_09,	PKG_VALIDATION.EXT_VAL_NO	1	
PGIT6_03	10-PD-03_01	WHEN-VALIDATE-ITE	PGIT_POL_RISK_ADDL	PRAI_NUM_03	PRAI_NUM_03,	PKG_VALIDATION.EXT_VAL_NO	1	
PGIT6_03	10-PD-03_01	WHEN-VALIDATE-ITE	PGIT_POL_RISK_ADDL	PRAI_DATA_03	PRAI_DATA_03,	PKG_VALIDATION.EXT_VAL_VEH	2	
PGIT6_03	10-PD-03_01	WHEN-VALIDATE-ITE	PGIT_POL_RISK_ADDL	PRAI_DATA_03	PRAI_DATA_03,	PKG_VALIDATION.EXT_VAL_VEH	2	
PGIT6_03	10-PD-03_01	WHEN-VALIDATE-ITE	PGIT_POL_RISK_ADDL	PRAI_DATA_03	PRAI_DATA_03,	PKG_VALIDATION.EXT_VAL_VEH	2	

Error Yn ☒ Clear Field YN ☐ Validate YN ☒

Action* DEFAULTING

Remarks DEFAULTING

Fig. 234 – Product - Front End EV

❑ Back End EV – Click this button to view the back end external validation of the Product Code

Type	Trigger Type	Block Name*	Field Name*	Stmt Type	Statement	S. No	Error No	Error Type
U	POST-UPDATE	PGIT_POL_RISK_ADDL		D	PKG_VALIDATION.EXT_PR_DFT_CVR_DTLS_P	1		N
V	WHEN-VALIDAT	PGIT_POL_RISK_ADDL	PRAI_DATE_05	D	PKG_VALIDATION.EXT_VAL_DRIVER_AGE(PG	1		N
V	WHEN-VALIDAT	PGIT_POL_RISK_ADDL	PRAI_DATE_05	D	PKG_VALIDATION.EXT_VAL_DRIVER_AGE_101	1		N
U	POST-INSERT	PGIT_POL_RISK_ADDL		D	EXT_VAL_DRIVER_NAME_VALID(PGIT_POL_F	1		N
U	POST-UPDATE	PGIT_POL_RISK_ADDL		D	EXT_VAL_DRIVER_NAME_VALID(PGIT_POL_F	2		N
U	POST-INSERT	PGIT_POL_RISK_COVER		D	PKG_VALIDATION.EXT_VAL_MOT_TP_CVR_VAL	1		N
U	POST-UPDATE	PGIT_POL_RISK_COVER		D	PKG_VALIDATION.EXT_VAL_MOT_TP_CVR_VAL	2		N
U	POST-INSERT	PGIT_POL_RISK_COVER		D	PKG_VALIDATION.EXT_VAL_MOT_CVR_VALID	1		N
U	POST-UPDATE	PGIT_POL_RISK_COVER		D	PKG_VALIDATION.EXT_VAL_MOT_CVR_VALID	2		N
V	WHEN-VALIDAT	PGIT_POL_RISK_COVER	PRC_CODE	D	PKG_VALIDATION.EXT_VAL_CVR_AOY_AOA_D	1		N

Type Description: Update

Trigger Type Description: POST UPDATETRIGGER

Block Description: PGIT_POL_RISK_ADDL_INFO_01

Field Description:

Statement Description: Procedure

Error Description:

Remarks: Risk Cover Default Logic

Fig. 235 – Product - Back End EV

Other Details

Click this button to define the condition, deductible, discount, loading, IBNR Details for the Product at product level. The system displays the screen as shown below:

Condition Code*	Product Code	Level	Description	Effective Frn Dt	Effective To Dt	Type
8049	1001	PROD	Free Text1	01/01/2000	01/05/2013	06
8050	1001	PROD	Free Text2	01/01/2000	01/05/2013	06
8051	1001	PROD	Free Text3	01/01/2000	01/05/2013	06
8052	1001	PROD	Free Text4			06
8053	1001	PROD	Free Text5			06

Short Description: Free Text1

Long Description 1: Free Text1

Long Description 2: Free Text1

Return

Fig. 236 – Product - Other Details

Refer [Product Setup](#) section in this manual for more information on field details.

Script Generator

Click this button to generate scripts for the programs. The purpose of this script generator is to generate scripts for the changes made in the product or if required, the script for the entire product, i.e., all back end tables containing the product code/details.

The system displays the screen as shown below:

Product: 1001

File Name: 44

Path: 8 Browse

Commit after: 50 Rows

Incremental Sc... Complete Script Return

Fig. 237 – Script Generator

Product

By default the system displays the Product code.

File Name

Enter the name of the file for generating scripts in which the generated script is to be placed or saved.

Path

Enter the path or click Browse to select the respective file from the path in which the generated script is to be saved.

Commit after

Select the rows to commit (save) the transactions when scripts are executed.

- ☐ Incremental Script – Click this button to generate scripts on an incremental basis based on the changes done. This implies that the scripts are generated only for the changes done to the product
- ☐ Complete Script – Click this button to generate complete script for the entire product from various back-end tables involved

Product Copy

Click this button to copy the product setup into new product.

Fig. 238 – Product Copy

Product Delete

Click this button to delete existing product setup.

Sections

This block allows the user to define or map the applicable sections for the product. The system displays the screen as shown below:

Fig. 239 – Product – Section Details

Details

Click this button to setup the section level details of the product.

Click the respective tabs available in the screen to attach applicable condition, deductible, cover, discount, loading, SMI and SMI group for the product at section level.

Fig. 240 – Product – Section level details

Refer [Product Setup](#) section in this manual for more information on field details.

Copy

Click this button to duplicate product and section level details to new product/section level.

Fig. 241 – Section level Copy

Preview

Click this button to view the Risk Details applicable for the product at section level.

Section Delete

Click this button to delete the section details applicable for the product.

Risk Details

Click this button to define the risk level details applicable for the product. User can configure Risk Data Blocks to provide clutter free, product specific screens.

Condition Code*	Product Code	Level	Description	Effective Fr Dt	Effective To Dt	Type	Default
1001		F					☐
							☐
							☐
							☐

Short Description

Long Description 1

Long Description 2

Return

Fig. 242 – Risk Details for the Product

Fields

This block allows the user to configure the Risk blocks for a product as well as product-specific data items.

Sr No	Field Name*	Position	Disp Length	X Pos	Y Pos	Text	Data Type	LOV	EV
1	PRAI_RISK_ID		30	110	13	Vehicle ID*	Text	LOV	EV
2	PRAI_EFF_FM_DT		80	110	31	Veh. Entry Dt	Date	LOV	EV
2	PRAI_YN_02		40	110	49	Cert. Req'd YN	Yes/No	LOV	EV
3	PRAI_DATA_08		40	190	49	Cert. Mode	Text	LOV	EV
3	PRAI_EFF_TO_DT		80	256	31	Veh. Exit Dt	Date	LOV	EV
4	PRAI_CODE_14		40	295	49	Cert. Type	Text	LOV	EV
5	PRAI_DATA_09		30	110	66	Book ID	Text	LOV	EV
6	PRAI_DATA_05		80	256	66	Cert No.	Text	LOV	EV

Hide ☐ Enterable ☒ Updatable ☒ Mandatory ☐ Correction YN ☐ Claims Lookup YN ☐

Dft Value Number Range From To

Num Format Mask Date Range From To

Fig. 243 – Product – Field Level details

Refer [Block Definition](#) section under Product Setup for more information on field details.

PRODUCT CHANGER

This screen enables the user to change an existing product codes to new product codes at master level. The system displays the screen as shown below:

Fig. 244 – Product Changer

Old Code

Enter the Old Code of the Product.

New Code

Enter the New Code of the Product.

Likewise enter the Old Code and New Code for the following items:

- ☐ Policy Type
- ☐ Section
- ☐ Cover
- ☐ SMI
- ☐ Discount
- ☐ Loading
- ☐ Deductible
- ☐ Conditions

Click 'OK' to save.

Click 'Create Master' to create the respective masters for the new product code.

PRODUCT CHANGER QUERY

Click this menu to query and view the old and new Product code details.

NAJM NET PROCESSING MASTERS

This menu enables the user to generate and validate a XML data file to be shared with Najm Net authority during inclusion or deletion of a vehicle by new policy or inclusion of vehicle endorsement.

The menu comprises of the following sub-menus:




Fig. 245 – Najm-Net Processing Masters

NAJM-NET APPLICABLE PRODUCT MAPPING

This menu enables the user to map the products with NAJM-NET. The system displays the screen as shown below:




Fig. 246 – Najm-Net Product Mapping

Enter the 'Product Code' and the 'Product Description' to map the product with Najm-Net. Click 'Save'.

NAJM-NET FIELD MAPPING

This menu enables the user to perform the setup by fetching the field details from underwriting screen to be shared with Najm Net.




Fig. 247 – Najm Net Field Mapping

Map Type

Select the appropriate map type to map respective policy field information to Najm Net.

☐ ROW_HEADER – Select this option to map the Policy details and Assured details

☐ DRIVER – Select this option to map the driver field details

☐ VEHICLE – Select this option to map the vehicle field details

Product Code

Enter the Product Code that is mapped in applicable products.

Section Code

Enter the Section Code mapped in applicable products.

Info Field

Enter the field name (field prompt) displayed in the Policy screen for mapping.

Table Name

Enter the corresponding PREMIA table name.

Field Name

Enter the corresponding field name being mapped in the Table

Sr. No

Enter the serial number to be inserted in Najm Interface table.

Req YN

Select 'Yes' option if the user needs to share the record details with Najm Net.

NAJM STATUS QUERY

This menu enables the user to query and view the Najm Status of a Policy.

The screenshot displays the 'NAJM STATUS QUERY' interface. At the top, there are search filters for Policy No, Customer Code, Plate No, Custom ID, and Sequence No, along with a 'Query' button. Below the filters, there are tabs for 'Pending', 'Success', and 'Failed'. The main section shows a table with columns: Policy No, Nn Pid, End No Idx, Insured Name, Status Code, Status Desc, Upload Flag, Service Type, and Upload Dt. The table lists several policies, all with a 'Pending' status and 'Insert' service type. At the bottom, there is a form for insured details including Insured Type, Insured ID/CR No, Insured City, Insured Id Ver Typ, Pol. Max Liability, Insured Po Code, Insured Ph No, Insured Mob No, Insured Po Box, and Driver Age Limit.

Policy No	Nn Pid	End No Idx	Insured Name	Status Code	Status Desc	Upload Flag	Service Type	Upload Dt
P/100/1002/2013/00096		0	Agent 001			Pending	Insert	26/09/2013
P/100/1002/2013/00113		0	Agent 001			Pending	Insert	14/10/2013
P/100/1002/2013/00113		0	Agent 001			Pending	Insert	14/10/2013
P/100/1002/2013/00116		0	Agent 001			Pending	Insert	25/10/2013
P/100/1002/2013/00121		0	Agent 001			Pending	Insert	30/10/2013
P/100/1002/2013/00122		0	Agent 001			Pending	Insert	30/10/2013
P/100/1002/2013/00123		0	Agent 001			Pending	Insert	30/10/2013
P/100/1002/2013/00125		0	Mr. Madhivanan Balakrishnan			Pending	Insert	30/10/2013
P/100/1002/2013/00126		0	Mr. Madhivanan Balakrishnan			Pending	Insert	30/10/2013
P/100/1002/2013/00130		0	Agent 001			Pending	Insert	31/10/2013

Insured Type: Individual Insured ID/CR No: 687858 Insured City: Insured Id Ver Typ: Non-Saudi Pol. Max Liability: 0 Insured Po Code: Insured Ph No: ggswgw Insured Mob No: 1231231231 Insured Po Box: Driver Age Limit: 34

Fig. 248 – Najm Status Query

Enter any one of the fields to query for the Policy/Vehicle/Driver details:

- ☐ Policy No
- ☐ Customer Code
- ☐ Plate No
- ☐ Custom ID
- ☐ Sequence No



Query

Click this button to query and view the policy, vehicle and driver details with the status.

TAB Policy

Click this tab to view the policy information shared with Najm Net after policy approval. The system displays the screen as shown below:

Policy	Vehicle	Driver						
Policy No	Nn Pid	End No Idx	Insured Name	Status Code	Status Desc	Upload Flag	Service Type	Upload Dt
P/100/1002/2013/00096		0	Agent 001			Pending	Insert	26/09/2013
P/100/1002/2013/00113		0	Agent 001			Pending	Insert	14/10/2013
P/100/1002/2013/00113		0	Agent 001			Pending	Insert	14/10/2013
P/100/1002/2013/00116		0	Agent 001			Pending	Insert	25/10/2013
P/100/1002/2013/00121		0	Agent 001			Pending	Insert	30/10/2013
P/100/1002/2013/00122		0	Agent 001			Pending	Insert	30/10/2013
P/100/1002/2013/00123		0	Agent 001			Pending	Insert	30/10/2013
P/100/1002/2013/00125		0	Mr.Madhivanan Balakrishnan			Pending	Insert	30/10/2013
P/100/1002/2013/00126		0	Mr.Madhivanan Balakrishnan			Pending	Insert	30/10/2013
P/100/1002/2013/00130		0	Agent 001			Pending	Insert	31/10/2013
Insured Type	Individual		Insured ID/CR No	687858		Insured City		
Insured Id Ver Typ	Non-Saudi		Pol. Max Liability	0		Insured Po Code		
Insured Ph No	ggswwg		Insured Mob No	1231231231		Insured Po Box		
Driver Age Limit	34							

Fig. 249 – Policy Tab

Policy No

The system displays the approved Policy number.

End No

The system displays the endorsement number if any for the policy.

Insured Name

The system displays the name of the insured.

Upload Flag

The system displays the status of the Policy received from Najm Net as one of the following:

- ☐ Pending – - Transaction is not yet uploaded to Najm Net
- ☐ Success – On successful upload, the transaction is back updated with the Najm Unique Id in the interface tables
- ☐ Failed – When the status is failed during upload to Najm Net
- ☐ Reprocess – User needs to reprocess the records and re-upload to Najm Net
- ☐ Corrected – Transaction that is corrected during endorsement when the policy was in Failed status
- ☐ Rejected – Transaction is rejected finally due to some reasons

Service Type

The service type is displayed as one of the following for the corresponding transaction:

- ☐ Insert - newly inserted records
- ☐ Delete - deleted or cancelled
- ☐ Update - updated records.

Upload Date

The system displays the date of transaction upload.

The other details displayed in this screen from the Customer Master are:

- ☐ Insured Type
- ☐ Insured ID/CR No
- ☐ Insured City

- ☐ Insured Id Ver Type
- ☐ Pol Max Liability - This is total policy SI including the Third party liability(sum of all covers SI)
- ☐ Insured Po Code
- ☐ Insured Phone No
- ☐ Insured Mobile No
- ☐ Insured Po Box
- ☐ Driver Age Limit – This field is populated based on the vehicle owner's (Insured's) age calculated based on the Date of birth included in the insured master

TAB Vehicle

Click this tab to view the vehicle details applicable for that transaction. The system displays the screen as shown below:

Policy	Vehicle	Driver							
NN Vid	Def Type	Plate No	Custom Id	Sequence No	Status Code	Status Desc	Upload Flag	Service Type	Upload Dt
	1		12454545	8785454			Pending	Insert	26/09/2013
	2		2222				Pending	Insert	14/10/2013
	2		2222				Pending	Insert	14/10/2013
	1						Pending	Insert	25/10/2013
	1						Pending	Insert	30/10/2013
	1						Pending	Insert	30/10/2013
	2		587544				Pending	Insert	30/10/2013
	2		99999				Pending	Insert	30/10/2013
	2		99999				Pending	Insert	30/10/2013
	2	879788		99999			Pending	Insert	30/10/2013

Hijri Issue Dt	21/11/1434	Hijri Eff Dt	21/11/1434	Hijri Exp Dt	01/12/1435	Chassis No	79879794545
Gregorian Iss Dt	26/09/2013	Gregorian Eff Dt	26/09/2013	Gregorian Exp Dt	26/09/2014	Manufacturing Yr	2013
Manufacturer	ADMIRAL	Model	3	Coverage Type	1	Color	
Plate Type	26	Risk ID	1	Plate Letters	a a a	Category	PRIVATE
Privu Pol No	P/100/1002/2013/00096/1						

Fig. 250 – Vehicle Tab

The system displays the following vehicle details:

- ☐ Vehicle Plate Number – The plate number of the vehicle captured in the vehicle details tab
- ☐ Custom Id – Customer Code
- ☐ Coverage Type – the type of coverage based on the Product details selected (sub class code Ex: 23101- Motor Comprehensive / 23102- Motor TPL in case of Takaful Or 13101- Motor Comprehensive / 13102- Motor TPL in case of cooperative) during the entry of the transaction
- ☐ Issue Date (Hijri) – The Policy Inception Date captured and converted to Hijri date format and shared with Najm Net. In case of endorsements, this date will be endorsement date
- ☐ Effective Date (Hijri) – The Vehicle entry date captured is converted to Hijri date format and shared with Najm Net. The same date is applicable for endorsements.
- ☐ Expire Date (Hijri) – The Vehicle exit Date captured and converted to Hijri format and shared with Najm Net. The same date is applicable for endorsements
- ☐ Issue Date (Gregorian) – The Policy Inception Date captured and shared with Najm Net. In case of endorsements, this date is endorsement in inception date.
- ☐ Effective Date (Gregorian) – The Vehicle Entry date captured and shared with Najm Net. The same date is applicable for endorsements.
- ☐ Expire Date (Gregorian) – The Vehicle exit Date captured and shared with Najm Net. The same date is applicable for endorsements

TAB Driver

Click this tab to view the driver detail applicable for that transaction. The system displays the screen as shown below:

Policy			Vehicle			Driver		
NN DID	English Name	License No	Status Code	Status Desc	Upload Flag	Service Type	Upload Date	
	SANKAR	1234567890			Pending	Insert	26/09/2013	
	sankhi	1234567890			Pending	Insert	25/10/2013	
	sankhi	1234567890			Pending	Insert	30/10/2013	
	sankhi	1234567890			Pending	Insert	30/10/2013	
		1234567890			Pending	Insert	26/09/2013	
	sankhi	1234567890			Pending	Delete	30/10/2013	
	sankhi	1234567890			Pending	Delete	30/10/2013	
	sankhi	1234567890			Pending	Insert	23/10/2013	
		1234567890			Pending	Insert	30/09/2013	
		1234567890			Pending	Insert	30/09/2013	

Arabic Name		Driver Id Ver Type	
License Type	1	Pol No	P/100/1002/2013/00096

Fig. 251 – Driver Tab

BUSINESS RULE MASTER

Business Rule is a run time validation which insists the system while processing the transaction:

- ☐ To apply a factor to the basic/calculated premium
- ☐ To add loading/discount and apply deductible to the net premium
- ☐ To show warning/error message that allows the user to proceed further or to stop the transaction until the error is corrected

	The Business Rule is applicable only for an Underwriting and Claims transaction. It is not applicable to other modules
---	--

The Admin user is able to define the business rule for a Quote / Policy / Endt. There is a facility to accept, decline or referral for each rule. Using this feature the administrator is allowed to define the required business rule and also automatically validated by the system during transaction.

	The user must have the basic SQL knowledge to execute this operation.
---	---

The 'Business Rule Master' menu comprises of the following sub-menus:

-	Business Rule Master
o	Business Rule Relation Master
o	Business Rule Definition Master

Fig. 252 – Business Rule Master

BUSINESS RULE RELATION MASTER

The Business Rule Relation Master is a onetime setup master screen used to build the relationship between single or more than one policy transaction details (blocks) in PREMIA.

User is able to define the association between policy and products. It also defines a relation for product, instance and section with validity period for which the relation is defined

Apart from creating a new rule this screen also facilitates the option of retrieving a saved record. User can enter a field value in the upper pane of the screen and click the 'Query' button. All the relevant details are defaulted in the corresponding fields.

To define the business rule,

- ☐ Define a relation for a Product and Instance with validity period.
- ☐ Use the key columns example - driver age, vehicle age and vehicle model using the Policy, Vehicle and Driver details information.
- ☐ Define the relation between the tables used in PREMIA
- ☐ Identify each relation by business rule relation code and name. User has the option to define the relation using more than two tables. All the table names and column names are displayed as defined by the user (like Vehicle detail, Driver detail, Age, Date of birth) in instance definition / program definition / product setup and not the actual table name and column name defined in the PREMIA UW/Claims transaction table.
- ☐ Define the relation code and name that will be used in business rule setup
- ☐ Save the rule to generate a unique business relation code

The system displays the screen as shown below:

SL No.	Inst/Prod	Instance/Product Code*	Block Name-1*	Alias Name	Field Name-1*	Function Operator	Inst/Prod	Instance/Product Code*	Block Name-2*	Alias Name	Field Name-2*	Fixed Co
1	Pr...		Vehicle Details	PGIT_POL_	Chassis No.	Select						
2	Pr...		Vehicle Details	PGIT_POL_	Chassis No.	=						B3456
3	Pr...		Vehicle Details	PGIT_POL_	PRAI_POL_SYS	=	In...	10-PD-01_01	PGIT_POLICY	PGIT_POLI	POL_SYS_ID	
4	In...	10-PD-01_01	PGIT_POLICY	PGIT_POLI	POL_SYS_ID	Key C...						
5												

Fig. 253 – Business Rule Relation Master

BR (Business Rule) Relation Prefix

Enter a unique prefix to identify the new business rule.

BR Relation Code

On saving the business rule, the BR relation code is generated by the system.

The relation code is a combination of the prefix entered in the 'BR Relation Prefix' field and an auto-generated serial number. A provision is defined to relate the relation code and name which is used in business rule setup. This code is unique and the user is not allowed to modify the code.

BR Relation Name

Enter a relevant business rule relation name.

Product Code / Instance Code / Section Code

Select from the LOV the Product, Instance codes for which the relation is being defined. The Instance code selected here must map to the Instance Code in the Policy or Claim Registration or Claims Settlement screen.



Multiple instances for a single product are allowed. Instances are the duplication of the same product details. In instances there is an option to enable or disable required blocks and fields.

Effective From Date/Effective To Date

Enter the validity period for using this rule. The date from when the entered rule is to be applied, till the end date.

Save the details.

Select Statement

After saving the details, the Select statement is generated automatically with prefix entered by user which is applied at the transaction level.

TAB **Business Relation**

This block allows the user to define the table and column name by defining them in the Instance / Product Code field.

SI. No

By default, the serial number is 1.

Enter the serial number to build the order in which the “where” clause for the rule is to be applied.

Inst/Prod (Instance/Product)

Select the relevant option from the drop-down list, which are applicable to the instance code / product code defined for corresponding relation code. Subsequent fields are enabled for entering the data based on the option selected.



Block Name 1

Select from the LOV, the block name. The LOV displays all the PREMIA Tables and Block names like Policy header details, Risk Info details and Field details.

Alias Name

The system defaults the Alias name while selecting the blocks. It is also user enterable field.

Select the corresponding table name which is applicable to the selected Instance / Product code in the previous field.



Field Name 1

Select the corresponding field name which is applicable to the block name selected in the 'Block Name' field.



Function Operator

Select the required operator to set the condition for the relation being built. The available options are:

- ☐ Select – This option means to select the main columns from the PREMIA screens which can be used for building the business rule. For example, the driver age or vehicle age or vehicle model or policy holder details or policy holder previous claim details can be selected. The selected columns only can be used in the parameter details screen in business rule definition master.
- ☐ Key Column – Column defined as 'Key Column' is used to pass the actual value during the transaction. Only those columns defined in the parameter setup as 'KEY_COL' are chosen as the Key Columns
- ☐ &
- ☐ Join – This option is used to give the relation between two PREMIA blocks. If this option is used, then the system allows the user to select the Block Name-2 and Field name -2 values. This means that when more than one PREMIA blocks are used, then the user must give the relation between the 2 PREMIA blocks
- ☐ '=' – If this option is selected, the following fields are enabled.
 - o Instance/Product Code
 - o Block Name - 2
 - o Alias Name
 - o Field Name - 2
- ☐ '>=',
- ☐ '<=',
- ☐ '>',

- ☐ '<'
- ☐ 'Not in'
- ☐ 'Like'
- ☐ 'Not Like'
- ☐ 'In'
- ☐ 'Blank Condition'.

The relation defined needs to be linked with the adjacent columns which define the following:

Instance Product Code

Select the instance / product code which are applicable to the instance code / product code defined for corresponding relation code



Block Name 2

Select the corresponding table name which is applicable to the selected instance / product code in the previous field.

This Block is linked with the Block Name- 1 to construct the business rule condition.

Alias Name

The system displays the alias name based on the blocks selected.



Field Name – 2

Select the corresponding field name which is applicable to the block name selected in the previous field 'Block Name 2'.

This field name is linked with the Field Name -1 name to construct the business rule condition.

Fixed Column

If the function/operator is selected as '=', '>=', '<=', '>', '<', 'Not in', 'Like', 'Not Like', 'In' then this field is mandatory.

This is the free text column. Enter any fixed condition here. With Single Code like '30'. The length of this column will be 240 characters.

Click 'Save' to save the BR Relation master details. On saving, the system generates the BR Relation Code.

The 'Confirm' button is enabled.

Confirm

Click 'Confirm' to confirm the relation code and name is used in business rule setup. On confirming, the query statement (as highlighted) is displayed as shown below:

Business Rule Relation Master

BR Relation Prefix: B2
BR Relation Code: B2-37
BR Relation Name: BUSINESS RULE 2

Product Code*: 1001 Motor Commercial
Instance Code*: 10-PD-01_01 Instance Header For Motor Direct
Section Code*: 100101 Motor Commercial

Effective From Date: 06/11/2013 Effective To Date: 06/11/2016

Select Statement: **SELECT 'X' FROM PGIT_POLICY PGIT_POLICY,PGIT_POL_RISK_ADDL_INFO PGIT_POL_RISK_ADDL_INFO WHERE PGIT_POL_RISK_ADDL_INFO.PRAI_DATA_01 =**

Business Relation

SL. No.	Inst/ Prod.	Instance/ Product Code*	Block Name- 1*	Alias Name	Field Name - 1*	Function Operator	Inst/ Prod.	Instance Product Code*	Block Name- 2*	Alias Name	Field Name - 2*	Fixed Co
1	Pr...		Vehicle Details	PGIT_POL_	Chassis No.	Select						
2	Pr...		Vehicle Details	PGIT_POL_	Chassis No.	=						'B3456'
3	Pr...		Vehicle Details	PGIT_POL_	PRAI_POL_SYS_	=	In...	10-PD-01_01	PGIT_POLICY	PGIT_POLI(POL_SYS_ID		
4	In...	10-PD-01_01	PGIT_POLICY	PGIT_POLI(POL_SYS_ID	Key C...							

Fig. 254 – BR Relation Code

Copy

Click this button to copy the details of the business rule relation to a fresh rule.

Confirm/Amend

Click Confirm button to approve the rule created. Once the created rule is confirmed the 'Confirm' button changes to 'Amend'. Once the rule is confirmed, user can modify by clicking the 'Amend' button.

Similarly, the user can define the Business Relation between Claims transaction tables also as shown in the screen below:

Business Rule Relation Master

BR Relation Prefix:

BR Relation Code: BR Relation Name:

Product Code*:

Instance Code*:

Section Code*:

Effective From Date: Effective To Date:

Select Statement:

Business Relation

SL No.	Inst/ Prod.	Instance/ Product Code*	Block Name- 1*	Alias Name	Field Name - 1*	Function Operator	Inst/ Prod.	Instance/ Product Code*	Block Name- 2*	Alias Name	Field Name - 2*	Fixed C
1	Pr...		Risk Details	Risk	Limit Per Carryin	Select						
2	Pr...		Risk Details	Risk	Limit Per Carryin							*100000
3	Pr...		Risk Details	Risk	PRAI_POL_SYS_	=	In...	PGIT8000-014	PGIT_CLAIM	CLAIM	Cim Pol Sys Id	
4	In...	PGIT8000-01	PGIT_CLAIM	CLAIM	CLM_SYS_ID	Key C...						

Fig. 255 – Business Rule Relation Master – Claims

BUSINESS RULE DEFINITION MASTER

In Business Rule Definition Master the user is able to apply/add/modify/delete any Business rule. The purpose of this business rule definition screen is to guide the system to apply one or more than one condition for that type of transactions.

For example, creation of quotation/policy/during endorsement/renewal/ claims or settlement in accordance with the business rules and set the rule at various stages in the transaction.

TAB BR Header

The system displays the screen as shown below:

BR Header | Applicable Places | BR Key Columns | Cover Details | Endt Codes | Action

Rule Code:

Rule Name:

Business Type From*: Business Type To*:

Source Type From*: Source Type To*:

Effective Date From: Effective Date To:

Product Code*:

Instance Code*:

Section Code*:

Business Rule Type: Authorization Type:

Error / Warning Message:

Fig. 256 – BR Header



Ensure that the user completes all the entries in the tab to set the Business Rule.

UW/CLAIM

Select the stage at which the user needs to apply the business rule.

Rule Code

On saving the details, the system automatically generates the rule code for every business rule. The business rules are identified using this code.

Rule Name

Enter a unique rule name. All business rules are captured with the relevant rule name.

Business Type From/To

Enter or select, from the LOV, the business codes for which the business rule needs to be applied. The default values are '0' and 'zzzz' in the 'From' and 'To' fields respectively. This is the minimum and maximum values for the range. On selecting the relevant code, the description of the code gets automatically displayed in the adjacent field.

The business rule is based on the source and business types.

Source Type From/To

Enter or select, from the LOV, the source type for which the business rule needs to be applied. The default values are '0' and 'zzzz' in the 'From' and 'To' fields respectively. This is the minimum and maximum values for the range. On selecting the relevant code, the description of the code gets automatically displayed in the adjacent field.

The business rule is based on the source type and business type.

Effective Date From/To

Enter or select from the LOV, the date range within which the business rule is to be applied.



Ensure that the date range is equal to the date defined in Business Relation Master.

Product Code

Enter or select, from the LOV, the Product Code for which the business rule needs to be applied. The product code's description is defaulted in the adjacent field.

Instance Code

Enter or select, from the LOV, the Instance Code for which the business rule needs to be applied. The instance code's description is defaulted in the adjacent field.

Section Code

Enter or select, from the LOV, the Section Code for which the business rule needs to be applied.

Business Rule Type

Select the type of business rule from the drop-down list. The available options are:

- ☐ Terms and Conditions – Select this option to define the conditions for this business rule
- ☐ Business Rule – Select this option to define any error/warning message to be displayed for a transaction under UW Rule Log / Claims Rule Log.



The rule defined in the system is applied either during the policy approval or premium calculation, based on the applicable From/To places defined in the Applicable Places tab.

- ☐ User Authorization (for future enhancement) - Refers to multiple approvals to users with respect to the transaction type such as Policy, Quote and Endt. so on



This field is for future enhancement.

Error/Warning Message

This field is enabled only when the Business Rule Type is selected 'Business Rule'.

Enter the error or warning message to be displayed in UW Rule Log / Claims Rule Log when the business rule fails.

Click 'Save'. On saving the Rule Code is generated and 'Confirm' button is enabled.

TAB Applicable Places

Click this tab to define the link between the 'Applicable At' and the 'Applicable For' column. Therefore, during the transaction, the system picks the applicable rules depending on the transaction business type and source type and applies the rules in the order of priority defined in the setup.

The system displays the screen as shown below:

Serial No.	Applicable For	Applicable At
1	Policy	Before Premium Calculation

Fig. 257 – Applicable Places



Applicable For

Select the option from the drop-down list. The option states the stage of transaction in which the rule has to be applied. The options are available are:

- ☐ Policy
- ☐ Quote
- ☐ Endt
- ☐ Renewal
- ☐ Claims
- ☐ Settlement



Applicable At

Select the relevant status option to apply the rule based on Instance Code from the drop-down list. The options available are:

- ☐ Before Premium Calculation
- ☐ Before Policy Approval
- ☐ Before Claim Approval

☐ Before Claim Settlement

TAB BR Key Column

Click this tab to define the list of columns (Key columns) to be used to construct the business rule. The values are in range for the factors used in the business rule.

The system displays the screen as shown below:

Relation Code*	Relation Name	BR- Key Data*	BR - Key Data	Condition	Operator	Fixed Condition
B2-37	BUSINESS RULE 2	PRAI_DATA_01	Chassis No.	Condition	=	'B3456'
B2-37	BUSINESS RULE 2	POL_SYS_ID	POL_SYS_ID	Key Column		

Fig. 258 – BR Key Columns



Relation Code

Enter or select a unique relation code from the LOV. The code's description is defaulted in the 'Relation Name' field.



BR-Key Data

Enter or select the 'BR-Key Data' from the LOV. Based on the key data selected, the corresponding value is displayed in the 'BR-Key Data' field. The LOV displays those fields which were selected as 'Select' or 'Key Column' in the Function Operator field in the 'Business Rule Relation Master' screen.

Condition

This field displays the options based on the 'BR Key Data' selected. The options and their definition are given below.

☐ Condition – If this option is selected then the fields 'Operator' and 'Fixed Condition' is enabled.

☐ Key Column

Operator

Select any value from the drop-down list. Based on the option selected the condition for the relation is built.

Fixed Condition

Enter the condition that was defined in Business Rule Relation Master under 'Fixed Column' field. This is a free text column. This field is mandatory if the 'Operator' option is selected.

Save the tab details.

TAB Cover Details



This tab is not applicable for Claims.

Click this tab to define the applicable covers for a business rule. The system displays the screen as shown below:

BR Header	Applicable Places	BR Key Columns	Cover Details	Endt Codes	Action
Serial No.	Cover Code*	Cover Description	Applicable YN		
1	3101	Own Damage	☒		
			☐		
			☐		
			☐		
			☐		
			☐		
			☐		
			☐		
			☐		
			☐		
			☐		
			☐		

Fig. 259 – Cover Details

Serial No

Enter the serial number.

Cover Code

Enter or select from the LOV, the cover code to apply the business rule. Based on the option selected the description is defaulted in the 'Cover Description' field.

Applicable YN

Select the check box if the selected rule needs to be applied to the package/cover code selected.

TAB Endt Codes

	This tab is not applicable for Claims.
---	---

Click this tab to define the endorsements applicable to a business rule. The rule is validated only if the transaction belongs to the respective endorsement.

The system displays the screen as shown below:

Serial No.	Endorsement Code*	Endorsement Description	Applicable YN
1	ED002	Increase of Sum Insured	☒
			☐
			☐
			☐
			☐
			☐
			☐
			☐
			☐
			☐

Fig. 260 – Endt. Code

Serial No

Enter the serial number.

Cover Code

Enter or select from the LOV, the endorsement code to apply the business rule. Based on the option selected the description is defaulted in the adjacent field.

Applicable YN

Select the check box if the rule needs to be applied for this endorsement code.
Save the details.

TAB Action

Click this tab to assign the level of authority to the user/user group to perform the transaction. This tab is enterable only if the 'Business Rule Type' selected is either 'Business Rule' or 'Terms & Conditions' or 'User Authorization' in the 'BR Header' tab.

The system displays the screen as shown below:

Serial No.	Level No.	User/ User Group	User/ User Group Code*	Action	Error Warning	Applicable YN
1		User	PDC01	Decline	Error	☒
						☐
						☐
						☐
						☐
						☐
						☐
						☐
						☐
						☐

Fig. 261 – Action

Serial No.

Enter the serial number in this field. By default, serial number is 1.

Level No.

This is applicable only if the rule type is 'User Authorization'.

Enter the level number as per the rank assigned to the user/ user group in the hierarchy.



This field is for future enhancement.

User/User Group

Select the user category from the drop-down list. The available options are.

- ☐ User
- ☐ User Group
- ☐ Others

User/User Group Code

Enter or select the user/user group code from the LOV. The options available in the LOV are based on the 'User/User Group' category selected.

Action (Underwriting Action)

Enter or select the underwriting action from the drop-down list. The transaction varies based on the underwriting action selected. The action types and their outcome during transaction are listed below.

- ☐ Decline – If this option is selected the system displays a pop-up message stops the user from proceeding further
- ☐ Terms & Conditions – If this option is selected, the system displays a pop-up message and allows the processing after adding the specified terms and conditions. If this is selected the 'Terms and Conditions' button gets enabled



This action is not applicable for Claims.

- ☐ Refer – If this option is selected, the system will divert the approval process to some other underwriter



This action is not applicable for Claims.

A workflow item is generated by the system automatically when the Referral option is selected.

- ☐ Accept – If this option is selected, the system displays a pop-up message and allows the user to continue with the transaction



If the 'Business Rule Type' is 'User Authorization' then the 'Action' displays 'Accept' by default.

If the 'Business Rule Type' is 'Terms & Condition' then the 'Action' displays 'Terms & Condition' by default

Error/Warning

Select the relevant option from the drop-down list. This option is provided for the U/W Action. If the action fails to meet the criteria the system throws an error/warning message to the user.

Appl YN (Applicable Yes/No)

Select the check box if the entered action needs to be applied for the specific user/user groups/others.

Terms & Conditions

If the selected 'Business Rule Type' is 'Terms & Conditions' in the 'BR Header' screen, then the Terms & Condition button is enabled under the 'Action' tab. The system displays the screen as shown below:




Fig. 262 – Terms & Condition

Terms/Condition Type

By default the system displays the Condition Type as 'Condition'. The available values are:

- ☐ Discount
- ☐ Loading
- ☐ Excess

Terms/Condition Code

Enter or select the code from the LOV. The code's detail is defaulted in the 'Description' field. If the given criteria in the business rule are successful then at the time of transaction this term is added.

Perc/Fixed Amt

Select the calculation type from the drop-down list. The options available are given below:

- ☐ Percentage
- ☐ Amount

Value

If the calculation type is selected as 'Amount', then enter the amount value in this field.

Rate Per

Enter the percentage rate in this field.

Appl At

Select the option from the drop-down list. This field provides the options of when to apply the term. The options are listed below.

- ☐ Policy
- ☐ Cover
- ☐ Section
- ☐ Risk

Appl YN

Select the check box if the condition needs to be added at the time of transaction.

Click 'Main' to navigate to previous screen.



Confirm/Amend

After entering all the tab details, click 'BR Header' tab.

Click 'Confirm' to approve the rule created. Once the rule created is confirmed the 'Confirm' button changes to 'Amend'.

The screenshot shows the 'BR Header' tab of the Business Rule Definition Master form. The form contains the following fields and values:

Rule Code	72	UW/CLAIM	UW	
Rule Name	Rule 1			
Business Type From*	0		Business Type To*	////
Source Type From*	0		Source Type To*	////
Effective Date From	06/11/2013		Effective Date To	06/11/2016
Product Code*	1001	Motor Commercial		
Instance Code*	10-PD-01_01	Instance Header For M		
Section Code*	100101	Motor Commercial		
Business Rule Type	Business Rule		Authorization Type	
Error / Warning Message	Display the error message			

Buttons: Copy Bus Rule, Amend

Fig. 263 – Business Rule Definition Master with Amend Button

Once the rule is confirmed, user cannot change the entered data.

To modify, click the 'Amend' button.



Copy Bus Rule (Copy Business Rule)

User is provided with a copy facility to copy the details of the business rule definition master to a fresh rule.

Click 'Copy' after confirmation of the rule. The business rule is copied with all the details except the rule name.

End of Document