# ETSITS 102 868-1 V1.3.1 (2015-07)



Intelligent Transport Systems (ITS); Testing;

Conformance test specifications for Cooperative Awareness Basic Service (CA); Part 1: Test requirements and Protocol Implementation Conformance Statement (PICS) pro forma Reference
RTS/ITS-00152

Keywords
ITS, PICS, testing

#### **ETSI**

650 Route des Lucioles F-06921 Sophia Antipolis Cedex - FRANCE

Tel.: +33 4 92 94 42 00 Fax: +33 4 93 65 47 16

Siret N° 348 623 562 00017 - NAF 742 C Association à but non lucratif enregistrée à la Sous-Préfecture de Grasse (06) N° 7803/88

#### Important notice

The present document can be downloaded from: http://www.etsi.org/standards-search

The present document may be made available in electronic versions and/or in print. The content of any electronic and/or print versions of the present document shall not be modified without the prior written authorization of ETSI. In case of any existing or perceived difference in contents between such versions and/or in print, the only prevailing document is the print of the Portable Document Format (PDF) version kept on a specific network drive within ETSI Secretariat.

Users of the present document should be aware that the document may be subject to revision or change of status.

Information on the current status of this and other ETSI documents is available at

<a href="http://portal.etsi.org/tb/status/status.asp">http://portal.etsi.org/tb/status/status.asp</a></a>

If you find errors in the present document, please send your comment to one of the following services: https://portal.etsi.org/People/CommiteeSupportStaff.aspx

#### **Copyright Notification**

No part may be reproduced or utilized in any form or by any means, electronic or mechanical, including photocopying and microfilm except as authorized by written permission of ETSI.

The content of the PDF version shall not be modified without the written authorization of ETSI.

The copyright and the foregoing restriction extend to reproduction in all media.

© European Telecommunications Standards Institute 2015.
All rights reserved.

**DECT**<sup>TM</sup>, **PLUGTESTS**<sup>TM</sup>, **UMTS**<sup>TM</sup> and the ETSI logo are Trade Marks of ETSI registered for the benefit of its Members. **3GPP**<sup>TM</sup> and **LTE**<sup>TM</sup> are Trade Marks of ETSI registered for the benefit of its Members and of the 3GPP Organizational Partners.

GSM® and the GSM logo are Trade Marks registered and owned by the GSM Association.

# Contents

Intell	lectual Property Rights	
Forev	word	4
Moda	al verbs terminology	4
1	Scope	5
2	References	
2.1	Normative references	
2.2	Informative references	
3	Definitions and abbreviations	5
3.1	Definitions	
3.2	Abbreviations	5
4	Conformance requirement concerning PICS	6
Anne	ex A (normative): CA PICS Pro forma	
A.1	Partial cancellation of copyright.	7
A.2	Guidance for completing the ICS pro forma	
A.2.1		
A.2.2		
A.2.3		
A.3	Identification of the implementation	Ç
A.3.1	*	
A.3.2		
A.3.3		
A.3.4		
A.3.5		
A.3.6		
A.3.7	1	
A.4	Identification of the protocol	11
A.5	Global statement of conformance	11
A.6	Tables	12
A.6.1		
A.6.2	<b>√1</b>	
A.6.3	1	
A.6.4	•	
A.6.5		
A.6.6 A.6.7		
A.6.7.	±	
A.6.8	e i	
Anne	ex B (informative): Bibliography	23
Histo	ory.	2/

# Intellectual Property Rights

IPRs essential or potentially essential to the present document may have been declared to ETSI. The information pertaining to these essential IPRs, if any, is publicly available for **ETSI members and non-members**, and can be found in ETSI SR 000 314: "Intellectual Property Rights (IPRs); Essential, or potentially Essential, IPRs notified to ETSI in respect of ETSI standards", which is available from the ETSI Secretariat. Latest updates are available on the ETSI Web server (http://ipr.etsi.org).

Pursuant to the ETSI IPR Policy, no investigation, including IPR searches, has been carried out by ETSI. No guarantee can be given as to the existence of other IPRs not referenced in ETSI SR 000 314 (or the updates on the ETSI Web server) which are, or may be, or may become, essential to the present document.

#### **Foreword**

This Technical Specification (TS) has been produced by ETSI Technical Committee Intelligent Transport Systems (ITS).

The present document is part 1 of a multi-part deliverable covering Conformance test specification for Co-operative Awareness Basic Service (CA) as identified below:

- Part 1: "Test requirements and Protocol Implementation Conformance Statement (PICS) pro forma";
- Part 2: "Test Suite Structure and Test Purposes (TSS & TP)";
- Part 3: "Abstract Test Suite (ATS) and Protocol Implementation eXtra Information for Testing (PIXIT)".

# Modal verbs terminology

In the present document "shall", "shall not", "should", "should not", "may", "need not", "will", "will not", "can" and "cannot" are to be interpreted as described in clause 3.2 of the <u>ETSI Drafting Rules</u> (Verbal forms for the expression of provisions).

"must" and "must not" are NOT allowed in ETSI deliverables except when used in direct citation.

# 1 Scope

The present document provides the Protocol Implementation Conformance Statement (PICS) pro forma for Conformance test specification for Co-operative Awareness Basic Service (CA) as defined in ETSI EN 302 637-2 [1] in compliance with the relevant requirements and in accordance with the relevant guidance given in ISO/IEC 9646-7 [3].

## 2 References

#### 2.1 Normative references

References are either specific (identified by date of publication and/or edition number or version number) or non-specific. For specific references, only the cited version applies. For non-specific references, the latest version of the reference document (including any amendments) applies.

Referenced documents which are not found to be publicly available in the expected location might be found at <a href="http://docbox.etsi.org/Reference">http://docbox.etsi.org/Reference</a>.

NOTE: While any hyperlinks included in this clause were valid at the time of publication, ETSI cannot guarantee their long term validity.

The following referenced documents are necessary for the application of the present document.

- [1] ETSI EN 302 637-2 (V1.3.2): "Intelligent Transport Systems (ITS); Vehicular Communications; Basic Set of Applications; Part 2: Specification of Cooperative Awareness Basic Service".
- [2] ISO/IEC 9646-1 (1994): "Information technology -- Open Systems Interconnection -- Conformance testing methodology and framework -- Part 1: General concepts".
- [3] ISO/IEC 9646-7 (1995): "Information technology -- Open Systems Interconnection -- Conformance testing methodology and framework -- Part 7: Implementation Conformance Statements".
- [4] Void.

#### 2.2 Informative references

References are either specific (identified by date of publication and/or edition number or version number) or non-specific. For specific references, only the cited version applies. For non-specific references, the latest version of the reference document (including any amendments) applies.

NOTE: While any hyperlinks included in this clause were valid at the time of publication, ETSI cannot guarantee their long term validity.

The following referenced documents are not necessary for the application of the present document but they assist the user with regard to a particular subject area.

Not applicable.

## 3 Definitions and abbreviations

#### 3.1 Definitions

For the purposes of the present document, the terms and definitions given in ETSI EN 302 637-2 [1], ISO/IEC 9646-1 [2] and ISO/IEC 9646-7 [3] apply.

#### 3.2 Abbreviations

For the purposes of the present document, the following abbreviations apply:

ATS Abstract Test Suite

BTP **Basic Transport Protocol** 

CAM Co-operative Awareness Messages

CAN Controller Area Network

DCC **Decentralized Congestion Control** 

**ICS** Implementation Conformance Statement

**Intelligent Transport Systems** ITS

ITS-S **ITS-Station** 

IUT Implementation Under Test LSB Least Significant Bit PDU Protocol Data Unit

**PICS** Protocol Implementation Conformance Statement

**SUT** System Under Test Test Purpose TP TSS Test Suite Structure

#### Conformance requirement concerning PICS 4

If it claims to conform to the present document, the actual PICS pro forma to be filled in by a supplier shall be technically equivalent to the text of the PICS pro forma given in annex A, and shall preserve the numbering, naming and ordering of the pro forma items.

An ICS which conforms to the present document shall be a conforming PICS pro forma completed in accordance with the instructions for completion given in clause A.1.

# Annex A (normative): CA PICS Pro forma

# A.1 Partial cancellation of copyright

Notwithstanding the provisions of the copyright clause related to the text of the present document, ETSI grants that users of the present document may freely reproduce the Partial PIXIT pro forma in this annex so that it can be used for its intended purposes and may further publish the completed Partial PIXIT.

# A.2 Guidance for completing the ICS pro forma

## A.2.1 Purposes and structure

The purpose of this PICS pro forma is to provide a mechanism whereby a supplier of an implementation of the requirements defined in ETSI EN 302 637-2 (V1.3.2) [1] may provide information about the implementation in a standardized manner.

The PICS pro forma is subdivided into clauses for the following categories of information:

- guidance for completing the ICS pro forma;
- identification of the implementation;
- identification of the ETSI EN 302 637-2 (V1.3.2) [1];
- global statement of conformance;
- PICS pro forma tables.

#### A.2.2 Abbreviations and conventions

The ICS pro forma contained in this annex is comprised of information in tabular form in accordance with the guidelines presented in ISO/IEC 9646-7 [3].

#### Item column

The item column contains a number which identifies the item in the table.

#### Item description column

The item description column describes in free text each respective item (e.g. parameters, timers, etc.). It implicitly means "is <item description> supported by the implementation?".

#### Status column

The following notations, defined in ISO/IEC 9646-7 [3], are used for the status column:

m mandatory - the capability is required to be supported.

o optional - the capability may be supported or not.

n/a not applicable - in the given context, it is impossible to use the capability.

x prohibited (excluded) - there is a requirement not to use this capability in the given context.

o.i qualified optional - for mutually exclusive or selectable options from a set. "i" is an integer which

identifies an unique group of related optional items and the logic of their selection which is

defined immediately following the table.

c.i conditional - the requirement on the capability ("m", "o", "x" or "n/a") depends on the support of

other optional or conditional items. "i" is an integer identifying an unique conditional status

expression which is defined immediately following the table.

i irrelevant (out-of-scope) - capability outside the scope of the reference specification. No answer is

requested from the supplier.

NOTE 1: This use of "i" status is not to be confused with the suffix "i" to the "o" and "c" statuses above.

#### Reference column

The reference column makes reference to ETSI EN 302 637-2 (V1.3.2) [1], except where explicitly stated otherwise.

#### Support column

The support column shall be filled in by the supplier of the implementation. The following common notations, defined in ISO/IEC 9646-7 [3], are used for the support column:

Y or y supported by the implementation.

N or n not supported by the implementation.

N/A, n/a or - no answer required (allowed only if the status is n/a, directly or after evaluation of a conditional

status).

NOTE 2: As stated in ISO/IEC 9646-7 [3], support for a received PDU requires the ability to parse all valid parameters of that PDU. Supporting a PDU while having no ability to parse a valid parameter is non-conformant. Support for a parameter on a PDU means that the semantics of that parameter are supported.

#### Values allowed column

The values allowed column contains the type, the list, the range, or the length of values allowed. The following notations are used:

range of values: <min value> .. <max value>

example: 5 .. 20

- list of values: <value1>, <value2>, ..., <valueN>

example: 2, 4, 6, 8, 9

example: '1101'B, '1011'B, '1111'B example: '0A'H, '34'H, '2F'H

- list of named values: <name1>(<val1>), <name2>(<val2>), ..., <nameN>(<valN>)

example: reject(1), accept(2)

- length: size (<min size> .. <max size>)

example: size (1 .. 8)

#### Values supported column

The values supported column shall be filled in by the supplier of the implementation. In this column, the values or the ranges of values supported by the implementation shall be indicated.

#### References to items

For each possible item answer (answer in the support column) within the ICS pro forma a unique reference exists, used, for example, in the conditional expressions. It is defined as the table identifier, followed by a slash character "/", followed by the item number in the table. If there is more than one support column in a table, the columns are discriminated by letters (a, b, etc.), respectively.

EXAMPLE 1: A.5/4 is the reference to the answer of item 4 in table 5 of annex A.

EXAMPLE 2: A.6/3b is the reference to the second answer (i.e. in the second support column) of item 3 in

table 6 of annex A.

#### Prerequisite line

A prerequisite line after a clause or table title indicates that the whole clause or the whole table is not required to be completed if the predicate is FALSE.

## A.2.3 Instructions for completing the ICS pro forma

The supplier of the implementation shall complete the ICS pro forma in each of the spaces provided. In particular, an explicit answer shall be entered, in each of the support or supported column boxes provided.

If necessary, the supplier may provide additional comments in space at the bottom of the tables or separately.

More detailed instructions are given at the beginning of the different clauses of the ICS pro forma.

# A.3 Identification of the implementation

Date of the statement

#### A.3.1 Introduction

A.3.2

Identification of the Implementation Under Test (IUT) and the system in which it resides (the System Under Test (SUT)) shall be filled in so as to provide as much detail as possible regarding version numbers and configuration options.

The product supplier information and client information shall both be filled in if they are different.

A person who can answer queries regarding information supplied in the ICS shall be named as the contact person.

A.3.3 IUT name:	Implementation Under Test (IUT) identification
IUT version:	

# System Under Test (SUT) identification A.3.4 SUT name: Hardware configuration: Operating system: A.3.5 Product supplier Name: Address: Telephone number: Facsimile number: E-mail address: Additional information: Client (if different from product supplier) A.3.6 Name: Address:

Celephone number:
acsimile number:
E-mail address:
Additional information:
A.3.7 ICS contact person
A person to contact if there are any queries concerning the content of the ICS)
Name:
elephone number:
acsimile number:
-mail address:
Additional information:
A.4 Identification of the protocol
This ICS pro forma applies to the following standard: ETSI EN 302 637-2 (V1.3.3) [1]: "Intelligent Transport Systems ITS); Vehicular Communications; Basic Set of Applications; Part 2: Specification of Cooperative Awareness Basic

Service".

#### **A.5** Global statement of conformance

Are all mandatory capabilities implemented? (Yes/No) .....

Answering "No" to this question indicates non-conformance to the CA standard specification. Non-supported mandatory capabilities are to be identified in the ICS, with an explanation of why the implementation is non-conforming, on pages attached to the ICS pro forma.

## A.6 Tables

## A.6.1 Introduction

Unless stated otherwise, the column references of all tables below indicates the clause numbers of ETSI EN 302 637-2 [1].

## A.6.2 ITS Station type

Table A.1: ITS Station type

Item	Туре	Reference	Status	Support
1	Personal ITS-S	6.1.2	n/a	
2	Road side ITS-S	6.1.2	0	
3	Vehicle ITS-S	6.1.2	m	
4	Other	6.1.2	n/a	

## A.6.3 CA vehicle profiles

Table A.2: CA vehicle profiles supported

Item	CA vehicle profile	Reference	Status	Support
1	PublicTransport	7.4	o.201	
2	SpecialTransport	7.4	o.201	
3	DangerousGoods	7.4	o.201	
4	RoadWork	7.4	o.201	
5	Rescue	7.4	o.201	
6	Emergency	7.4	0.201	
7	SafetyCar	7.4	o.201	
8	BasicVehicle	7.4	0.201	
o.201:	It is mandatory to support only one of these type.			

# A.6.4 CA Basic Functionality

Table A.3: CA Basic Functionality supported

Item	Vehicle Type	Reference	Status	Support
1	Transmission of CA Messages	4.3	m	
2	Reception of CA Messages	4.4	m	

# A.6.5 CA Interfaces to data provisioning services

Table A.4: CA Interfaces supported

Item	Vehicle Type	Reference	Status	Support
1	Interface to ITS applications	5.3.1	m	
2	Interface to data provisioning facilities	5.3.2	m	
3	Interface to the Networking & Transport Layer	5.3.3	m	
4	Interfaces protocol stacks of the Networking & Transport Layer	5.3.4	m	
5	Interface to the Management entity	5.3.5	m	
6	Interface to the Security entity	5.3.6	m	

Table A.5: CA Interfaces to Networking & Transport Layer

Prereq	Prerequisite: A.4/3						
Item	Vehicle Type	Reference	Status	Support			
1	Interface to the GeoNetworking/BTP stack	5.3.4.1	m				
2	Interface to the IPv6 stack and the combined IPv6/GeoNetworking stack	5.3.4.2	m				

# A.6.6 CA Message

#### Table A.6: CA message

Item	Name of field	Ref.	Туре	Status	Support
1	header	B.1	ItsPduHeader (Table A.23)	m	
2	cam	B.2,	CoopAwareness (Table A.7)	m	
		Annex A			

#### Table A.7: CoopAwareness

Prerequisite: A.6/2							
Item	Name of field	Ref.	Туре	Status	Support		
1	generationDeltaTime	B.3, Annex A	Integer { oneMilliSec(1) } (065535)	m			
2	camParameters	B.4, Annex A	CamParameters (Table A.8)	m			

#### **Table A.8: CamParameters**

Prerequ	Prerequisite: A.7/2							
Item	Name of field	Ref.	Туре	Status	Support			
1	basicContainer	B.5,	BasicContainer	m				
		Annex A	(Table A.9)					
2	highFrequencyContainer	B.6,	HighFrequencyContainer	m				
		Annex A	(Table A.10)					
3	IowFrequencyContainer	B.7,	LowFrequencyContainer	0				
		Annex A	(Table A.11)					
4	specialVehicleContainer	B.8,	SpecialVehicleContainer	0				
		Annex A	(Table A.12)					

#### Table A.9: BasicContainer

Prerequisite: A.8/1							
Item	Name of field	Ref.	Туре	Status	Support		
1	stationType	B.18	StationType (Table A.25)	m			
2	referencePosition	B.19	ReferencePosition (Table A.24))	m			

#### Table A.10: HighFrequencyContainer

Prerequisite: A.8/2								
Item	Name of field	Ref.	Туре	Status	Support			
1	basicVehicleHF	B.9, Annex A	BasicVehicleContainerHighFrequency (Table A.13)	c.1001				
2	emptyRSUHF	Annex A	NULL	c.1002				
c.1001:	IF vehicle THEN m ELSE	x.						
c.1002:	IF road side unit THEN m	n ELSE x.						

Table A.11: LowFrequencyContainer

Prerequisite: A.8/3							
Item	Name of field	Ref.	Туре	Status	Support		
1	basicVehicleLF	B.10,	BasicVehicleContainerLowFrequency	m			
		Annex A	(Table A.14)				

Table A.12: SpecialVehicleContainer

Prerequ	Prerequisite: A.8/4								
Item	Name of field	Ref.	Туре	Status	Support				
1	publicTransport	B.11,	PublicTransportContainer	m					
		Annex A	(Table A.15)						
2	specialTransport	B.12,	SpecialTransportContainer	m					
		Annex A	(Table A.16)						
3	dangerousGoods	B.13,	DangerousGoodsContainer	m					
		Annex A	(Table A.17)						
4	roadWorksBasic	B.14,	RoadWorksContainerBasic	m					
		Annex A	(Table A.18)						
5	rescue	B.15,	RescueContainer	m					
		Annex A	(Table A.19)						
6	emergency	B.16,	EmergencyContainer	m					
		Annex A	(Table A.20)						
7	safetyCar	B.17,	SafetyCarContainer	m					
	·	Annex A	(Table A.21)						

Table A.13: BasicVehicleContainerHighFrequency

Item	Name of field	Ref.	Туре	Status	Support
1	heading	B.21	Heading (Table A.26)	m	
2	speed	B.22	Speed (Table A.27)	m	
3	driveDirection	B.25	DriveDirection (Table A.28)	m	
4	vehicleLength	B.35	VehicleLength (Table A.41)	m	
5	vehicleWidth	B.36	VehicleWidth (Table A.42)	m	
6	IongitudinalAcceleration	B.26	LongitudinalAcceleration (Table A.32)	m	
7	curvature	B.31	Curvature (Table A.37)	m	
8	curvatureCalculationMode	B.32	CurvatureCalculationMode (Table A.38)	m	
9	yawRate	B.33	YawRate (Table A.39)	m	
10	accelerationControl	B.27	AccelerationControl (Table A.33)	0	
11	laneNumber	B.24	LaneNumber (Table A.31)	0	
12	steeringWheelAngle	B.34	SteeringWheelAngle (Table A.40)	0	
13	lateralAcceleration	B.28	LateralAcceleration (Table A.34)	0	
14	verticalAcceleration	B.29	VerticalAcceleration (Table A.35)	0	
15	performanceClass	B.20	PerformanceClass (Table A.29)	0	

Table A.14: BasicVehicleContainerLowFrequency

ltem	Name of field	Ref.	Туре	Status	Support
1	vehicleRole	B.23	VehicleRole	m	
			(Table A.30)		
2	exteriorLights	B.37	ExteriorLights	m	
			(Table A.43)		
3	pathHistory	B.38	PathHistory	m	
			(Table A.44)		

#### Table A.15: PublicTransportContainer

Prerequ	Prerequisite: A.12/1							
Item	Name of field	Ref.	Туре	Status	Support			
1	embarkationStatus	B.30	EmbarkationStatus (Table A.36)	m				
2	ptActivation	B.39	PtActivation (Table A.45)	0				

#### Table A.16: SpecialTransportContainer

Prerequ	Prerequisite: A.12/2							
Item	Name of field	Ref.	Туре	Status	Support			
1	specialTransportType	B.40	SpecialTransportType (Table A.47)	m				
2	lightBarSirenInUse	B.46	LightBarSirenInUse (Table A.46)	0				

#### **Table A.17: DangerousGoodsContainer**

Prerequisite: A.12/3							
Item	Name of field	Ref.	Туре	Status	Support		
1	dangerousGoodsBasic	B.41	3	m			
			(Table A.48)				

#### Table A.18: RoadWorksContainerBasic

Prereq	Prerequisite: A.12/4								
Item	Name of field	Ref.	Туре	Status	Support				
1	roadworksSubCauseCode	B.42	RoadworksSubCauseCode (Table A.49)	0					
2	lightBarSirenInUse	B.46	LightBarSirenInUse (Table A.46)	m					
3	closedLanes	B.43	ClosedLanes (Table A.50)	0					

#### Table A.19: RescueContainer

Prerequ	Prerequisite: A.12/5							
Item	Name of field	Ref.	Туре	Status	Support			
1	lightBarSirenInUse	B.46	LightBarSirenInUse (Table A.46)	m				
9	emergencyPriority	B.48	EmergencyPriority (Table A.51)	0				

**Table A.20: EmergencyContainer** 

Prerequisite: A.12/6								
Item	Name of field	Ref.	Туре	Status	Support			
1	lightBarSirenInUse	B.46	LightBarSirenInUse (Table A.46)	m				
2	incidentIndication	B.47	CauseCode (Table A.52)	0				
3	emergencyPriority	B.48	EmergencyPriority (Table A.51)	О				

Table A.21: SafetyCarContainer

Prereq	Prerequisite: A.12/7								
Item	Name of field	Ref.	Туре	Status	Support				
1	lightBarSirenInUse	B.46	LightBarSirenInUse (Table A.46)	m					
2	incidentIndication	B.47	CauseCode (Table A.52)	О					
3	trafficRule	B.44	TrafficRule (Table A.53)	О					
3	speedLimit	B.45	SpeedLimit (Table A.54)	0					

# A.6.7 Protocol parameters

# A.6.7.1 Timing requirements

**Table A.22: Timing requirements** 

Item	Name of field	Reference	Default value	Status	Support
1	Maximum CAM generation frequency (T_GenCamMax)	6.1.3	1 000 ms	m	
2	Minimum CAM generation frequency (T_GenCamMin)	6.1.3	100 ms	m	
3	T_CheckCamGen	6.1.3	≤ T_GenCamMin	m	
4	T_ GenCam_Dcc	6.1.3	T_GenCamMin ≤ T_GenCam_DCC ≤ T_GenCamMax.	m	
5	T_GenCam	6.1.3	T_GenCamMax	m	
6	N_GenCam	6.1.3	maximum value 3	m	
7	Maximum time without including low frequency container	6.1.3	500 ms	m	
8	Maximum time without including special vehicle container	6.1.3	500 ms	m	
9	CAM generation time	6.1.5.1	< 50 ms	m	
10	Difference between CAM generation time and time stamp	6.1.5.2	< 32 767 ms	m	

## A.6.8 Common elements

Table A.23: ITS PDU header

Item	Туре	Reference	Value
1	protocolVersion	7.1.1, B.1	currentVersion(1)
2	messageID	7.1.1, B.1	cam(2)
3	stationID	7.1.1, B.1	Integer (0 4 294 967 295)

**Table A.24: ReferencePosition** 

Item	Туре	Reference		Value
1	latitude	B.19	Integer { oneMicrodegreoneMicrodegreeSouth (-(-900 000 000 900 000 microdegree	10), unavailable(900 000 001) }
2	longitude	B.19	(-10), unavailable(1 800	eEast (10), oneMicrodegreeWest 000 001) } 000 001) multiples of 0,1
3	positionConfidenceEllipse	B.19	semiMajorConfidence	Integer { oneCentimeter(1), outOfRange(4 094), unavailable(4 095) } (0 4 095)
			semiMinorConfidence	Integer { oneCentimeter(1), outOfRange(4 094), unavailable(4 095) } (0 4 095)
			semiMajorOrientation	Heading
4	altitude	B.19	altitudeValue	Integer { seaLevel(0), oneCentimeter(1), unavailable(800 001) } (-100 000 800 001)
			altitudeConfidence	Enum { alt-000-01 (0), alt-000-02 (1), alt-000-05 (2), alt-000-10 (3), alt-000-20 (4), alt-000-50 (5), alt-001-00 (6), alt-002-00 (7), alt-005-00 (8), alt-010-00 (9), alt-020-00 (10), alt-050-00 (11), alt-100-00 (12), alt-200-00 (13), outOfRange (14), unavailable (15)} (1 127)

## Table A.25: StationType

Item	Type	Reference	Value
1	stationType		Integer { unknown(0), pedestrian(1), cyclist(2), moped(3), motorcycle(4), passengerCar(5), bus(6), lightTruck(7), heavyTruck(8), trailer(9), specialVehicles(10), tram(11), roadSideUnit(15) } (0 255)

## Table A.26: Heading

Item	Туре	Reference	Value
1	headingValue		Integer { wgs84North(0), wgs84East(900), wgs84South(1 800), wgs84West(2 700), unavailable(3 600) } (0 3 600)
2	headingConfidence		Integer { withinZeroPointOneDegree(1), withinOneDegree(10), outOfRange(126), unavailable(127) } (1 127)

#### Table A.27: Speed

Item	Туре	Reference	Value
1	speedValue	B.22	Integer { standstill(0), oneCentimeterPerSec(1), unavailable(16 383) } (0 16 383)
2	SpeedConfidence	B.22	Integer { withinOneCentimeterPerSec(1), withinOneMeterPerSec(100), outOfRange(126), unavailable(127) } (1 127)

#### **Table A.28: DriveDirection**

Item	Туре	Reference	Value
1	driveDirection	B.25	Enum { forward (0), backward (1), unavailable (2) }

#### **Table A.29: PerformanceClass**

Item	Туре	Reference	Value
1	performanceClass	B.20	Integer { unavailable(0), performanceClassA(1),
			performanceClassB(2) } (0 7)

#### Table A.30: VehicleRole

Item	Туре	Reference	Value
1	vehicleRole	B.23	Enum { default(0), publicTransport(1), specialTransport(2), dangerousGoods(3), roadWork(4), rescue(5), emergency(6), safetyCar(7) }

#### Table A.31: LaneNumber

Item	Туре	Reference	Value
1	laneNumber	B.24	Integer { offTheRoad(-1), hardShoulder(0),
			outermostDrivingLane(1), secondLaneFromOutside(2) }
			(-1 14)

#### **Table A.32: LongitudinalAcceleration**

Item	Туре	Reference	Value
1	IongitudinalAccelerationValue	B.26	Integer { pointOneMeterPerSecSquaredForward(1),
			pointOneMeterPerSecSquaredBackward(-1), unavailable(161)} (-160 161)
2	IongitudinalAccelerationConfidence	B.26	Integer{ pointOneMeterPerSecSquared(1),
			outOfRange(101), unavailable(102)} (0 102)

#### **Table A.33: AccelerationControl**

Item	Туре	Reference	Value
1	accelerationControl		Bitstring { brakePedalActive (0), gasPedalActive (1), emergencyBrakeActive (2), collisionWarningActive (3), accActive (4), cruiseControl (5), speedLimiterActive (6)} (SIZE(7))

#### Table A.34: Lateral Acceleration

Item	Туре	Reference	Value
1	lateralAccelerationValue	B.28	Integer { pointOneMeterPerSecSquaredToRight(-1),
			pointOneMeterPerSecSquaredToLeft(1),
			unavailable(161) } (-160 161)
2	lateralAccelerationConfidence	B.28	Integer { pointOneMeterPerSecSquared(1),
			outOfRange(101), unavailable(102)} (0 102)

#### **Table A.35: Vertical Acceleration**

Item	Туре	Reference	Value
1	verticalAccelerationValue		Integer { pointOneMeterPerSecSquaredUp(1), pointOneMeterPerSecSquaredDown(-1), unavailable(161) } (-160 161)
2	verticalAccelerationConfidence		Integer { pointOneMeterPerSecSquared(1), outOfRange(101), unavailable(102)} (0 102)

#### **Table A.36: EmbarkationStatus**

Item	Туре	Reference	Value
1	embarkationStatus	B.30	Boolean

#### **Table A.37: Curvature**

Item	Туре	Reference	Value
1	curvatureValue	B.31	Integer { straight(0), reciprocalOf1MeterRadiusToRight(-30 000), reciprocalOf1MeterRadiusToLeft(30 000), unavailable(30001) } (-30 000 30 001) }
2	curvatureConfidence	B.31	Enum { onePerMeter-0-00002 (0), within 0,00002 m^-1 onePerMeter-0-0001 (1), within 0,0001 m^-1 onePerMeter-0-0005 (2), within 0,0005 m^-1 onePerMeter-0-002 (3), within 0,002 m^-1 onePerMeter-0-01 (4), within 0,01 m^-1 onePerMeter-0-1 (5), within 0,1 m^-1 outOfRange (6), unavailable (7) }

#### Table A.38: CurvatureCalculationMode

Item	Туре	Reference	Value
1	curvatureCalculationMode	B.32	Enum { yawRateUsed(0), yawRateNotUsed(1),
			transitionMode(2)}

#### Table A.39: YawRate

Item	Туре	Reference	Value
1	yawRateValue	B.33	Integer { straight(0), degSec-000-01ToRight(-1), degSec-000-01ToLeft(1), unavailable(32 767) } (-32 767 32 767) LSB units of 0,01 degrees per second
2	yawRateConfidence	B.33	Enum { degSec-000-01 (0), degSec-000-05 (1), degSec-000-10 (2), degSec-001-00 (3), degSec-005-00 (4), degSec-010-00 (5), degSec-100-00 (6), outOfRange (7), unavailable (8) }

## Table A.40: SteeringWheelAngle

Item	Туре	Reference	Value
1	steeringWheelAngleValue	B.34	Integer { straight(0),
			onePointFiveDegreesToRight(-1),
			onePointFiveDegreesToLeft(1), unavailable(511) }
			(-511 511)
2	steeringWheelConfidence	B.34	Integer { withinOnePointFiveDegrees(1),
			outOfRange(126), unavailable(127) } (1 127)

#### Table A.41: VehicleLength

Item	Туре	Reference	Value
1	vehicleLengthValue		Integer { tenCentimeters(1), outOfRange(1 022), unavailable(1 023) } (1 1 023)
2	vehicleLengthConfidenceIndication		Enum { noTrailerPresent(0), trailerPresentWithKnownLength(1), trailerPresentWithUnknownLength(2), trailerPresenceIsUnknown(3) }

#### Table A.42: VehicleWidth

Item	Туре	Reference	Value
1	vehicleWidth	B.36	Integer { tenCentimeters(1), outOfRange(61),
			unavailable(62) } (1 62)

#### **Table A.43: ExteriorLights**

Item	Туре	Reference	Valu	е
1	exteriorLights	B.37	Bitstring {	
			lowBeamHeadlightsOn	(0),
			highBeamHeadlightsOn	(1),
			leftTurnSignalOn	(2),
			rightTurnSignalOn	(3),
			daytimeRunningLightsOn	(4),
			reverseLightOn	(5),
			fogLightOn	(6),
			parkingLightsOn	(7)
			) (SIZE(8))	

#### Table A.44: PathHistory

Item	Туре	Reference	Value
1	pathHistory	B.38	Sequence (SIZE(0 23)) OF PathPoint

#### **Table A.45: PtActivation**

Item	Туре	Reference	Value
1	ptActivationType		Integer { undefinedCodingType(0), r09- 16CodingType(1), vdv-50149CodingType(2) } (0 255)
2	ptActivationData	B.39	OctetString (SIZE(1 20))

#### Table A.46: LightBarSirenInUse

Item	Туре	Reference	Value
1	lightBarSirenInUse	B.46	Bitstring { lightBarActivated (0), sirenActivated (1)} (SIZE(2))

## Table A.47: SpecialTransportType

Item	Туре	Reference	Value
1	specialTransportType	B.40	Bitstring { heavyLoad(0), excessWidth(1), excessLength(2),
			excessHeight(3) } (SIZE(4))

#### Table A.48: DangerousGoodsBasic

Item	Туре	Reference	Value
1	dangerousGoodsBasic	B.41	Bitstring { explosives1(0), explosives2(1), explosives3(2),
			explosives4(3), explosives5(4), explosives6(5),
			flammableGases(6), nonFlammableGases(7), toxicGases(8),
			flammableLiquids(9), flammableSolids(10),
			substancesLiableToSpontaneousCombustion(11),
			substancesEmittingFlammableGasesUponContactWithWater(12),
			oxidizingSubstances(13), organicPeroxides(14),
			toxicSubstances(15), infectiousSubstances(16),
			radioactiveMaterial(17), corrosiveSubstances(18),
			miscellaneousDangerousSubstances(19)}

#### Table A.49: RoadworksSubCauseCode

Item	Туре	Reference	Value
1	roadworksSubCauseCode		Integer {unavailable(0), majorRoadworks(1), roadMarkingWork(2), slowMovingRoadMaintenance(3), winterService(4), streetCleaning(5) } (0 255)

#### Table A.50: ClosedLanes

Item	Туре	Reference	Value
1	hardShoulderStatus		Enum { availableForStopping(0), closed(1), availableForDriving(2) } OPTIONAL
2	drivingLaneStatus	B.43	Bitstring { outermostLaneClosed(1), secondLaneFromOutsideClosed(2) } (SIZE (1 14))

#### **Table A.51: EmergencyPriority**

Item	Туре	Reference	Value
1	emergencyPriority		BitString { requestForRightOfWay(0), requestForFreeCrossingAtATrafficLight(1) } (SIZE (2))

#### Table A.52: CauseCode

Item	Туре	Reference	Value
1	causeCode		Integer { reserved (0), trafficCondition (1), accident (2), roadworks (3), adverseWeatherCondition-Adhesion (6),hazardousLocation-SurfaceCondition (9), hazardousLocation-ObstacleOnTheRoad (10), hazardousLocation-AnimalOnTheRoad (11), humanPresenceOnTheRoad (12), wrongWayDriving (14), rescueAndRecoveryWorkInProgress (15), adverseWeatherCondition-ExtremeWeatherCondition (17), adverseWeatherCondition-Visibility (18), adverseWeatherCondition-Precipitation (19), slowVehicle (26), dangerousEndOfQueue (27), vehicleBreakdown (91), postCrash (92), humanProblem (93), stationaryVehicle (94), emergencyVehicleApproaching (95), hazardousLocation-DangerousCurve (96), collisionRisk (97), signalViolation (98), dangerousSituation (99) } (0255)
2	subCauseCode	B.47	Integer (0 255)

#### Table A.53: TrafficRule

Item	Туре	Reference	Value
1	trafficRule	B.44	Enum { noPassing(0), noPassingForTrucks(1),

## Table A.54: SpeedLimit

Item	Туре	Reference	Value
1	speedLimit	B.45	Integer { oneKmPerHour(1) } (0 255)

# Annex B (informative): Bibliography

- ETSI TS 102 637-3 (V1.1.1): "Intelligent Transport Systems (ITS); Vehicular Communications; Basic Set of Applications; Part 3: Specifications of Decentralized Environmental Notification Basic Service".
- ETSI TS 102 637-4: "Intelligent Transport Systems (ITS); Vehicular Communications; Basic set of applications; Part 4: Operational Requirements".
- ETSI ETS 300 406 (1995): "Methods for testing and Specification (MTS); Protocol and profile conformance testing specifications; Standardization methodology".

# History

Document history				
V1.1.1	March 2011	Publication		
V1.2.1	April 2014	Publication		
V1.3.1	July 2015	Publication		