


DOCUMENT 02

User Guide

Screen-by-screen guide to every feature in NGW.

Application Overview

NGW is organized around three primary workflows: Analyze, Shoot Mode, and My Kit. Access each from the Home screen. Settings and the NGW Lab are available via the navigation bar at all times.



Home Screen — Analyze, Shoot Mode, and My Kit entry points

Home Screen

Entry Points


- Analyze — Upload a reference photo and receive an immediate lighting recommendation.
- Shoot Mode — Convert a recommendation into a step-by-step on-set workflow.
- My Kit — Manage the equipment list that constrains every recommendation.

Navigation Bar


- Home — Return to the main entry screen.
- Recipes — Browse 13 master lighting recipes as learning references.
- Settings — Configure units, notifications, and account preferences.
- NGW Lab — Developer tools (restricted — see Lab Guide).

Settings


Settings controls system-wide preferences and account details. Changes take effect immediately — no restart required.



Settings Screen — units, notifications, account, and lab access



Settings — Lab access toggle (restricted to allowlisted emails)



Settings — Developer tools panel with debug options

Configurable Options

- Distance Units — Switch between feet and meters for all positional guidance.
- Ceiling Height Default — Set your studio's ceiling height; Shoot Mode warns when lights exceed it.
- Room Dimensions — Pre-set your shooting space for proximity and wall-bounce guidance.
- Notification Preferences — Control when NGW sends analysis-complete and outcome reminders.
- Developer Tools — Enable the NGW Lab (restricted to approved team members).

How To: Change Your Distance Units

NGW supports both feet and metric units. All positional guidance in Shoot Mode and recommendations updates instantly when you change the setting.

Open Settings

- 1 Tap the gear icon in the navigation bar from any screen.

Find Distance Units

- 2 Scroll to the "Units & Measurements" section.

Select your unit

- 3 Toggle between Feet and Meters. The label updates live.

Return to Analyze

- 4 All distances in the current recommendation re-render immediately.

How To: Set Up Your Studio Space

Entering your room dimensions lets Shoot Mode flag when a light position is too close to a wall, or when a boom arm would exceed your ceiling height.

Open Settings

- 1 Tap the gear icon in the navigation bar.

Enter Ceiling Height

- 2 Type your ceiling height in feet or meters. Include any drop from beams.

Enter Room Dimensions

- 3 Width and depth in your preferred units. Approximate is fine.

Save

- 4 Tap outside the field or hit Done on the keyboard. Settings persist across sessions.

WHY THIS MATTERS

- Without room dimensions, Shoot Mode cannot warn you about wall-proximity bounce, ceiling clearance, or spill risk from nearby reflective surfaces. Takes 30 seconds and significantly improves instruction accuracy.

Running Your First Analysis

Open the Analyze screen

- 1 Tap "Analyze" from the Home screen.

Upload a reference image

- 2 Choose a photo with clear subject lighting. Portraits work best; avoid heavy post-processing.

Set your scene context

- 3 Specify subject type (portrait / product), environment (studio / outdoor), and any constraints.

Review the recommendation

- 4 NGW returns the detected pattern, confidence score, modifier list, and gear setup.

Launch Shoot Mode

- 5 Tap "Start Shoot Mode" to convert the recommendation into on-set steps.

PRO TIP


- For best results, use a reference photo with a single subject against a neutral background. Heavy color grading or composite backgrounds reduce detection confidence.

Reading a Recommendation

Field	What It Means	Example
Pattern	Named lighting configuration detected	Loop — Key 45° off-axis, slight elevation
Confidence	Engine certainty (0–100)	87%
Key Light	Primary source: type, position, modifier	Godox AD600 · 45°R · 6 ft · Octa 90cm
Fill Light	Secondary source or reflector	V-flat reflector · camera-left
Modifiers	Shaping tools detected	Diffusion sock · grid
Power	Estimated flash stop relative to key	Key: f/8 · Fill: –2 stops
Gear Tier	Flexibility applied to your kit	Tier 2 — Close substitute

How To: Use a Master Mode

Master Mode lets you bias recommendations toward the aesthetic of a specific photographer — adjusting contrast ratios, modifier softness, and tonal guidance to match a signature look.



Wizard — Master Mode selection screen

Start an analysis

1

Upload a reference image from the Analyze screen.

Open Master Mode

2

After the initial result appears, tap the "Master Mode" option.

Select a photographer

3

Choose from Avedon, Penn, Lindbergh, LaChapelle, and others.

Review adjusted output

4

The recommendation re-renders with the selected master's aesthetic biases applied.

Toggle off

5


Tap "None" to return to the unbiased recommendation at any time.

WHAT CHANGES


- Contrast ratio target shifts to match the master's signature fill ratio.
- Modifier softness guidance adjusts — Penn favors harder sources; Avedon softer.
- Copy in the recommendation reflects the visual philosophy of the selected master.

How To: Set Subject and Mood

NGW adjusts recommendations based on subject type and mood context. Setting these before analysis improves pattern confidence and modifier selection.



Wizard — Subject type selection



Wizard — Mood and tone selection

Subject Types


- Portrait — Individual subject, face-priority analysis.
- Editorial — Fashion or lifestyle; full-body and environment considered.
- Product — Still life; specular and reflection signature prioritized.
- Group — Multiple subjects; pattern limited to wrap-friendly setups.

Mood Presets

- Natural — Prioritizes believable, soft, directional light.
- Dramatic — High contrast, low fill ratio, deep shadows.
- Commercial — Clean, on-axis, even, highly controlled.
- Editorial — Edgy, cross-light, mixed source temperature acceptable.

How To: Enable NGW Lab Access

The NGW Lab is restricted to approved team members. Access requires both a Studio plan and an email on the allowlist configured in the backend environment.



Home screen with NGW Lab tab visible

Confirm eligibility

1

Your email must be in LAB_ALLOWED_EMAILS on the backend. Contact your team admin.

Open Settings**2**

Tap the gear icon in the navigation bar.

Enable Developer Tools**3**

Scroll to the bottom. Toggle "Developer Tools" on.

Enter your lab email**4**

Type the email registered in the allowlist.

Lab tab appears**5**

The NGW Lab tab appears in the navigation bar immediately.

TROUBLESHOOTING LAB ACCESS

- If the Lab tab does not appear after enabling Developer Tools, your email is not in the allowlist. Ask your backend admin to add it to LAB_ALLOWED_EMAILS in the server environment variables and restart the backend.