Standard components

Spacer

Learn about the Spacer component for use in UI extensions.

Use the `Spacer` component to add vertical space between components. This component is intended for one-off use in situations where other layout components like **Flex** don't fully provide the spacing you need. You can use this component in tandem with the **AutoGrid**, **Flex**, **Box**, and **Inline** components to **manage extension layout**.

For consistent spacing between multiple components, use the **Flex** component with the `direction="column"` and the `gap` props instead. Flex automatically applies uniform spacing between children, which makes layout easier to maintain.

These buttons have medium spacing between them:

Button

Button

HubSpot Developers

```
const Extension = () => {
  return (
    <>
      <Text>These buttons have medium spacing between them:</Text>
      <Button>Button</Button>
      <Spacer size="medium" />
      <Button>Button</Button>
    </>
  );
};
```

Props

Prop	Type	Description
`size`	`"extra-large"` | `"extra-small"` | `"large"` | `"medium"` | `"small"` **Default:** `"small"`	The amount of vertical space to render.
`testId`	`string`	Used by `findByTestId()` to locate this component in tests. **See:** Testing utilities reference

Distances

The `size` prop controls how much vertical space is rendered. Each size maps to a consistent spacing value from the HubSpot design system:

- `extra-small` : minimal spacing for tightly grouped elements.
- `small` : default spacing suitable for most use cases.
- `medium` : moderate spacing for separating related content sections.
- `large` : generous spacing for creating clear visual breaks.
- `extra-large` : maximum spacing for major section divisions.

HubSpot Developers

›

to manually insert `Spacer` components.

```
import { Flex, Text } from '@hubspot/ui-extensions';

const Extension = () => {
  return (
    <Flex direction="column" gap="medium">
      <Text>First section</Text>
      <Text>Second section</Text>
      <Text>Third section</Text>
    </Flex>
  );
};
```

Use `Spacer` for situations where you need non-uniform spacing or a one-off adjustment:

```
import { Flex, Text, Spacer } from '@hubspot/ui-extensions';

const Extension = () => {
  return (
    <Flex direction="column" gap="small">
      <Text>First section</Text>
      <Text>Second section</Text>
      <Spacer size="extra-large" />
      <Text>Final section with extra space above</Text>
    </Flex>
  );
};
```

Guidelines

DO: use `Spacer` for one-off vertical spacing adjustments where you need different spacing at a specific point.

DO: use the smallest `Spacer` size that creates adequate visual separation.

DON'T: use `Spacer` when a `Divider` would better communicate the separation between sections.

Related components

- AutoGrid
- Flex
- Box
- Divider
- Inline

Last modified on February 17, 2026

Was this page helpful? Yes No

Select
‹ Previous

Statistics
Next ›

HubSpot Developers

Copyright © 2026 HubSpot, Inc

Privacy Policy

Security

Website Accessibility

Manage Cookies