






# How to Configure DHCP Failover


First confirm all verifications of ADDS DNS from Host Server  
i.e. Server 1







Then go to the host server i.e. server 2



Server Manager

Server Manager ▸ Local Server

Dashboard  
Local Server  
All Servers  
File and Storage Services ▸

**PROPERTIES**  
For server2

|               |          |                          |                                             |
|---------------|----------|--------------------------|---------------------------------------------|
| Computer name | server2  | Last installed updates   | Never                                       |
| Domain        | hpit.com | Windows Update           | Download updates only, using Windows Update |
|               |          | Last checked for updates | Never                                       |

|                           |                             |                                    |                                                 |
|---------------------------|-----------------------------|------------------------------------|-------------------------------------------------|
| Windows Defender Firewall | Domain: On                  | Windows Defender Antivirus         | Real-Time Protection: On                        |
| Remote management         | Enabled                     | Feedback & Diagnostics             | Settings                                        |
| Remote Desktop            | Disabled                    | IE Enhanced Security Configuration | On                                              |
| NIC Teaming               | Disabled                    | Time zone                          | (UTC+05:30) Chennai, Kolkata, Mumbai, New Delhi |
| Ethernet                  | 192.168.1.101, IPv6 enabled | Product ID                         | 00431-20000-00000-AA480 (activated)             |

|                          |                                                     |                        |                                          |
|--------------------------|-----------------------------------------------------|------------------------|------------------------------------------|
| Operating system version | Microsoft Windows Server 2019 Datacenter Evaluation | Processors             | Intel(R) Core(TM) i3-5005U CPU @ 2.00GHz |
| Hardware information     | innotek GmbH VirtualBox                             | Installed memory (RAM) | 2 GB                                     |
|                          |                                                     | Total disk space       | 32.67 GB                                 |

**EVENTS**  
All events | 28 total

| Server Name | ID   | Severity | Source                              | Log    | Date and Time       |
|-------------|------|----------|-------------------------------------|--------|---------------------|
| SERVER2     | 1014 | Warning  | Microsoft-Windows-DNS Client Events | System | 8/4/2021 4:21:39 PM |
| SERVER2     | 129  | Warning  | Microsoft-Windows-Time-Service      | System | 8/4/2021 1:40:14 PM |
| SERVER2     | 1014 | Warning  | Microsoft-Windows-DNS Client Events | System | 8/4/2021 1:38:36 PM |

Server Manager

Add Roles and Features Wizard

Select server roles

Before You Begin  
Installation Type  
Server Selection  
Server Roles  
Features  
DHCP Server  
Confirmation  
Results

Select one or more roles to install on the selected server.

**Roles**

- ☐ Active Directory Certificate Services
- ☐ Active Directory Domain Services
- ☐ Active Directory Federation Services
- ☐ Active Directory Lightweight Directory Services
- ☐ Active Directory Rights Management Services
- ☐ Device Health Attestation
- ☒ **DHCP Server**
- ☐ DNS Server
- ☐ Fax Server
- ☐ File and Storage Services (2 of 12 installed)
- ☐ Host Guardian Service
- ☐ Hyper-V
- ☐ Network Controller
- ☐ Network Policy and Access Services
- ☐ Print and Document Services
- ☐ Remote Access
- ☐ Remote Desktop Services
- ☐ Volume Activation Services
- ☐ Web Server (IIS)
- ☐ Windows Deployment Services



**Description**  
Dynamic Host Configuration Protocol (DHCP) Server enables you to centrally configure, manage, and provide temporary IP addresses and related information for client computers.



DESTINATION SERVER  
server2.hpit.com


< Previous Next > Install Cancel

| Server Name | ID   | Severity | Source                              | Log    | Date and Time       |
|-------------|------|----------|-------------------------------------|--------|---------------------|
| SERVER2     | 1014 | Warning  | Microsoft-Windows-DNS Client Events | System | 8/4/2021 4:21:39 PM |
| SERVER2     | 129  | Warning  | Microsoft-Windows-Time-Service      | System | 8/4/2021 1:40:14 PM |
| SERVER2     | 1014 | Warning  | Microsoft-Windows-DNS Client Events | System | 8/4/2021 1:38:36 PM |


## Then go to the complete DHCP Configuration Link











Then again go back to the server1 and configure the DHCP failover  
Then click on the TOOLS and then click on the DHCP






Configure a failover relationship on any scope of the server







**Then click on advance Button and then Find Now Button**




And after proper selection you can see the SERVER2 in the list





Then click on OK and then Click on Next




Then click on finish



Then verify the failover



**Then go to the server2 and refresh once you see that the scope is automatically added and also check again failover configuration details on server2**



then go to the client machine and run CMD

type `ipconfig /release` and then again type `ipconfig /renew` and then again type `ipconfig /all`