

Interface: IF_JVA_EQUITY_ADJUST

Status: Active

Properties

Description: Interface for Equity Adjustment

Package: GJVA

Original lang.: EN

Created by: SAP

Created On: 27.12.2018

Last changed on: 21.05.2026

Forward declaration type grps.

ABAP

SLIS

Methods

CHECK_SCREEN_PARAMETERS

Description: Check the screen parameters for validity and completeness

Instance mthd

Changing parameter

CV_FRDATE TYPE SYST_DATUM OPTIONAL (ABAP system field: Current date of application server)

CV_TODATE TYPE SYST_DATUM OPTIONAL (ABAP system field: Current date of application server)

CV_FRPER TYPE MONAT OPTIONAL (Fiscal Period)

CV_FRYEAR TYPE GJAHR OPTIONAL (Fiscal Year)

CV_TOPER TYPE MONAT OPTIONAL (Fiscal Period)

CV_TOYEAR TYPE GJAHR OPTIONAL (Fiscal Year)

CV_ITD TYPE ABAP_BOOL OPTIONAL (Inception to Date)

HANDLE_CB_EVENT_AFTER_LINE_OUT

Description: Handler for the ALV AFTER-LIST-OUTPUT event in cutback

Instance mthd

Importing parameter

IS_LINEINFO TYPE SLIS_LINEINFO

HANDLE_CB_EVENT_TOP_OF_LIST

Description: Handler for the ALV TOP-OF-LIST event in cutback

Instance mthd

HANDLE_CB_EVENT_TOP_OF_PAGE

Description: Handler for the ALV TOP-OF-PAGE event in cutback

Instance mthd

HANDLE_EA_EVENT_AFTER_LINE_OUT

Description: Handler for the ALV AFTER-LIST-OUTPUT event in equity adjust

Instance mthd

Importing parameter

IS_LINEINFO TYPE SLIS_LINEINFO

HANDLE_EA_EVENT_BEFOR_LINE_OUT

Description: Handler for the ALV AFTER-LIST-OUTPUT event in equity adjust
Instance mthd

Importing parameter

IS_LINEINFO TYPE SLIS_LINEINFO

HANDLE_EA_EVENT_TOP_OF_LIST

Description: Handler for the ALV TOP-OF-LIST event in equity adjustment
Instance mthd

HANDLE_EA_EVENT_TOP_OF_PAGE

Description: Handler for the ALV TOP-OF-PAGE event in equity adjustment
Instance mthd

RUN_PROCESS

Description: Run the equity adjustment process
Instance mthd

SET_RUN_PARAMETERS

Description: Set the program parameters
Instance mthd

Importing parameter

IT_ACCT TYPE JV_ACCOUNT_RANGE_TABLE
IT_BUDAT TYPE FINS_T_BUDAT_RANGE
IT_CNTR TYPE JV_COST_CENTER_RANGE_TABLE
IT_NPLNR TYPE JV_NETWORK_RANGE_TABLE
IT_ORDNR TYPE JV_ORDER_RANGE_TABLE
IT_PROJK TYPE JV_PROJECT_RANGE_TABLE
IT_VORNR TYPE VORNR_RANG_T
IV_BKTXT TYPE BKTXT
IV_BUDAT TYPE SYST_DATUM
IV_BUKRS TYPE BUKRS
IV_CASHC1 TYPE ABAP_BOOL DEFAULT SPACE
IV_CASHC2 TYPE ABAP_BOOL DEFAULT SPACE
IV_STLAC2 TYPE RACCT OPTIONAL (Settlement Account)
IV_CUTBCK TYPE ABAP_BOOL DEFAULT 'X'
IV_EQCHNG TYPE ABAP_BOOL DEFAULT 'X'
IV_BLOCK_OLD_EG TYPE JV_EC_EQ_BLK OPTIONAL (Flag: Old EQ is blocked)
IV_EQNEW TYPE JV_EGROUP
IV_EQOLD TYPE JV_EGROUP
IV_EXCLOI TYPE CHAR1
IV_FRDATE TYPE SYST_DATUM OPTIONAL
IV_INTCOC TYPE ABAP_BOOL DEFAULT SPACE
IV_ICOREV TYPE ABAP_BOOL DEFAULT SPACE
IV_IVPEQG TYPE ABAP_BOOL

IV_IVPPTN TYPE ABAP_BOOL
IV_IVPEXP TYPE ABAP_BOOL
IV_PERIOD TYPE MONAT
IV_REPID_CALLBACK TYPE SY-REPID
IV_ANALYSIS_ONLY TYPE ABAP_BOOL
IV_EC_AGGREGATED TYPE ABAP_BOOL
IV_TEST TYPE CHAR1
IV_TODATE TYPE SYST_DATUM OPTIONAL
IV_VNAME TYPE JV_NAME
IV_YEAR TYPE GJAHR
IV_FRPER TYPE MONAT OPTIONAL (Fiscal Period - From)
IV_FRYEAR TYPE GJAHR OPTIONAL (Fiscal Year - From)
IV_TOPER TYPE MONAT OPTIONAL (Fiscal Period - To)
IV_TOYEAR TYPE GJAHR OPTIONAL (Fiscal Year - To)
IV_ITD TYPE ABAP_BOOL OPTIONAL (Inception to Date)
IV_FARM_IN_OUT TYPE ABAP_BOOL (Indicates if Farm In/Out is running)