

Created on....17.08.2016 Last changed on/by..... 29.06.2026 ABAP7
Author.....ABAP4

Title.....SAP-ASRS SQL Data Push

Type.....1 Reporting

Status.....

Application.....

Class.....

Logical database.....

 from Application....

Selection screen.....

Authorization group...

Package.....ZMM

 Start by Variants

 Deactivate editor lock

X Fixed point arithmetic active

```
1  *&-----*
2  *& Report  ZDEMO_SQL_ASRS_SAP
3  *&
4  *&-----*
5  *&
6  *&
7  *&-----*
8
9  REPORT zmm_sql_asrs_sap_push_cor.
10
11 TABLES: zmm_asrs.
12
13 SELECT-OPTIONS: s_type for zmm_asrs-msg_trans_type.
14
15 DATA: gs_asrs TYPE zmm_asrs,
16        gt_asrs TYPE STANDARD TABLE OF zmm_asrs,
17        gt_con TYPE STANDARD TABLE OF zmm_dbcon_asrs,
18        gs_con TYPE zmm_dbcon_asrs.
19 FIELD-SYMBOLS <fs_asrs> TYPE zmm_asrs.
20 DATA: dbs TYPE dbcon-con_name.
21 DATA: con(20) TYPE c.
22
23
24 START-OF-SELECTION.
25
26     SELECT *
27         FROM zmm_dbcon_asrs
28         INTO TABLE gt_con.
29
30
31     DATA: lv_date TYPE char10.
32     DATA: lv_date1 TYPE char10.
33     DATA: lv_date2 TYPE char10.
34     SELECT *
35         FROM zmm_asrs
36         INTO CORRESPONDING FIELDS OF TABLE gt_asrs
37         WHERE msg_trans_type in s_type
38         AND trf_status = 'N'.
39
40     DATA: exc_ref    TYPE REF TO cx_sy_native_sql_error,
41           error_text TYPE string.
42
43     SORT gt_asrs BY plant.
44     LOOP AT gt_asrs ASSIGNING <fs_asrs>.
45         ON CHANGE OF <fs_asrs>-plant.
46             READ TABLE gt_con INTO gs_con WITH KEY werks = <fs_asrs>-plant.
47             IF sy-subrc <> 0.
48                 CONTINUE.
49             ENDIF.
50             TRY.
51                 IF con IS NOT INITIAL.
52                     EXEC SQL.
53                         DISCONNECT :con
54                     ENDEXEC.
55                 ENDIF.
56                 CLEAR con.
57                 EXEC SQL. "#EC CI_EXECSQL
58                     CONNECT TO :gs_con-DBCON
59                 ENDEXEC.
60                 EXEC SQL. "#EC CI_EXECSQL
61                     GET CONNECTION :CON
```

```
62      ENDEXEC.
63      EXEC SQL.
64          SET CONNECTION :gs_con-DBCON
65      ENDEXEC.
66      CATCH cx_sy_native_sql_error INTO exc_ref.
67  ENDTRY.
68  ENDON.
69  gs_asrs = <fs_asrs>.
70
71  lv_date = gs_asrs-msg_dt_def.
72  IF gs_asrs-msg_dt_trm IS NOT INITIAL.
73      lv_date1 = gs_asrs-msg_dt_trm.
74  ENDIF.
75  IF gs_asrs-mfg_date IS NOT INITIAL.
76      lv_date2 = gs_asrs-mfg_date.
77  ENDIF.
78  TRY.
79      EXEC SQL.
80          INSERT INTO host_to_wms (MSG_SRC,
81                                  MSG_REC_ID,
82                                  MSG_TRANS_TYPE,
83                                  MSG_ACTION,
84                                  MSG_DT_DEF,
85                                  MSG_STAT,
86                                  REQ_ID,
87                                  REQ_TYPE,
88                                  MAT_CODE,
89                                  SAP_BATCH,
90                                  QTY,
91                                  STATUS,
92                                  LINE_ITEM)
93              VALUES (
94                  :gs_asrs-MSG_SRC ,
95                  :gs_asrs-MSG_REC_ID ,
96                  :gs_asrs-MSG_TRANS_TYPE ,
97                  :gs_asrs-MSG_ACTION ,
98                  :lv_date,
99                  :gs_asrs-MSG_STAT ,
100                 :gs_asrs-REQ_ID ,
101                 :gs_asrs-REQ_TYPE ,
102                 :gs_asrs-MAT_CODE ,
103                 :gs_asrs-SAP_BATCH ,
104                 :gs_asrs-QTY ,
105                 :gs_asrs-STATUS ,
106                 :gs_asrs-LINE_ITEM )
107
108      ENDEXEC.
109
110      CATCH cx_sy_native_sql_error INTO exc_ref.
111          error_text = exc_ref->get_text( ).
112
113      CONTINUE.
114  ENDTRY.
115
116  COMMIT WORK AND WAIT .
117
118  * EXEC SQL.
119  * DISCONNECT :con
120  * ENDEXEC.
121  <fs_asrs>-trf_status = 'Y'.
122  ENDLOOP.
123
124  IF con IS NOT INITIAL.
```

```
123      EXEC SQL.  
124          DISCONNECT :con  
125      ENDEXEC.  
126  ENDIF.  
127  MODIFY zmm_asrs FROM TABLE gt_asrs.
```

Title:
SAP-ASRS SQL Data Push

Selection texts:

S_TYPE
D .

DATABASE OPERATIONS

SELECT:

	Line	Page
ZMM_ASRS..... ZMM_SQL_ASRS_SAP_PUSH_COR	35	2
ZMM_DBCON_ASRS..... ZMM_SQL_ASRS_SAP_PUSH_COR	27	2

MODIFY:

	Line	Page
ZMM_ASRS..... ZMM_SQL_ASRS_SAP_PUSH_COR	127	4

INTERNAL TABLE OPERATIONS

READ TABLE:

	Line	Page
GT_CON..... ZMM_SQL_ASRS_SAP_PUSH_COR	46	2
