

Created on....17.08.2016 Last changed on/by..... 29.06.2026 ABAP7
Author.....ABAP4

Title.....SAP-ASRS SQL Data Push

Type.....1 Reporting

Status.....

Application.....

Class.....

Logical database.....

 from Application....

Selection screen.....

Authorization group...

Package.....ZMM

 Start by Variants

 Deactivate editor lock

X Fixed point arithmetic active

```
1  *&-----*
2  *& Report  ZDEMO_SQL_ASRS_SAP
3  *&
4  *&-----*
5  *&
6  *&
7  *&-----*
8
9  REPORT zmm_sql_asrs_sap_push_in.
10
11  TABLES: zmm_asrs.
12
13  SELECT-OPTIONS: s_type for zmm_asrs-msg_trans_type.
14
15  DATA: gs_asrs TYPE zmm_asrs,
16         gt_asrs TYPE STANDARD TABLE OF zmm_asrs,
17         gt_con  TYPE STANDARD TABLE OF zmm_dbcon_asrs,
18         gs_con  TYPE zmm_dbcon_asrs.
19  FIELD-SYMBOLS <fs_asrs> TYPE zmm_asrs.
20  DATA: dbs TYPE dbcon-con_name.
21  DATA: con(20) TYPE c.
22
23
24  START-OF-SELECTION.
25
26      SELECT *
27          FROM zmm_dbcon_asrs
28          INTO TABLE gt_con.
29
30
31
32
33
34
35
36  *WRITE sy-subrc.
37
38
39
40  DATA: lv_date TYPE char10.
41  DATA: lv_date1 TYPE char10.
42  DATA: lv_date2 TYPE char10.
43  SELECT *
44      FROM zmm_asrs
45      INTO CORRESPONDING FIELDS OF TABLE gt_asrs
46      WHERE msg_trans_type in s_type
47      AND trf_status = 'N'.
48  *  lv_date = sy-datum.
49  *  exec SQL.
50  *      SELECT MSG_REC_ID   FROM HOST_TO_WMS_TEST INTO :gs_asrs-msg_rec_id
51  *  ENDEXEC.
52  DATA: exc_ref    TYPE REF TO cx_sy_native_sql_error,
53         error_text TYPE string.
54
55  SORT gt_asrs BY plant.
56  LOOP AT gt_asrs ASSIGNING <fs_asrs>.
57      ON CHANGE OF <fs_asrs>-plant.
58          READ TABLE gt_con INTO gs_con WITH KEY werks = <fs_asrs>-plant.
59          IF sy-subrc <> 0.
60              CONTINUE.
61          ENDIF.
```

```

62      TRY.
63          IF con IS NOT INITIAL.
64              EXEC SQL.
65                  DISCONNECT :con
66              ENDEXEC.
67          ENDIF.
68          CLEAR con.
69          EXEC SQL. "#EC CI_EXECSQL
70              CONNECT TO :gs_con-DBCON
71          ENDEXEC.
72          EXEC SQL. "#EC CI_EXECSQL
73              GET CONNECTION :CON
74          ENDEXEC.
75          EXEC SQL.
76              SET CONNECTION :gs_con-DBCON
77          ENDEXEC.
78          CATCH cx_sy_native_sql_error INTO exc_ref.
79      ENDTRY.
80  ENDON.
81  gs_asrs = <fs_asrs>.
82
83  lv_date = gs_asrs-msg_dt_def.
84  IF gs_asrs-msg_dt_trm IS NOT INITIAL.
85      lv_date1 = gs_asrs-msg_dt_trm.
86  ENDIF.
87  IF gs_asrs-mfg_date IS NOT INITIAL.
88      lv_date2 = gs_asrs-mfg_date.
89  ENDIF.
90  TRY.
91      EXEC SQL.
92          INSERT INTO host_to_wms (MSG_SRC,
93                                  MSG_REC_ID,
94                                  MSG_TRANS_TYPE,
95                                  MSG_ACTION,
96                                  MSG_DT_DEF,
97                                  MSG_STAT,
98                                  GR_NO,
99                                  MAT_CODE,
100                                 SAP_BATCH,
101                                 QTY,
102                                 STATUS,
103                                 TOTAL_PACK,
104                                 MFG_DATE,
105                                 MANUFACTURER,
106                                 MFG_BATCH,
107                                 LINE_ITEM,
108                                 PLANT)
109          VALUES (
110                  :gs_asrs-MSG_SRC ,
111                  :gs_asrs-MSG_REC_ID ,
112                  :gs_asrs-MSG_TRANS_TYPE ,
113                  :gs_asrs-MSG_ACTION ,
114                  :lv_date,
115                  :gs_asrs-MSG_STAT ,
116                  :gs_asrs-GR_NO ,
117                  :gs_asrs-MAT_CODE ,
118                  :gs_asrs-SAP_BATCH ,
119                  :gs_asrs-QTY ,
120                  :gs_asrs-STATUS ,
121                  :gs_asrs-TOTAL_PACK ,
122                  :lv_date2,
                  :gs_asrs-MANUFACTURER ,

```

```
123                                     :gs_asrs-MFG_BATCH ,
124                                     :gs_asrs-LINE_ITEM ,
125                                     :gs_asrs-PLANT)
126     ENDEXEC.
127
128     CATCH cx_sy_native_sql_error INTO exc_ref.
129         error_text = exc_ref->get_text( ).
130
131     CONTINUE.
132 ENDTRY.
133
134     COMMIT WORK AND WAIT .
135
136 * EXEC SQL.
137 *     DISCONNECT :con
138 * ENDEXEC.
139     <fs_asrs>-trf_status = 'Y'.
140 ENDLOOP.
141
142 IF con IS NOT INITIAL.
143     EXEC SQL.
144         DISCONNECT :con
145     ENDEXEC.
146 ENDIF.
147 MODIFY zmm_asrs FROM TABLE gt_asrs.
```

Title:
SAP-ASRS SQL Data Push

Selection texts:

S_TYPE
D .

DATABASE OPERATIONS

SELECT:

	Line	Page
ZMM_ASRS..... ZMM_SQL_ASRS_SAP_PUSH_IN	44	2
ZMM_DBCON_ASRS..... ZMM_SQL_ASRS_SAP_PUSH_IN	27	2

MODIFY:

	Line	Page
ZMM_ASRS..... ZMM_SQL_ASRS_SAP_PUSH_IN	147	4

INTERNAL TABLE OPERATIONS

READ TABLE:

	Line	Page
GT_CON..... ZMM_SQL_ASRS_SAP_PUSH_IN	58	2
