# DARK KNIGHT USER MANUAL

| | |
|---|---|
| **Version:** 1.0 | **Date:** August 03, 2024 |
| **Project Title:** Dark Knight | **Document:** User Manual |

## CONTENT

- 2D Character Dark Knight
- Beam Projectile
- Custom Dark Knight Shader
- Particle Effect Beam Loading
- Particle Effect Dark Trail
- Script  Dark Knight Controller
- Script Beam Shot Controller
- 6 Action Sounds.

## SHADERS

**Custom Dark Knight Shader:** Shader used for set glow and normal map to character, includes dissolve effect for Death Animation.

**Beam Shader:** Shader used for setting glow and color to power ball sprite.

## SCRIPTS

- **DarkKnightController**: Script used to help users to control the animations.
- **Beam Shot:** Script used to set power and direction to Beam attack.

## ¿HOW TO USE?

### Using PREFAB

The simplest way to use this package is by quickly instantiating the predefined Prefab housed in the folder "DarkKnight/Prefabs". There, you will find a Prefab ready to instance on your scene. This package don't have fight mechanics, We consider that each scenario it's different and you need to adapt it to your game.
There is another prefab prepared to use, DarkKnight_Dyeable, you can select the color for the different parts on the sprite renderer, and at last, you can use the Built In Renderer prefab, but I recommend to use URP.

### Controller Script

#### Explanation

**General Settings**

Script with 3 different parts, on General settings you can change the basic movement parameters and use the buttons to test the sort of animations.

**Death Settings**




When you use the Death animation, the character explodes, in the first part of this settings you can change the prefab for the effect, point used to calculate explosión vectors, explosion power and the HDR Color of the dissolve effect. Destroy GameObject will delete de GameObject when Death animation is over.

**Fight Settings**




In the second part, you can change the amount of distance when the character attacks or does a back step and the Beam Attack prefab.

Exist  prepared events  when the character Death, when the Beam attack is completely charged and when the character hurt event is fired.

In the last part, you can personalize the sounds and the audio source.




| Shader Power Ball | |
|---|---|
| **Parameters** | |
| Color | Base Color of Dark Ball |
| Light Color | Color for light over the base color |
| Light Opacity | Light power blend. |

| Shader Dark Knight | | |
|---|---|---|
| **Parameters** | | |
| **Property** | **Type** | **Description** |
| Glow | HDR Color | **Change it from Dark Controller Script** |
| Emission | Texture 2D | For Glow Eye Color (Config) |
| Normal Map | Texture 2D | For 2D Lights (Config) |
| Magenta PNG | Texture 2D | Texture for calculate Alpha (Config) |
| Dissolve Status | Float | % Dissolve, From 1 to 0 |
| Dissolve Color | HDR Color | Dissolve Color |
| **You can use this VFX for other Sprites ;D** | | |

| | |
|---|---|
| | https://discord.gg/DPWHUP7vWA |

# TUTORIAL

**What do we need?**

- A platform map or Scene
- Some Script for controlling the AI Character.

**How to Start: Using a Prefab**

**Step 1: Instantiate the prefab.**

**Step 2: You can use the interface to communicate your scripts with the controller to activate animations, the methods of the controller animation script are públics.**

## Running Details

### Movement

The movement is controlled with methods of velocity.

**ActivateIdle**. The character target speed becomes 0, and the speed starts reducing till this point.

**ActivateWalk**. The character target speed becomes  the **MaxWalkSpeed** parameter, and the speed starts changing to the configured point. The Animator starts “Walk”.

**ActivateRun**.  Same stuff as "Walk", but the animation goes to “Run” and use **MaxRunSpeed**.

**Flip**. The character changes x transform scale to -1 and the character direction changes. The speed becomes 0.

## Fighting

**Guard State.** The guard state can activate when the character stays in Idle state.

From Guard State you can use 2 actions, Attack and Back Step.

## Beam Attack

Beam Attack can activate on Guard or on Idle state. You can configure the color, direction and power on the script of DarkBall prefab and be free to change the color particles to change the attack like you love it.

If you want to change time to power charging, you can go to Beam Attack coroutine and update the wait seconds.