

NAME

mbm_tmap – Macro to convert XYZ point clouds to 3D Tiles and generate a Cesium viewer.

VERSION

Version 5.0

SYNOPSIS

mbm_tmap -I*pointcloud.xyz* [-**O***tiles_dir*] [-**P***port*] [--**serve-only** | --**no-convert**] [-**N**] [-**S**] [-**W**] [-**V**] [-**H**]

DESCRIPTION

mbm_tmap is a macro that automates point cloud web visualization setup. It runs **py3dtiles convert** on an input XYZ point cloud file, writes an **index.html** Cesium viewer file into the output tiles directory, and can optionally start a local HTTP server using **python -m http.server**.

By default **mbm_tmap** performs conversion from XYZ input. If --**serve-only** (or --**no-convert**) is specified, conversion is skipped and an existing tiles directory is served directly.

This macro is intended for quick local testing and browsing of tiled point cloud data products.

MB-SYSTEM AUTHORSHIP

David W. Caress
Monterey Bay Aquarium Research Institute
Dale N. Chayes
Center for Coastal and Ocean Mapping
University of New Hampshire
Christian do Santos Ferreira
MARUM - Center for Marine Environmental Sciences
University of Bremen

OPTIONS

-**I** *pointcloud.xyz*
Input XYZ point cloud file. This option is required unless --**serve-only** or --**no-convert** is specified.

-**O** *tiles_dir*
Output directory for 3D Tiles and generated **index.html**. Default is **tiles**.

-**P** *port*
HTTP server port used when starting **python -m http.server**. Default is **8000**.

--**serve-only**, --**no-convert**
Skip **py3dtiles** conversion and serve an existing tiles directory. In this mode -**O** should point to an existing tiles directory. If **index.html** already exists it is reused.

-**N**
Do not open a browser automatically.

-**S**
Do not start a local HTTP server.

- W** Wait on the server process after starting it. Use Ctrl+C to stop.
- V** Verbose output.
- H** Print help message and exit.

EXAMPLES

Convert an XYZ file to tiles and start local server:

mbm_tmap -I cloud.xyz -O tiles -V

Serve an existing tiles directory without reconversion:

mbm_tmap --serve-only -O tiles -P 8081 -W -V

Convert an XYZ file to tiles without starting server:

mbm_tmap -I cloud.xyz -O tiles -S

Start server and keep the macro attached to server lifetime:

mbm_tmap -I cloud.xyz -O tiles -W

SEE ALSO

mbgrd2gltf(1), **mbsystem(1)**

BUGS

No known bugs.