

WIC API Authorization

[WHINT Integration Cockpit](#)

[Create DataSource](#)

[Create Access Token](#)

[Usage of the Token](#)

WHINT Integration Cockpit [🔗](#)

Create DataSource [🔗](#)

Go to **Settings** → **Connectivity** → **Data Sources** and click on the “+” on the top right.

In the pop up choose a **Name**, select “API” as **type** and select the **category** for the data source.

Create Data Source

Name

WHINTIC API

Type

API

▼

Category

DEVELOPMENT

▼

Cancel

Save

After saving, the new datasource will open.

Create Access Token [🔗](#)

In the newly created data source, you can choose the type of authentication

Authentication

Type

✓ ACESSTOKEN

APIKEY

BASICAUTH

OAuth2

We choose **ACESSTOKEN** for this example.

After selecting the type of authentication, go to **Tokens** and create a new token by selecting the “+” on the top right of the section.

Tokens			+	-
☐ Name	Token	Expires		
☐ default	MJ7ymPBnyaxW3hKwSWgFd1975pjtec3PV7aLOR_GjwEBuPrs3geailwdgjejIFtuGCR5xH3dw0uE3	2025-11-18T08:03:27Z		

A new token will be created and shown in the table.

After creating the token, click on Save on the bottom of the page to save the Data Source configuration and the token.

Usage of the Token [↗](#)

The token can be used as Bearer token.

Example form Postman:

Auth Type: Bearer Token

Token: *Access token from the created Data Source*

WHINT Integration Cockpit API

Overview

Authorization ●

Scripts

Variables

Runs

This authorization method will be used for every request in this collection. You can override this by specifying one in the request.

Auth Type

Bearer Token ▼

The authorization header will be automatically generated when you send the request.
Learn more about [Bearer Token](#) authorization.

Token

MJ7ymPBnyaxW3hKwSWgFd197Spjte
c3PV7aL0R_GjwE8uPrs3geailwdgi6jIF
tuGCR5xH3dw0uEJWYgl_Mws5NcLw
PX_vSLZm4dYK-
UgnL9OBk9S1ekYz9ZDT0AOxvtLLqK
xq0dh0CXeGRHrgzzhwdSbU3EkCzLr
eZ3NtgQ6Fo