





```

Terminal
R1 x R2 x VPC-4 x VPC-1 x VPC-2 x Win x
Router(dhcp-config)#network 192.168.2.0 255.255.255.0
Router(dhcp-config)#default-router 192.168.2.1
Router(dhcp-config)#dns-server 50.0.0.30
Router(dhcp-config)#lease 1 2 3
Router(dhcp-config)#exit
Router(config)#ip dhcp excluded-address 192.168.2.1 192.168.2.50
Router(config)#do wr
Building configuration...
[OK]
Router(config)#
Router(config)#
Router(config)#
Router(config)#do sh ip dhcp binding
Bindings from all pools not associated with VRF:
IP address      Client-ID/      Lease expiration    Type
                Hardware address/
                User name
50.0.0.51        0100.5079.6668.0c  Sep 02 2026 08:10 PM Automatic
50.0.0.52        0100.5079.6668.0d  Sep 02 2026 08:11 PM Automatic
192.168.2.51     0150.ae34.0911.00  Sep 02 2026 08:08 PM Automatic
192.168.2.52     0100.5079.6668.0e  Sep 02 2026 08:12 PM Automatic
Router(config)#
  
```



```
Terminal
R1 x R2 x VPC-4 x VPC-1 x VPC-2 x Win x
Welcome to Virtual PC Simulator, version 1.3 (0.0.1)
Dedicated to Daling.
Build time: May 7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.


VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC-4>
VPC-4> ip dhcp
ODORA IP 192.168.2.52/24 GW 192.168.2.1

VPC-4>
```



```
Terminal
R1 x R2 x VPC-4 x VPC-1 x VPC-2 x Win x
Welcome to Virtual PC Simulator, version 1.3 (0.8.1)
Dedicated to Daling.
Build time: May 7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.


VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file


VPC-2>
VPC-2> ip dhcp
DDORA IP 50.0.0.52/8 GW 50.0.0.1

VPC-2>
```



```
Terminal
R1 x R2 x VPC-4 x VPC-1 x VPC-2 x Win x
Default IPv4 mask is /24, IPv6 is /64. Example:
ip 10.1.1.70/26 10.1.1.65 set the VPC's ip to 10.1.1.70,
the gateway to 10.1.1.65, the netmask to 255.255.255.192.
In tap mode, the ip of the tapx is the maximum host ID
of the subnet. In the example above the tapx ip would be
10.1.1.126
mask may be written as /26, 26 or 255.255.255.192
auto Attempt to obtain IPv6 address, mask and gateway using SLAAC
dhcp [OPTION] Attempt to obtain IPv4 address, mask, gateway, DNS via DHCP
-d Show DHCP packet decode
-r Renew DHCP lease
-x Release DHCP lease
dns ip Set DNS server ip, delete if ip is '0'
dns6 ipv6 Set DNS server ipv6, delete if ipv6 is '0'
domain NAME Set local domain name to NAME


VPC-1>
VPC-1>
172 VPC-1> ip dhcp
DDORA IP 50.0.0.51/8 GW 50.0.0.1
VPC-1> █
```

```

Terminal
R1 x R2 x VPC-4 x VPC-1 x VPC-2 x Win x
Router#w
*Sep 1 12:30:20.564: %SYS-5-CONFIG_I: Configured from console by console
Router#wr
Building configuration...
[OK]
Router#ip dhcp pool hr
^
% Invalid input detected at '^' marker.

Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip dhcp pool hr
Router(dhcp-config)#network 192.168.2.0 255.255.255.0
Router(dhcp-config)#default-router 192.168.2.1
Router(dhcp-config)#dns-server 50.0.0.30
Router(dhcp-config)#lease 1 2 3
Router(dhcp-config)#exit
Router(config)#ip dhcp excluded-address 192.168.2.1 192.168.2.50
Router(config)#do wr
Building configuration...
[OK]
Router(config)#
  
```



```

Terminal
R1 x R2 x VPC-4 x VPC-1 x VPC-2 x Win x
*Sep  1 12:25:22.639: %LINK-3-UPDOWN: Interface Ethernet0/1, changed state to up
*Sep  1 12:25:23.640: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/1,
state to up
Router(config-if)#no shut
Router(config-if)#do sh i
*Sep  1 12:25:30.056: %LINK-3-UPDOWN: Interface Ethernet0/0, changed state to up
*Sep  1 12:25:31.056: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/0,
state to up
Router(config-if)#do sh ip int brief
Interface                                IP-Address      OK? Method Status      Protoc
Ethernet0/0                              192.168.2.1     YES manual up          up
Ethernet0/1                              172.16.0.2     YES manual up          up
Ethernet0/2                              unassigned      YES unset  administratively down down
Ethernet0/3                              unassigned      YES unset  administratively down down
Router(config-if)#ip route 50.0.0.0 255.0.0.0 172.16.0.1
Router(config)#int e0/0
Router(config-if)#ip helper-address 172.16.0.1
Router(config-if)#exit
17 Router(config)#do wr
Building configuration...
[OK]
Router(config)#
  
```