Extractext

1. Importing Libraries

```
```python
import fitz # PyMuPDF
```

This line imports the fitz module, which is part of the PyMuPDF library.
 PyMuPDF is a powerful library for working with PDF files. You'll need to install it if you haven't already: pip install pymupdf

## 2. Defining the Extraction Function

```
def extract_text_from_pdf(pdf_path):
 doc = fitz.open(pdf_path)
 text = "\n".join([page.get_text() for page in doc])
 return text
```

- def extract\_text\_from\_pdf(pdf\_path): This defines a function named extract\_text\_from\_pdf
   that takes one argument:
  - pdf\_path: The file path to the PDF file you want to extract text from.
- doc = fitz.open(pdf\_path): This line opens the PDF file specified by pdf\_path using fitz.open(). The opened PDF document is stored in the doc variable.
- text = "\n".join([page.get\_text() for page in doc]): This is the core of the text extraction.
   Let's break it down:
  - o [page.get\_text() for page in doc]: This is a list comprehension. It iterates through each page in the doc (the PDF document). For each page, it calls the page.get\_text() method to extract the text content of that page. This creates a list where each element is the text from a single page.
  - o "\n".join(...): The join() method takes the list of strings (the page texts) and concatenates them into a single string. "\n" specifies that the pages' text

Extractext 1

- should be joined with a newline character (n) in between them. This preserves the page breaks and formatting to some extent.
- return text: The function returns the complete extracted text as a single string.

## 3. Example Usage

pdf\_text = extract\_text\_from\_pdf("/Users/vinod/Desktop/mike/sample.pdf")
print(pdf\_text[:500]) # Print first 500 characters

- pdf\_text = extract\_text\_from\_pdf("/Users/vinod/Desktop/mike/sample.pdf"): This line calls the extract\_text\_from\_pdf function, passing the path to your PDF file. Important:

  Replace "/Users/vinod/Desktop/mike/sample.pdf" with the actual path to your PDF file.

  The returned text is stored in the pdf\_text variable.
- print(pdf\_text[:500]): This line prints the first 500 characters of the extracted text. This is useful for quickly previewing the extracted content. You can remove the [:500] to print the entire text.

This code provides a clean and efficient way to extract text from PDFs using PyMuPDF. Remember to install the library and replace the placeholder PDF path with your actual file path.

Extractext 2