Package 'DrillR'

October 12, 2022

Type Package		
Title R Driver for Apache Drill		
Version 0.1		
Date 2016-06-28		
Author Hanbing Yang		
Depends R (>= $3.0.2$)		
Imports httr,methods		
Maintainer Hanbing Yang Hanbing Yang <a drill.apache.org"="" href="maintai</td></tr><tr><td>Description Provides a R driver for Apache Drillhttps://drill.apache.org, which could connect to the Apache Drill clusterhttps://drill.apache.org/docs/installing-drill-on-the-cluster or drill-bithttps://drill.apache.org/docs/embedded-mode-prerequisites and get result(in data frame) from the SQL query and check the current configuration status. This link https://drill.apache.org/docs contains more information about Apache Drill.		
License GPL		
RoxygenNote 5.0.1		
NeedsCompilation no		
Repository CRAN		
Date/Publication 2016-06-29 15:57:26		
R topics documented:		
drill-class 2 rdrill 2 rd_active 3 rd_metrics 3 rd_options 4 rd_profiles 4 rd_query 5 rd_stats 5		

2 rdrill

Index 7

drill-class

Class drill defines a Apache Drill driver class.

Description

Class drill defines a Apache Drill driver class.

Slots

```
host A string denoting the Apache Drill cluster/node host port A numeric denoting the Apache Drill cluster/node port
```

rdrill

Get the Apache Drill Connection, return the RDrill object.

Description

Get the Apache Drill Connection, return the RDrill object.

Usage

```
rdrill(host, port)
## S4 method for signature 'character,numeric'
rdrill(host, port)
```

Arguments

host Apache Drill cluster/node host
port Apache Drill cluster/node port

```
rdrill("127.0.0.1",8047)
```

rd_active 3

rd_active

To show whether the connection is active.

Description

To show whether the connection is active.

Usage

```
rd_active(object)
## S4 method for signature 'drill'
rd_active(object)
```

Arguments

object

the RDrill object

Examples

```
\#rd_active(R_DRILL_OBJECT) \#please replace 'R_DRILL_OBJECT' with your RDrill object.
```

rd_metrics

Show the information of the memory metrics.

Description

Show the information of the memory metrics.

Usage

```
rd_metrics(object)
## S4 method for signature 'drill'
rd_metrics(object)
```

Arguments

object

the RDrill object

```
\verb| \#rd_metrics(R_DRILL_OBJECT) | \#please replace 'R_DRILL_OBJECT' with your RDrill object.
```

rd_profiles

rd_options	Show the information of the system and session options such as name and data type and so forth.

Description

Show the information of the system and session options such as name and data type and so forth.

Usage

```
rd_options(object)
## S4 method for signature 'drill'
rd_options(object)
```

Arguments

object

the RDrill object

Examples

```
#rd_options(R_DRILL_OBJECT) #please replace 'R_DRILL_OBJECT' with your RDrill object.
```

rd_profiles

Show the information about the running and completed queries.

Description

Show the information about the running and completed queries.

Usage

```
rd_profiles(object)
## S4 method for signature 'drill'
rd_profiles(object)
```

Arguments

object

the RDrill object

```
\verb| #rd_profiles(R_DRILL_OBJECT) | \verb| #please replace 'R_DRILL_OBJECT' with your RDrill object. |
```

rd_query 5

rd_query

Submit a SQL query and return results as a data frame.

Description

Submit a SQL query and return results as a data frame.

Usage

```
rd_query(object, sql)
## S4 method for signature 'drill'
rd_query(object, sql)
```

Arguments

object the RDrill object sql the query submitted

Examples

 $\#rd_query(R_DRILL_OBJECT, SQL_QUERY)$ $\#please\ replace\ 'R_DRILL_OBJECT'\ with\ your\ RDrill\ object.$

rd_stats

Show the information of Drillbits, their ports and hosts.

Description

Show the information of Drillbits, their ports and hosts.

Usage

```
rd_stats(object)
## S4 method for signature 'drill'
rd_stats(object)
```

Arguments

object the RDrill object

```
#rd_stats(R_DRILL_OBJECT) #please replace 'R_DRILL_OBJECT' with your RDrill object.
```

6 rd_threads

rd_storages

Show the configurations of the storage plugins.

Description

Show the configurations of the storage plugins.

Usage

```
rd_storages(object)
## S4 method for signature 'drill'
rd_storages(object)
```

Arguments

object

the RDrill object

Examples

```
\#rd\_storages(R\_DRILL\_OBJECT) \#please replace 'R\_DRILL\_OBJECT' with your RDrill object.
```

rd_threads

Show the information of the threads status.

Description

Show the information of the threads status.

Usage

```
rd_threads(object)
## S4 method for signature 'drill'
rd_threads(object)
```

Arguments

object

the RDrill object

```
\#rd\_threads(R\_DRILL\_OBJECT) \#please replace 'R\_DRILL\_OBJECT' with your RDrill object.
```

Index

```
* RDrillClass
    rdrill, 2
* \ RDrill Generic \\
    rd_active, 3
    rd_metrics, 3
    rd_options, 4
    rd_profiles, 4
    rd_query, 5
    rd_stats, 5
    rd_storages, 6
    rd_threads, 6
drill-class, 2
rd_active, 3
rd_active, drill-method (rd_active), 3
rd_metrics, 3
rd_metrics, drill-method (rd_metrics), 3
rd_options, 4
rd_options,drill-method(rd_options), 4
rd_profiles, 4
rd_profiles,drill-method(rd_profiles),
        4
rd_query, 5
rd_query,drill-method(rd_query),5
rd_stats, 5
rd_stats,drill-method(rd_stats),5
rd_storages, 6
rd_storages,drill-method(rd_storages),
        6
rd_threads, 6
rd_threads, drill-method (rd_threads), 6
rdrill, 2
rdrill, character, numeric-method
        (rdrill), 2
```