What is the machine code for the following instructions:

```
ADD x16, x0, x0
ADDI x2, x1, -16
LHU, x4, x3, -4
JALR x0, 8(x1)
```

Response

The machine code for the following instructions are:

```
What is the machine code for the following JAL instruction:
```

```
X100 jal x0, Loop
...
X200 Loop:
```

Response

The machine code for the following JAL instruction is:

0 0000000000 0 1100100 00001 1101111

Translate the following machine codes into RISC-V assembly language (numbers are in hex).

fe1ff06f 0000c133

Response

The instruction fe1ff06f translates to: 1111 1110 0001 1111 1111 0000 0110 1111 which, when rearranged, yields: 1 11111100001 1 1111111 00000 1101111 which is a J-type, so we get: 1 1111111 1 111111100001 00000 1101111 (imm[20|10:1|11|19:12]) or: jal -31(x0)

The instruction 0000c133 translates to: $0000\ 0000\ 0000\ 0000\ 1100\ 0001\ 0011\ 0011$ which, when rearranged, yields: $0000000\ 00000\ 00001\ 100\ 00010\ 0110011$ which is:

xor x2 x0 in RISC-V assembly.

Write a RISC-V assembly language program for determining if a number is even or not.

Use the following information in writing your assembly code.

- 1. The function starts at memory location 0x400. Each instruction is 32 bits, thus the second instruction should start at 0x404, and so on. Use this information to correctly compute the offset for jump and branch instructions (you are not allowed to use labels).
- 2. The input is passed (stored) in register a0.
- 3. The return value, c, should be stored in a0.
- 4. The return address is tored in ra.
- 5. You are free to use saved and temporary registers (don't forget to save values if you are using saved registers).
- 6. You are allowed to use Pseudoinstructions (e.g. ret, call, etc.)

```
addi t0, a0, 0
addi t0, t0, -2
blt zero, t0, -4
sub a0, a0, a0
blt zero, t0, 8
addi t0, t0, 2
xor a0, a0, t0
xori a0, a0, 1
```